



One Identity Manager 8.0.1

CSV Connector User Guide

## Copyright 2018 One Identity LLC.

### ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC .

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity make no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity do not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.  
Attn: LEGAL Dept  
4 Polaris Way  
Aliso Viejo, CA 92656

Refer to our Web site (<http://www.OneIdentity.com>) for regional and international office information.

### Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

### Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at [www.OneIdentity.com/legal](http://www.OneIdentity.com/legal). All other trademarks are the property of their respective owners.

### Legend

-  **WARNING:** A WARNING icon indicates a potential for property damage, personal injury, or death.
-  **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.
-  **IMPORTANT, NOTE, TIP, MOBILE, or VIDEO:** An information icon indicates supporting information.

# Contents

<b>Setting up Synchronization with the CSV Connector</b> .....	<b>4</b>
Users and Permissions for Synchronizing .....	5
Setting Up a Custom Application Role for Synchronization .....	8
Setting Up the Synchronization Server .....	10
Creating a Synchronization Project .....	13
How to Set up a Synchronization Project .....	15
Customizing the CSV System File .....	19
How to Edit a CSV File Schema .....	20
How to remove a CSV file from the System Connection .....	23
How to Change the Path to the CSV System File .....	23
Updating Schemas .....	24
Starting Synchronization .....	25
Analyzing Synchronization .....	25
Post-Processing Outstanding Objects .....	26
Configuring Target System Synchronization .....	26
How to Post-Process Outstanding Objects .....	28
Configuring Memberships Provisioning .....	29
<b>Troubleshooting</b> .....	<b>31</b>
Help for Analyzing Synchronization Issues .....	31
<b>About us</b> .....	<b>32</b>
Contacting us .....	32
Technical support resources .....	32
<b>Index</b> .....	<b>33</b>

# Setting up Synchronization with the CSV Connector

The CSV connector can transfer data between CSV files and the One Identity Manager database. The CSV connector has read/write-access. You can use CSV files to synchronize target systems with the One Identity Manager database without a direct connection existing between the target system and the One Identity Manager database. For example, the CSV connector can be used to import employee data into the One Identity Manager database.

The data to synchronize must be in a fixed data structure. The data can be distributed between several CSV files. The synchronization server must be able to access the CSV files and the CSV system file directly.

**NOTE:** The CSV connector does not provide a project template for setting up synchronization. You must create synchronization configuration components (mappings, workflows, start up configurations,...) manually after the synchronization project has been saved.

## **To set up synchronization with a CSV file**

1. Install and configure a synchronization server and declare the server as Job server in One Identity Manager.
2. Provide One Identity Manager users with the required permissions for setting up synchronization and post-processing of synchronization objects.
3. Create a synchronization project with the Synchronization Editor.

## **Detailed information about this topic**

- [Setting Up the Synchronization Server](#) on page 10
- [Users and Permissions for Synchronizing](#) on page 5
- [Creating a Synchronization Project](#) on page 13

# Users and Permissions for Synchronizing

In the synchronization process, there are three use cases for mapping synchronization objects in the One Identity Manager data model with the CSV connector.

1. Mapping custom target systems
2. Mapping default tables (for example Person, Department)
3. Mapping custom tables

In the case of non role-based log in on One Identity Manager tools, it is sufficient to add one system user in the permissions group "DPR\_EditRights\_Methods". For more detailed information about system users and permissions groups, see the One Identity Manager Configuration Guide.

**Table 1: Users and Permissions Groups for Non Role-Based Login**

User	Task
One Identity Manager administrators	<ul style="list-style-type: none"><li>• Create customized permissions groups for application roles for role-based login to administration tools in the Designer, as required.</li><li>• Create system users and permissions groups for non-role based login to administration tools, as required.</li><li>• Enable or disable additional configuration parameters in the Designer, as required.</li><li>• Create custom processes in the Designer, as required.</li><li>• Create and configures schedules, as required.</li><li>• Create and configure password policies, as required.</li></ul>
System users in the permissions group "DPR_EditRights_Methods"	<ul style="list-style-type: none"><li>• Configure and start synchronization in the Synchronization Editor.</li><li>• Edit the synchronization's target system types as well as outstanding objects in the Manager.</li></ul>

There are different steps required for role-based login, in order to equip One Identity Manager users with the required permissions for setting up synchronization and post-processing of synchronization objects.

**Table 2: User and permissions groups for role-based login: Mapped as custom target system**

User	Task
One Identity Manager	<ul style="list-style-type: none"><li>• Create customized permissions groups for application</li></ul>

User	Task
administrators	<p>roles for role-based login to administration tools in the Designer, as required.</p> <ul style="list-style-type: none"> <li>• Create system users and permissions groups for non-role based login to administration tools, as required.</li> <li>• Enable or disable additional configuration parameters in the Designer, as required.</li> <li>• Create custom processes in the Designer, as required.</li> <li>• Create and configures schedules, as required.</li> <li>• Create and configure password policies, as required.</li> </ul>
Target system administrators	<p>Target system administrators must be assigned to the application role <b>Target system   Administrators</b>.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> <li>• Administrate application roles for individual target systems types.</li> <li>• Specify the target system manager.</li> <li>• Set up other application roles for target system managers if required.</li> <li>• Specify which application roles are conflicting for target system managers</li> <li>• Authorize other employee to be target system administrators.</li> <li>• Do not assume any administrative tasks within the target system.</li> </ul>
Target system managers	<p>Target system managers must be assigned to the application role <b>Target systems   Custom target systems</b> or a sub application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> <li>• Assume administrative tasks for the target system.</li> <li>• Create, change or delete target system objects, like user accounts or groups.</li> <li>• Edit password policies for the target system.</li> <li>• Prepare groups for adding to the IT Shop.</li> <li>• Configure synchronization in the Synchronization Editor and defines the mapping for comparing target systems and One Identity Manager.</li> <li>• Edit the synchronization's target system types and</li> </ul>

User	Task
	<p>outstanding objects.</p> <ul style="list-style-type: none"> <li>• Authorize other employees within their area of responsibility as target system managers and create child application roles if required.</li> </ul>

**Table 3: User and permissions groups for role-based login: Mapped as default tables**

User	Task
One Identity Manager administrators	<ul style="list-style-type: none"> <li>• Create customized permissions groups for application roles for role-based login to administration tools in the Designer, as required.</li> <li>• Create system users and permissions groups for non-role based login to administration tools, as required.</li> <li>• Enable or disable additional configuration parameters in the Designer, as required.</li> <li>• Create custom processes in the Designer, as required.</li> <li>• Create and configures schedules, as required.</li> <li>• Create and configure password policies, as required.</li> </ul>
Custom application role	<p>Users with this application role:</p> <ul style="list-style-type: none"> <li>• Configure and start synchronization in the Synchronization Editor.</li> <li>• Edit the synchronization's target system types as well as outstanding objects in the Manager.</li> </ul> <p>This application role gets its write access through a custom permissions group and the permissions group "vi_4_SYNCPROJECT_ADMIN".</p>

**Table 4: Users and permissions groups for role-based login: Mapped in custom tables**

User	Task
One Identity Manager administrators	<ul style="list-style-type: none"> <li>• Create customized permissions groups for application roles for role-based login to administration tools in the Designer, as required.</li> <li>• Create system users and permissions groups for non-role based login to administration tools, as required.</li> <li>• Enable or disable additional configuration parameters in the Designer, as required.</li> <li>• Create custom processes in the Designer, as required.</li> </ul>

User	Task
	<ul style="list-style-type: none"> <li>• Create and configures schedules, as required.</li> <li>• Create and configure password policies, as required.</li> </ul>
Application roles for custom tasks	<p>Administrators must be assigned to the application role <b>Custom   Administrators</b>.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> <li>• Administrate custom application roles.</li> <li>• Set up other application roles for managers, if required.</li> </ul>
Manager for custom tasks	<p>Managers must be assigned to the application role <b>Custom   Managers</b> or a subordinate role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> <li>• Add custom task in the One Identity Manager.</li> <li>• Configure and start synchronization in the Synchronization Editor.</li> <li>• Edit the synchronization's target system types as well as outstanding objects in the Manager.</li> </ul> <p>This application role gets its write access through a custom permissions group and the permissions group "vi_4_SYNCPROJECT_ADMIN".</p>

***To configure synchronization projects and target system synchronization (in the use cases 2 and 3)***

1. Set up a custom permissions group with all permissions for configuring synchronization and editing synchronization objects.
2. Assign a custom application role to this permission group.

**Detailed information about this topic**

- [Setting Up a Custom Application Role for Synchronization](#) on page 8

## Setting Up a Custom Application Role for Synchronization

For role-based login, create a custom application role to guarantee One Identity Manager users the necessary permissions for configuring synchronization and handling outstanding objects. This application role obtains the required permissions by using a custom permissions group.



### ***To set up an application role (use case 2)***

1. Select the default application role to use to edit the objects you want to synchronization in the Manager.

- Establish the application role's default permissions group.

If you want to import employee data, for example, select the application role **Identity Management | Employees | Administrators**. The default permissions group is "vi\_4\_PERSONADMIN".

2. Create a new permissions group in the Designer.

- Set the option **Only use for role based authentication**.

3. Make the new permissions group dependent on the permission group "vi\_4\_SYNCPROJECT\_ADMIN".

The permissions "vi\_4\_SYNCPROJECT\_ADMIN" must be assigned as parent permissions group. This means that the new permissions group inherits the properties.

4. Make the new permissions group dependent on the default permission group of the selected default application role.

The default permissions group must be assigned as a subgroup. This means that the new permissions group inherits the properties.

5. Save the changes.

6. Create a new application role in the Manager.

- a. Assign the selected application role to be the parent application role.
- b. Assign the newly created permissions group to it

7. Assign employees to this application role.

8. Save the changes.

### ***To set up an application role for synchronization (use case 3)***

1. Create a new permissions group for custom tables, which are populated though synchronization, in the Designer.

- Set the option **Only use for role based authentication**.

2. Guarantee this permissions group all the required permissions to the custom tables.

3. Create another permissions group for synchronization.

- Set the option **Only use for role based authentication**.

4. Make the permissions group for synchronization dependent on the permissions group for custom tables.

The permissions group for custom tables must be assigned as parent permissions group. This means the permissions groups for synchronization inherits its properties.

5. Make the permissions group for synchronization dependent on the permissions group "vi\_4\_SYNCPROJECT\_ADMIN".

The permissions "vi\_4\_SYNCPROJECT\_ADMIN" must be assigned as parent permissions group. This means the permissions groups for synchronization inherits its properties.

6. Save the changes.
7. Create a new application role in the Manager.
  - a. Assign the application role **Custom | Managers** as parent application role.
  - b. Assign the permissions group for synchronization.
8. Assign employees to this application role.
9. Save the changes.

For more detailed information about setting up application roles, see the One Identity Manager Application Roles Administration Guide. For more detailed information about permissions groups, see the One Identity Manager Configuration Guide.

## Setting Up the Synchronization Server

A server with the following software must be available for setting up synchronization:

- One Identity Manager Service
  - Install One Identity Manager components with the installation wizard.
    1. Select the option **Select installation modules with existing database**.
    2. Select the machine role **Server | Job server**.

For more detailed information about system requirements for installing the One Identity Manager Service, see the One Identity Manager Installation Guide.

The synchronization server must be declared as a Job server in One Identity Manager.

Use the Server Installer to install the One Identity Manager Service. This program executes the following steps.

- Setting up a Job server.
- Specifying machine roles and server function for the Job server.
- Remote installation of One Identity Manager Service components corresponding to the machine roles.
- Configures the One Identity Manager Service.
- Starts the One Identity Manager Service.

**NOTE:** The program executes remote installation of the One Identity Manager Service. Local installation of the service is not possible with this program. Remote installation is only supported within a domain or a trusted domain.

## To install and configure the One Identity Manager Service remotely on a server

1. Start the program Server Installer on your administrative workstation.
2. Enter valid data for connecting to One Identity Manager on the **Database connection** page and click **Next**.
3. Specify on which server you want to install the One Identity Manager Service on the **Server properties** page.
  - a. Select a job server in the **Server** menu.  
- OR -  
Click **Add** to add a new job server.
  - b. Enter the following data for the Job server.

**Table 5: Job Servers Properties**

Property	Description
Server	Name of the Job servers.
Queue	Name of queue to handle the process steps. Each One Identity Manager Service within the network must have a unique queue identifier. The process steps are requested by the job queue using exactly this queue name. The queue identifier is entered in the One Identity Manager Service configuration file.
Full server name	Full name of the server in DNS syntax. Example: <name of server>.<fully qualified domain name>

**NOTE:** Use the **Advanced** option to edit other Job server properties. You can use the Designer to change properties at a later date.

4. Specify which job server roles to include in One Identity Manager on the **Machine role** page. Installation packages to be installed on the Job server are found depending on the selected machine role.  
Select at least the following roles:
  - Job Server
5. Specify the server's functions in One Identity Manager on the **Server functions** page. One Identity Manager processes are handled depending on the server function. The server's functions depend on which machine roles you have selected. You can limit the server's functionality further here.  
Select at least one of the following server functions:
  - CSV connector
6. Check the One Identity Manager Service configuration on the **Service settings** page.

**NOTE:** The initial service configuration is already predefined. If further changes need to be made to the configuration, you can do this later with the Designer. For more detailed information about configuring the service, see One Identity Manager Configuration Guide.

7. To configure remote installations, click **Next**.
8. Confirm the security prompt with **Yes**.
9. Select the directory with the install files on the **Select installation source** page.
10. Select the file with the private key on the page **Select private key file**.

**NOTE:** This page is only displayed when the database is encrypted.

11. Enter the service's installation data on the **Service access** page.

**Table 6: Installation Data**

<b>Data</b>	<b>Description</b>
Computer	<p>Server on which to install and start the service from.</p> <p><b>To select a server</b></p> <ul style="list-style-type: none"> <li>• Enter the server name.</li> <li>- OR -</li> <li>• Select a entry from the list.</li> </ul>
Service account	<p>One Identity Manager Service user account data.</p> <p><b>To enter a user account for the One Identity Manager Service</b></p> <ul style="list-style-type: none"> <li>• Set the option <b>Local system account</b>. This starts the One Identity Manager Service under the account "NT AUTHORITY\SYSTEM".</li> <li>- OR -</li> <li>• Enter user account, password and password confirmation. The One Identity Manager Service farm's server farm account must be used as user account for SharePoint.</li> </ul>
Installation account	<p>Data for the administrative user account to install the service.</p> <p><b>To enter an administrative user account for installation</b></p> <p><b>Enable Advanced</b></p> <ul style="list-style-type: none"> <li>• .</li> <li>• Enable the option <b>Current user</b>. This uses the user account of the current user.</li> </ul>

Data	Description
	- OR -
	<ul style="list-style-type: none"> <li>• Enter user account, password and password confirmation.</li> </ul>
	12. Click <b>Next</b> to start installing the service.
	Installation of the service occurs automatically and may take some time.
	13. Click <b>Finish</b> on the last page of the Server Installer.
	<p><b>NOTE:</b> The is entered with the name "One Identity Manager Service" in the server's service administration.</p>

## Creating a Synchronization Project

A synchronization project collects all the information required for synchronizing the One Identity Manager database with a target system. Connection data for target systems, schema types and properties, mapping and synchronization workflows all belong to this.

Have the following information available for setting up a synchronization project.

**Table 7: Information Required for Setting up a Synchronization Project**

Data	Explanation
Synchronization server	<p>All One Identity Manager Service actions are executed against the target system environment on the synchronization server. Data entries required for synchronization and administration with the One Identity Manager database, are processed by the synchronization server.</p> <p>Installed components:</p> <ul style="list-style-type: none"> <li>• One Identity Manager Service (started)</li> </ul> <p>The synchronization server must be declared as a Job server in One Identity Manager. The Job server name is required.</p> <p>For more information, see <a href="#">Setting Up the Synchronization Server</a> on page 10.</p>
Remote connection server	<p>To configure synchronization with a target system, One Identity Manager must load the data from the target system. One Identity Manager communicates directly with target system to do this. Sometimes direct access from the workstation on which the Synchronization Editor is installed is not possible, because of the firewall configuration, for example, or because the workstation does not fulfill the necessary hardware and software requirements. If direct access to the workstation is not possible,</p>

Data	Explanation
	<p>you can set up a remote connection.</p> <p>The remote connection server and the workstation must be in the same Active Directory domain.</p> <p>Remote connection server configuration:</p> <ul style="list-style-type: none"> <li>• One Identity Manager Service is started</li> <li>• RemoteConnectPlugin is installed</li> </ul> <p>The remote connection server must be declared as a Job server in One Identity Manager. The Job server name is required.</p> <p><b>TIP:</b> The remote connection server requires the same configuration (with respect to the installed software) as the synchronization server. Use the synchronization as remote connection server at the same time, by simply installing the RemoteConnectPlugin as well.</p> <p>For more detailed information about setting up a remote connection, see the One Identity Manager Target System Synchronization Reference Guide.</p>
Synchronization workflow	<p>Set the option <b>Data import</b> in the synchronization step if CSV import data is supplied by a secondary system. You cannot select the processing method "MarkAsOutstanding" for these synchronization steps.</p> <p>For more detailed information about synchronizing user data with different systems, see the One Identity Manager Target System Synchronization Reference Guide.</p>
Base object	<p>You cannot normally specify a base object for synchronizing with the CSV connector. In this case, assignment of one base table and the synchronization server is sufficient.</p> <ul style="list-style-type: none"> <li>• Select the <b>Base table</b> from the menu in which to import the objects. The base table can be used to defined downstream processes for synchronizing a CSV system. For more information about downstream processes, see the One Identity Manager Target System Synchronization Reference Guide.</li> <li>• All Job servers, which have the server function "CSV connector" enabled are displayed in the <b>Synchronization servers</b> menu.</li> </ul>
Variable set	<p>If you implement specialized variable sets, ensure that the start up configuration and the base object use the same variable set.</p>

### **To configure synchronization with the CSV connector**

1. Create a new synchronization project.

2. Add mappings. Define property mapping rules and object matching rules.
3. Create synchronization workflows.
4. Create a start up configuration.
5. Define the synchronization scope.
6. Specify the base object of the synchronization.
7. Specify the extent of the synchronization log.
8. Run a consistency check.
9. Activate the synchronization project.
10. Save the new synchronization project in the database.

### Detailed information about this topic

- [How to Set up a Synchronization Project](#) on page 15

## How to Set up a Synchronization Project

There is an wizard to assist you with setting up a synchronization project. This wizard takes you all the steps you need to set up initial synchronization with a target system. Click **Next** once you have entered all the data for a step.

**NOTE:** The following sequence describes how you configure a synchronization project if the Synchronization Editor is both:

- In default mode
- Started from the launchpad

Additional settings can be made if the project wizard is run in expert mode or is started directly from the Synchronization Editor. Follow the project wizard instructions through these steps.

### To set up a synchronization project

1. Start the Launchpad and log on to the One Identity Manager database.
  - NOTE:** If synchronization is executed by an application server, connect the database through the application server.
2. Select the entry **CSV connector**. Click **Run**.

This starts the Synchronization Editor's project wizard.
3. Specify how the One Identity Manager can access the target system on the **System access** page.
  - If you have access from the workstation from which you started the Synchronization Editor, do not set anything.

- If you do not have access from the workstation from which you started the Synchronization Editor, you can set up a remote connection.  
In this case, set the option **Connect using remote connection server** and select, under **Job server**, the server you want to use for the connection.
  - Click **Next** to start the system connection wizard to create a connection to the CSV file.
4. Select **Create new CSV system** on the system connection wizard start page.
  5. Select the CSV file whose data is to be synchronized in the file browser. Click **Open**.
  6. Check the values for coding the files and language on the **Load CSV file** page.

**Table 8: CSV File Properties**

<b>Property</b>	<b>Description</b>
CSV file path	Full directory path to CSV file.
File encoding	CSV file character encoding. Encoding of the character set is determined from the character set on your workstation when the import file is loaded. Change the setting if the file was created with another character set.
File language	File language for the file. The language is required in order to read local character formats correctly, for example, dates.
Read only access	Specifies whether the CSV connector only has read access to the CSV file.  If this option is not set, the CSV connector can also write to the CSV file when the synchronization project is configured correspondingly.

7. Describe the CSV file structure on the **File structure** page.

**Table 9: File Structure**


<b>Property</b>	<b>Description</b>
Number of lines in header	Number of lines in the CSV file header. The header is not imported.
Column names in line	Lines, which contain column names.
Columns identified by	ID for column limits. <ul style="list-style-type: none"> <li>• Select the option <b>Delimiter</b> if the data is separated by a semi-colon, comma, space, tab, pipe or other character. Specify the</li> </ul>



Property	Description
	line structure.
	<ul style="list-style-type: none"> <li>Select the option <b>Fixed width</b> if all the data in the columns has the same length. Specify the line structure.</li> </ul>

8. Describe the row structure in the CSV file on the **Line structure** page.
  - a. If columns are separated by a delimiter, enter the delimiter.

**Table 10: Line structure**

Property	Description
Delimiter	<p>Delimiter used to separate the data in the file. You can choose between "semi-colon", "comma", "space", "tab" and "pipe".</p> <p>If the data is separated by another character select "other" and enter the delimiter in the field next to the list.</p>
Text delimiter	<p>Character enclosing the column text. This text is treated as one value on import, even is the text contains the delimiter given as above.</p> <p> <b>NOTE:</b> The delimiters are masked by doubling them up.</p>
Mask delimiter	<p>Specifies whether the data is separated by several of the same delimiters. Data that contains a new line must be marked with a text qualifier.</p>

- b. If the columns are delimited by a fixed width, specify the separation points.
      - Click on the ruler to set the separation points. A separation mark is inserted.
      - When you click again on a fixed separation point, the separation mark is deleted.
9. Describe the data structure on the page **Display information**.
  - a. Specify the **Display pattern** for displaying the objects in the Synchronization Editor. The display pattern is, for example, used in error messages or test result from object matching rules.
  - b. Specify the following properties for each column.

**Table 11: Column Structure**

Property	Description
Column	CSV file column name.

Property	Description
Key column	Specifies whether the column is used as a key column. More than one key columns can be defined. Data records should be uniquely identified with these key columns.
Hierarchical sort order	Specify whether the column maps the path in an object hierarchy. Synchronization objects are sorted by this order. This make it possible to resolve object dependencies. This option can only be set for <b>one</b> column of the CSV file. An example from the One Identity Manager schema: A department's full name (Department.FullPath) specifies the path in the department hierarchy (department with all parent departments). Objects are sorted by their full name during synchronization. All parent departments are loaded first during synchronization and then the child departments.
Display name	Name with which to display the column in the mapping editor. Specify a new display name or copy the column name from the CSV file.
Description	Spare text box for additional explanation.
Data type	Column's data type.
MVP column	Specifies whether the import contains a multi-value column (MVP). Enter the value delimiter.

10. On the page **Define CSV system file** specify the name and repository of the CSV system file. The system connection configuration to the CSV file is saved in this file.
11. On the past page of the system connection wizard you can add another CSV file to the system connection.
  - To add another CSV file to the system connection, click **Add another CSV file**.
  - Set the option **Save connection data on local computer** to save the connection data. This can be reused when you set up other synchronization projects.
  - Click **Finish**, to end the system connection wizard and return to the project wizard.

**NOTE:** The connection data is saved in a variable set and can be modified under **Configuration | Variables** in the Synchronization Editor.

12. Verify the One Identity Manager database connection data on the **One Identity Manager connection** page. The data is loaded from the connected database. Reenter the password.

**NOTE:** Reenter all the connection data if you are not working with an encrypted One Identity Manager database and no synchronization project has been saved yet in the database. This page is not shown if a synchronization project already exists.

13. The wizard loads the target system schema. This may take a few minutes depending on the type of target system access and the size of the target system.
14. Select a project template on the **Select project template** page to use for setting up the synchronization configuration.

**NOTE:** The CSV connection does not provide a default project template for setting up synchronization. If you have created your own project template, you can select it to configure the synchronization project. Otherwise, select **Create blank project**.

15. Enter the general setting for the synchronization project on the **General** page.

**Table 12: General Synchronization Project Properties**

Property	Description
Display name	Display name for the synchronization project.
Script language	<p>Language in which the scripts for this synchronization project are written.</p> <p>Scripts are implemented at various points in the synchronization configuration. Specify the script language when you set up an empty project.</p> <p><b>IMPORTANT:</b> The script language cannot be changed after the synchronization project has been saved.</p> <p>If you use a project template, the template's script language is used.</p>
Description	Spare text box for additional explanation.



16. Click **Finish** to complete the project wizard.
17. Save the synchronization project in the database.

## Customizing the CSV System File

The synchronization configuration must be changed if the CSV file schema changes. Changes are entered in the CSV system file. The CSV system file is edited in the system connection wizard. You can update the directory to the CSV files or CSV system file here.

# How to Edit a CSV File Schema

## To add a new CSV file to a system connection and edit the CSV file schema

1. Select the category **Configuration | Target systems**.
2. Click **Edit connection....**  
This starts the system connection wizard.
3. Specify the CSV files with which to set up the system connection on the page **Load CSV system file**, in view **CSV system information**.
  - To add a new CSV file to the system connection, click . Then edit the schema for this file.
  - To edit a CSV file schema, mark the file and click .
4. Check the values for coding the files and language on the **Load CSV file** page.

**Table 13: CSV File Properties**

Property	Description
CSV file path	Full directory path to CSV file.
File encoding	CSV file character encoding. Encoding of the character set is determined from the character set on your workstation when the import file is loaded. Change the setting if the file was created with another character set.
File language	File language for the file. The language is required in order to read local character formats correctly, for example, dates.
Read only access	Specifies whether the CSV connector only has read access to the CSV file.  If this option is not set, the CSV connector can also write to the CSV file when the synchronization project is configured correspondingly.

5. Describe the CSV file structure on the **File structure** page.


**Table 14: File Structure**

Property	Description
Number of lines in header	Number of lines in the CSV file header. The header is not imported.
Column	Lines, which contain column names.

Property	Description
names in line	
Columns identified by	<p>ID for column limits.</p> <ul style="list-style-type: none"> <li>• Select the option <b>Delimiter</b> if the data is separated by a semi-colon, comma, space, tab, pipe or other character. Specify the line structure.</li> <li>• Select the option <b>Fixed width</b> if all the data in the columns has the same length. Specify the line structure.</li> </ul>

6. Describe the row structure in the CSV file on the **Line structure** page.
  - a. If columns are separated by a delimiter, enter the delimiter.

**Table 15: Line structure**

Property	Description
Delimiter	<p>Delimiter used to separate the data in the file. You can choose between "semi-colon", "comma", "space", "tab" and "pipe".</p> <p>If the data is separated by another character select "other" and enter the delimiter in the field next to the list.</p>
Text delimiter	<p>Character enclosing the column text. This text is treated as one value on import, even is the text contains the delimiter given as above.</p> <p> <b>NOTE:</b> The delimiters are masked by doubling them up.</p>
Mask by doubling	<p>Specifies whether the data is separated by several of the same delimiters. Data that contains a new line must be marked with a text qualifier.</p>

- b. If the columns are delimited by a fixed width, specify the separation points.
      - Click on the ruler to set the separation points. A separation mark is inserted.
      - When you click again on a fixed separation point, the separation mark is deleted.
7. Describe the data structure on the page **Display information**.
  - a. Specify the **Display pattern** for displaying the objects in the Synchronization Editor. The display pattern is, for example, used in error messages or test

result from object matching rules.

- b. Specify the following properties for each column.

**Table 16: Column Structure**

<b>Property</b>	<b>Description</b>
Column	CSV file column name.
Key column	Specifies whether the column is used as a key column. More than one key columns can be defined. Data records should be uniquely identified with these key columns.
Hierarchical sort order	Specify whether the column maps the path in an object hierarchy. Synchronization objects are sorted by this order. This make it possible to resolve object dependencies. This option can only be set for <b>one</b> column of the CSV file. An example from the One Identity Manager schema: A department's full name (Department.FullPath) specifies the path in the department hierarchy (department with all parent departments). Objects are sorted by their full name during synchronization. All parent departments are loaded first during synchronization and then the child departments.
Display name	Name with which to display the column in the mapping editor. Specify a new display name or copy the column name from the CSV file.
Description	Spare text box for additional explanation.
Data type	Column's data type.
MVP column	Specifies whether the import contains a multi-value column (MVP). Enter the value delimiter.


8. On the past page of the system connection wizard you can add another CSV file to the system connection.
  - To add another CSV file to the system connection, click **Add another CSV file**.
  - Click **Finish** to end the system connection wizard.
9. Select the view **General** and click **Update schema**.
10. Confirm the security prompt with **Yes**.
11. This reloads the schema data.
12. Save the changes.

## Related Topics

- [How to Set up a Synchronization Project](#) on page 15
- [Updating Schemas](#) on page 24

# How to remove a CSV file from the System Connection

### *To remove a CSV file from the system connection*

1. Select the category **Configuration | Target systems**.
2. Click **Edit connection....**  
This starts the system connection wizard.
3. Specify the CSV files with which to set up the system connection on the page **Load CSV system file**, in view **CSV system information**. To remove a CSV file from the system connection, mark the file and click . Click **Next**.
4. Click **Finish** to end the system connection wizard.
5. Select the view **General** and click **Update schema**.
6. Confirm the security prompt with **Yes**.
7. This reloads the schema data.
8. Save the changes.

## Related Topics

- [Updating Schemas](#) on page 24

# How to Change the Path to the CSV System File

### *To change the CSV system file directory path*

1. Select the category **Configuration | Target systems**.
2. Click **Edit connection....**  
This starts the system connection wizard.
3. Select the correct CSV system file on the **Load CSV system file** page under **CSV system file** and click **Next..**
4. Click **Finish** to end the system connection wizard.

# Updating Schemas

All the schema data (schema types and schema properties) of the target system schema and the One Identity Manager schema are available when you are editing a synchronization project. Only a part of this data is really needed for configuring synchronization. If a synchronization project is finished, the schema is compressed to remove unnecessary data from the synchronization project. This can speed up loading the synchronization project. Deleted schema data can be added to the synchronization configuration again at a later point.

If the target system schema or the One Identity Manager schema has changed, these changes must also be added to the synchronization configuration. Then the changes can be added to the schema property mapping.

To include schema data that have been deleted through compressing and schema modifications in the synchronization project, update each schema in the synchronization project. This may be necessary if:

- A schema was changed by:
  - Changes to a target system schema
  - Customizations to the One Identity Manager schema
  - A One Identity Manager update migration
- A schema in the synchronization project was shrunk by:
  - Activating the synchronization project
  - Synchronization project initial save
  - Compressing a schema

## ***To update a system connection schema***

1. Select the category **Configuration | Target system**.  
- OR -  
Select the category **Configuration | One Identity Manager connection**.
2. Select the view **General** and click **Update schema**.
3. Confirm the security prompt with **Yes**.  
This reloads the schema data.

## ***To edit a mapping***

1. Select the category **Mappings**.
2. Select a mapping in the navigation view.  
Opens the Mapping Editor. For more detailed information about editing mappings, see One Identity Manager Target System Synchronization Reference Guide.

**NOTE:** The synchronization is deactivated if the schema of an activated synchronization project is updated. Reactivate the synchronization project to synchronize.



# Starting Synchronization

Synchronization is started using scheduled process plans. A scheduled process plan is added once a start up configuration is assigned to a schedule. Use schedules to define executing times for synchronization.

**NOTE:** Synchronization can only be started if the synchronization project is enabled.

To execute synchronization regularly, configure and activate the a schedule. You can also start synchronization manually if there is no active schedule.


**IMPORTANT:** As long as synchronization is running, you must not start another synchronization for the same target system. This applies especially, if the same synchronization objects would be processed.

- The moment another synchronization is started with the same start up configuration, the running synchronization process is stopped and given the status, "Frozen". An error message is written to the One Identity Manager Service log file.
- If another synchronization is started with another start up configuration, that addresses same target system, it may lead to synchronization error or loss of data. Specify One Identity Manager behavior in this case, in the start up configuration. Group start up configurations with the same start up behavior.

## Analyzing Synchronization

Synchronization results are summarized in the synchronization log. You can specify the extent of the synchronization log for each system connection individually. One Identity Manager provides several reports in which the synchronization results are organized under different criteria.

### **To display a synchronization log**

1. Select the category **Logs**.
2. Click  in the navigation view toolbar.  
Logs for all completed synchronization runs are displayed in the navigation view.
3. Select a log by double-clicking on it.

An analysis of the synchronization is shown as a report. You can save the report.

Synchronization logs are stored for a fixed length of time. The retention period is set in the configuration parameter "DPR\Journal\LifeTime" and its sub parameters.

### ***To modify the retention period for synchronization logs***

- Set the configuration parameter "Common\Journal\LifeTime" in the Designer and enter the maximum retention time for entries in the database journal. Use the configuration sub parameters to specify the retention period for each warning level.
- If there is a large amount of data, you can specify the number of objects to delete per DBQueue Processor operation and run in order to improve performance. Use the configuration parameters "Common\Journal\Delete\BulkCount" and "Common\Journal\Delete\TotalCount" to do this.
- Configure and set the schedule "Delete journal" in the Designer.

## **Post-Processing Outstanding Objects**

Objects, which do not exist in the target system, can be marked as outstanding in One Identity Manager by synchronizing. This prevents objects being deleted because of an incorrect data situation or an incorrect synchronization configuration.

Objects marked as outstanding:

- Cannot be edited in One Identity Manager.
- Are ignored by subsequent synchronization.
- Must be post-processed separately in One Identity Manager.

Start target system synchronization to do this.

### ***To allow post-processing of outstanding objects***

- Configure target system synchronization.  
For more information, see [Configuring Target System Synchronization](#) on page 26.


### **Related Topics**

- [How to Post-Process Outstanding Objects](#) on page 28
- [Users and Permissions for Synchronizing](#) on page 5

## **Configuring Target System Synchronization**


Create a target system for post-processing outstanding objects. Assign tables you want to be populated by synchronization, to this target system type. Specify the tables for which outstanding objects can be published in the target system during post-processing. Define a process for publishing the objects.

### To create a target system type

1. Start the Manager.
2. Select the category **Data Synchronization | Basic configuration data | Target system types**.
3. Click  in the result list toolbar.
4. Edit the target system type master data.
5. Save the changes.


Enter the following data for a target system type.

**Table 17: Master Data for a Target System Type**

Property	Description
Target system type	Target system type description.
Description	Spare text box for additional explanation.
Display Name	Name of the target system type as displayed in One Identity Manager tools.
Cross boundary inheritance	Specifies whether user accounts can be assigned to groups if they belong to different custom target systems.   <b>NOTE:</b> If this option is not set, the target system type is used to group the target systems.
Show in compliance rule wizard	Specifies whether the target system type for compliance rule wizard can be selected when rule conditions are being set up.
Text snippet	Text snippets used for linking text in the compliance rule wizard.

### To add tables to the target system synchronization.

1. Select the category **Data Synchronization | Basic configuration data | Target system types**.
2. Select the target system type in the result list.
3. Select **Assign synchronization tables** in the task view.
4. Assign tables whose outstanding objects you want to handle in **Add assignments**.
5. Save the changes.
6. Select **Configure tables for publishing**.
7. Select tables whose outstanding objects can be published in the target system and set the option **Publishable**.
8. Save the changes.

 **NOTE:** The connector must have write access to the target system in order to publish outstanding objects that are being post-processed. That means, the option **Connection is read only** must not be set for the target system connection.

### To publish outstanding objects

- Create a process for each table with outstanding objects you want to publish. The process is triggered by the event "HandleOutstanding" and provisions the objects. Use the process function "AdHocProjection" of the process component "ProjectorComponent". For more detailed information about defining processes, see One Identity Manager Configuration Guide.

## How to Post-Process Outstanding Objects

### To post-process outstanding objects

1. Start the Manager.
2. Select the category **Data synchronization | Target system synchronization: <target system type>**.

All tables assigned to the target system type are displayed in the navigation view.



3. Select the table whose outstanding objects you want to edit in the navigation view. All objects marked as outstanding are shown on the form.

#### TIP:

#### **To display object properties of an outstanding object**

- a. Select the object on the target system synchronization form.
  - b. Open the context menu and click **Show object**.
4. Select the objects you want to rework. Multi-select is possible.
  5. Click one of the following icons in the form toolbar to execute the respective method.

**Table 18: Methods for handling outstanding objects**

Icon	Method	Description
	Delete	The object is immediately deleted in the One Identity Manager. Deferred deletion is not taken into account. The "outstanding" label is removed from the object.  Indirect memberships cannot be deleted.
	Publish	The object is added in the target system. The "outstanding" label is removed from the object.  The method triggers the event "HandleOutstanding". This runs a target system specific process that triggers the provisioning process for the object.  Prerequisites: <ul style="list-style-type: none"><li>• The table containing the object can be published.</li></ul>

Icon	Method	Description
------	--------	-------------

- The target system connector has write access to the target system.
- A custom process is set up for provisioning the object.

	Reset	The "outstanding" label is removed from the object.
---	-------	---

6. Confirm the security prompt with **Yes**.

**NOTE:** By default, the selected objects are processed in parallel, which speeds up execution of the selected method. If an error occurs during processing, the action is stopped and all changes are discarded.

Bulk processing of objects must be disabled if errors are to be localized, which means the objects are processed sequentially. Failed objects are named in the error message. All changes that were made up until the error occurred are saved.

**To disable bulk processing**

- Deactivate  in the form toolbar.

## Related Topics

- [Configuring Target System Synchronization](#) on page 26
- [Users and Permissions for Synchronizing](#) on page 5

# Configuring Memberships Provisioning

Memberships, for example, user accounts in , are saved in assignment tables in the One Identity Manager database. During provisioning of modified memberships, changes made in the target system will probably be overwritten. This behavior can occur under the following conditions:

- Memberships are saved in the target system as an object property in list form (Example: List of user accounts in the property Members of an Active Directory group).
- Memberships can be modified in either of the connected systems.
- A provisioning workflow and provisioning processes are set up.

If a membership in One Identity Manager changes, the complete list of members is transferred to the target system by default. Memberships, previously added to the target system are removed by this; previously deleted memberships are added again.

To prevent this, provisioning can be configured such that only the modified membership is provisioned in the target system. The corresponding behavior is configured separately for each assignment table.

### **To allow separate provisioning of memberships**

1. Start the Manager.
2. Select the category **Data Synchronization | Basic configuration data | Target system types**.
3. Select **Configure tables for publishing**.
4. Select the assignment tables for which you want to allow separate provisioning. Multi-select is possible.
  - The option can only be set for assignment tables whose base table has a XDateSubItem or a CCC\_XDateSubItem .
  - Assignment tables, which are grouped together in a virtual schema property in the mapping, must be labeled identically (For example ADSAccountInADSGroup, ADSGroupInADSGroup and ADSMachineInADSGroup).
5. Click **Enable merging**.
6. Save the changes.

For each assignment table labeled like this, the changes made in the One Identity Manager are saved in a separate table. During modification provisioning, the members list in the target system is compared to the entries in this table. This means that only modified memberships are provisioned and the members list does not get entirely overwritten.

- NOTE:** The complete members list is updated by synchronization. During this process, objects with changes but incomplete provisioning are not handled. These objects are logged in the synchronization log.

For more detailed information about provisioning memberships, see the One Identity Manager Target System Synchronization Reference Guide.

## Troubleshooting

For detailed information about correcting errors during synchronization of object hierarchies, see the One Identity Manager Target System Synchronization Reference Guide.

### Help for Analyzing Synchronization Issues

You can generate a report for analyzing problems which occur during synchronization, for example, insufficient performance. The report contains information such as:

- Consistency check results
- Revision filter settings
- Scope applied
- Analysis of the synchronization buffer
- Object access times in the One Identity Manager database and in the target system

#### ***To generate a synchronization analysis report***

1. Open the synchronization project in the Synchronization Editor.
2. Select the menu **Help | Generate synchronization analysis report** and answer the security prompt with **Yes**.  
The report may take a few minutes to generate. It is displayed in a separate window.
3. Print the report or save it in one of the available output formats.

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

## Contacting us

For sales or other inquiries, visit <https://www.oneidentity.com/company/contact-us.aspx> or call +1-800-306-9329.

## Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to-videos at [www.YouTube.com/OneIdentity](http://www.YouTube.com/OneIdentity)
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product



## A

application role 5

## B

base object 13

## C

CSV connector 4

CSV file

change system connection data 19

## J

Job server

edit 10

## M

membership

modify provisioning 29

## O

object

delete immediately 28

outstanding 26, 28

publish 28

outstanding object 26

## P

provisioning

members list 29

## R

remote connection server 13

## S

schema

changes 24

shrink 24

update 24

synchronization

start 25

synchronization analysis report 31

synchronization configuration 13

for CSV import 15

synchronization log 25

synchronization server 13

configure 10

install 10

Job server 10

system connection wizard 19

## T

target system synchronization

table to assign 26

target system type 26

## V

variable set 13

## W

workflow 13