



Quest Recovery Manager for Active Directory
Forest Edition 10.4

Management Shell Guide



© 2026 Quest Software Inc.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of Quest Software Inc.

The information in this document is provided in connection with Quest Software products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of Quest Software products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, QUEST SOFTWARE ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL QUEST SOFTWARE BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF QUEST SOFTWARE HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Quest Software makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. Quest Software does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

Quest Software Inc.

Attn: LEGAL Dept

20 Enterprise, Suite 100

Aliso Viejo, CA 92656

Refer to our Web site (<https://www.quest.com>) for regional and international office information.

Patents

Quest Software is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <https://www.quest.com/legal>.

Trademarks

Quest, the Quest logo, and Join the Innovation are trademarks and registered trademarks of Quest Software Inc. For a complete list of Quest marks, visit <https://www.quest.com/legal/trademark-information.aspx>. All other trademarks and registered trademarks are property of their respective owners.

Updated – February 2026

Contents

Overview	7
About Management Shell	7
Installing and opening Management Shell	7
Installation requirements	7
Installing Management Shell	8
Opening Management Shell	8
Getting Help	8
Descriptions of PowerShell commands	9
Add-RMADBackup	16
Add-RMADCollectionItem	19
Add-RMADFECLOUDStorage	25
Add-RMADFECOMPUTER	31
Add-RMADREPLICATIONConsole	32
Add-RMADSTORAGEServer	36
Backup-RMADCollection	38
Close-RMADFEPROJECT	40
Compare-RMADOBJECT	41
Convert-RMADBackup	51
ConvertTo-RMADRECYCLEDObject	53
Create-RMADSTORAGEAgentSetup	56
Expand-RMADBackup	58
Export-RMADBackup	62
Export-RMADFECLOUDStorageBackup	64
Export-RMADFECLOUDStorageServers	66
Export-RMADFERecoveryCertificate	68
Export-RMADFEResult	70
Export-RMADSecureStorageBackup	71
Export-RMADSTORAGEServers	74
Get-RMADBackup	75
Get-RMADBackupAgent	83
Get-RMADBackupInfo	85
Get-RMADBackupObject	88
Get-RMADBackupSecurityStatus	93
Get-RMADCollection	94
Get-RMADCollectionItem	96
Get-RMADConsoleConfigurationBackup	101
Get-RMADDeletedObject	102
Get-RMADFECLOUDStorage	109
Get-RMADFECLOUDStorageCollection	111

Get-RMADFECloudStorageUploadSession	113
Get-RMADFEComputer	115
Get-RMADFEConsole	116
Get-RMADFEConsoleConfigurationBackupSchedule	118
Get-RMADFEDnsCache.....	119
Get-RMADFEDomain	120
Get-RMADFEEvent	123
Get-RMADFEFaultTolerance	124
Get-RMADFEGlobalOptions.....	125
Get-RMADFEOperation.....	127
Get-RMADFEProject	128
Get-RMADFERecoveryAgent.....	129
Get-RMADFERecoverySchedule	132
Get-RMADFERecoverySessions	133
Get-RMADFEReport.....	134
Get-RMADFESchedule	136
Get-RMADFEStandbyInstances.....	137
Get-RMADFEVerifySchedule	138
Get-RMADGlobalOptions	139
Get-RMADHybridRecoveryDomainOptions	141
Get-RMADHybridRecoveryOptions	142
Get-RMADLicenseInfo.....	143
Get-RMADObject.....	145
Get-RMADReplicationConsole	152
Get-RMADReplicationSchedule	153
Get-RMADReplicationSession	154
Get-RMADReplicationSessionItem	155
Get-RMADReportObject.....	157
Get-RMADReportObjectAttributes.....	158
Get-RMADReportObjectChildren	160
Get-RMADReportSession	161
Get-RMADSession	162
Get-RMADSessionItem	166
Get-RMADSessionItemEvent.....	168
Get-RMADStorageServer	170
Import-RMADBackup.....	171
Import-RMADFERecoveryCertificate	173
Install-RMADBackupAgent	175
Install-RMADFERecoveryAgent	177
New-RMADCollection	180
New-RMADFEProject.....	182
New-RMADFERecoveryMedia	184
New-RMADSchedule.....	188
Open-RMADFEProject	194
Protect-RMADSecureStorageServer.....	195
Publish-RMADBackupSecurityStatus.....	198
Refresh-RMADStorageServer	200
Register-RMADSecureStorageBackups	202

Remove-RMADBackup	204
Remove-RMADBackupAgent	207
Remove-RMADCollection	209
Remove-RMADCollectionItem	212
Remove-RMADFECLOUDStorage	213
Remove-RMADFECLOUDStorageUploadSession	216
Remove-RMADFECOMPUTER	219
Remove-RMADFERECOVERYAgent	220
Remove-RMADFERECOVERYSchedule	223
Remove-RMADFESCHEDULE	224
Remove-RMADFESTANDBYInstance	226
Remove-RMADFEVERIFYSchedule	227
Remove-RMADREPLICATIONConsole	229
Remove-RMADREPLICATIONSchedule	231
Remove-RMADREPLICATIONSession	232
Remove-RMADSESSION	234
Remove-RMADSTORAGEServer	236
Remove-RMADUNPACKEDComponent	239
Rename-RMADCollection	241
Restart-RMADFECLOUDStorageUploadSession	244
Restore-RMADDELETEDObject	246
Restore-RMADDOMAINController	256
Restore-RMADFECONSOLEConfiguration	261
Restore-RMADOBJECT	264
Resume-RMADFEOperation	272
Resume-RMADFERECOVERY	273
Save-RMADFEPROJECT	276
Send-RMADFECONSOLEConfigurationBackupToSecureStorage	277
Set-RMADCollection	280
Set-RMADFECLOUDStorage	289
Set-RMADFECLOUDStorageCollection	293
Set-RMADFECOMPUTER	296
Set-RMADFECONSOLEConfigurationBackupSchedule	318
Set-RMADFEDNSCache	321
Set-RMADFEDOMAIN	323
Set-RMADFEEFAULTTolerance	328
Set-RMADFEGLOBALOptions	331
Set-RMADFERECOVERYMode	336
Set-RMADFERECOVERYSchedule	338
Set-RMADFESCHEDULE	340
Set-RMADFEVERIFYSchedule	342
Set-RMADGLOBALOptions	344
Set-RMADHYBRIDRECOVERYDomainOptions	348
Set-RMADHYBRIDRECOVERYOptions	350
Set-RMADREPLICATIONConsole	354
Set-RMADREPLICATIONSchedule	358
Start-RMADFERECOVERY	360
Start-RMADFERECOVERYAgentOperation	363

Start-RMADFEShutdownInstance.....	366
Start-RMADFESync.....	367
Start-RMADHybridRecoveryDiscovery.....	369
Start-RMADReplication.....	371
Start-RMADReportViewer.....	373
Stop-RMADFESync.....	374
Stop-RMADFEShutdownInstance.....	376
Stop-RMADFESync.....	377
Test-RMADBackup.....	378
Test-RMADSecureStorageBackup.....	380
Update-RMADBackupAgent.....	382
Update-RMADFESync.....	385
Update-RMADLicense.....	387
About us.....	389

Overview

- [Installing and Opening Management Shell](#)
- [Getting Help](#)
- [Descriptions of PowerShell Commands](#)

About Management Shell

The Recovery Manager for Active Directory Management Shell, built on Microsoft Windows PowerShell® technology, provides a command-line interface that enables automation of backup/recovery-related administrative tasks. With this Management Shell, administrators can manage Computer Collections, backup/recovery sessions, compare and start backup/recovery jobs.

The Management Shell command-line tools (cmdlets), like all the Windows PowerShell® cmdlets, are designed to deal with objects—structured information that is more than just a string of characters appearing on the screen. The cmdlets do not use text as the basis for interaction with the system, but use an object model that is based on the Microsoft .NET platform. In contrast to traditional, text-based commands, the cmdlets do not require the use of text-processing tools to extract specific information. Rather, you can access portions of the data directly by using standard Windows PowerShell® object manipulation commands.

Installing and opening Management Shell

This section covers:

- [Installation requirements](#)
- [Installing Management Shell](#)
- [Opening Management Shell](#)

Installation requirements

Before you install the Recovery Manager for Active Directory Management Shell, ensure that your system meets the system requirements provided.

Requirements

Microsoft Windows PowerShell® version 5.0 or later

Installing Management Shell

To install Management Shell

1. Run the **Setup.exe** file included with the Recovery Manager for Active Directory installation package, and follow the instructions in the Setup Wizard.
2. To install Recovery Manager for Active Directory with default parameters (this includes installing the Management Shell component), click **Express**, and then follow the provided instructions to complete the Setup Wizard.

Opening Management Shell

You can open the Management Shell by using either of the following procedures. Each procedure loads the Recovery Manager for Active Directory Management Shell snap-in into Windows PowerShell®. If you do not load the Recovery Manager for Active Directory Management Shell snap-in before you run a command (cmdlet) provided by that snap-in, you will receive an error.

NOTE Verify that the user account under which you run Recovery Manager for Active Directory Management Shell console has the **Write** permission to the **%ProgramData%\Quest\Recovery Manager for Active Directory** folder. Otherwise, you will get warning messages when you run the snap-in cmdlets.

To open the Management Shell

1. Start Windows PowerShell®.

You can do so by running the **powershell** command at a command prompt (Cmd.exe).

2. At the Windows PowerShell® prompt, enter the following command: `Add-PSSnapin Quest.RecoveryManager.AD.*`

Alternatively, you can complete the following steps related to your version of Windows:

On the **Start** screen, click the **Management Shell** tile.

Upon the shell start, the console may present you with a message stating that a certain file published by Quest® is not trusted on your system. This security message indicates that the certificate the file is digitally signed with is not trusted on your computer, so the console requires you to enable trust for the certificate issuer before the file can be run. Press either R (Run once) or A (Always run). To prevent this message from appearing in the future, it is advisable to choose the second option (A).

Getting Help

The Recovery Manager for Active Directory Management Shell uses the Windows PowerShell® help cmdlets to assist you in finding the appropriate information to accomplish your task. The following table provides some examples of how to use the **Get-Help** and **Get-Command** cmdlets to access the help information that is available for each cmdlet in the Recovery Manager for Active Directory Management Shell.

Get-Help

When you use **Get-Help** without any parameters, you are presented with basic instructions on how to use the help system in Windows PowerShell®, including Help for the Recovery Manager for Active Directory Management Shell.

Get-Help

When you use **Get-Help** with the name of a cmdlet as an argument, you are presented with the help information for that cmdlet. For example, to retrieve the help information for the **Get-RMADCollection** cmdlet, use the following command:

```
Get-Help Get-RMADCollection
```

Get-Command

Get-Command without any parameters lists all the cmdlets that are available to the shell. You can use the **Get-Command** cmdlet with the **Format-List** or **Format-Table** cmdlet to provide a more readable display. For example, use **Get-Command | Format-List** to display the output in a list format. To display a list of all the Recovery Manager for Active Directory Management Shell cmdlets that are available to the shell, use the following syntax:

```
Get-Command *RMAD*
```

Get-Command

When you use **Get-Command** with the name of a cmdlet as an argument, you are presented with information about the parameters and other components of that cmdlet. The `<Cmdlet>` entry allows for wildcard character expansion. For example, to retrieve information about the cmdlets with the names ending in **Member**, you can use the following command:

```
Get-Command *Member
```

Descriptions of PowerShell commands

PowerShell cmdlets for Recovery Manager for Active Directory

Cmdlet	Description
Add-RMADBackup	Registers a backup in the Recovery Manager database.
Add-RMADCollectionItem	Adds a new item to a Computer Collection.
Add-RMADReplicationConsole	Adds a RMAD console as a replication source.
Add-RMADStorageServer	Adds a secure storage server, optionally remotely installs a storage server agent.
Backup-RMADCollection	Backs up an existing computer collection.
Compare-RMADObject	Compares Active Directory objects. This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA).
Convert-RMADBackup	Converts Windows Server backups into RMAD Bare Metal Recovery backups.
ConvertTo-RMADRecycledObject	Recycles specific deleted Active Directory objects.
Create-RMADStorageAgentSetup	Creates storage server agent setup.
Expand-RMADBackup	Extracts the contents of a specified backup file.

Cmdlet	Description
<code>Export-RMADBackup</code>	Exports registration information for a backup into an .xml file.
<code>Export-RMADSecureStorageBackup</code>	Exports a backup on a Secure Storage server to a remote network share.
<code>Export-RMADStorageServers</code>	Exports secure storage servers in CSV file.
<code>Get-RMADBackup</code>	Gets backups registered with Recovery Manager.
<code>Get-RMADBackupAgent</code>	Retrieves objects that represent Recovery Manager Backup Agents, or discovers manually preinstalled Recovery Manager Backup Agents.
<code>Get-RMADBackupInfo</code>	Gets the content of the backups held at a specified location.
<code>Get-RMADBackupObject</code>	Get objects from backups
<code>Get-RMADBackupSecurityStatus</code>	Gets security check information for a specified backup.
<code>Get-RMADCollection</code>	Retrieves Recovery Manager computer collection objects or default computer collection settings.
<code>Get-RMADCollectionItem</code>	Retrieves information about items contained in specified Recovery Manager for Active Directory computer collections.
<code>Get-RMADConsoleConfigurationBackup</code>	Retrieves console configuration backups registered for a specified Secure Storage server.
<code>Get-RMADDeletedObject</code>	Retrieves deleted Active Directory objects.
<code>Get-RMADGlobalOptions</code>	Sets global settings for the application.
<code>Get-RMADHybridRecoveryDomainOptions</code>	Gets the domain systems associated with the Hybrid Connector.
<code>Get-RMADHybridRecoveryOptions</code>	Gets the information related to the Hybrid Connector.
<code>Get-RMADLicenseInfo</code>	Retrieves information about the installed license key file.
<code>Get-RMADObject</code>	Retrieves specific objects from Active Directory or certain backups registered with Recovery Manager for Active Directory.
<code>Get-RMADReplicationConsole</code>	Gets all the RMAD consoles in the replication console list.
<code>Get-RMADReplicationSchedule</code>	Allows you to get the replication schedule from a specified computer.
<code>Get-RMADReplicationSession</code>	Retrieves information about replication sessions.
<code>Get-RMADReplicationSessionItem</code>	Retrieves a list of remote consoles that are involved in the specified replication session.
<code>Get-RMADReportObject</code>	Retrieves an object representing the online comparison or restore operation item.
<code>Get-RMADReportObjectAttributes</code>	Retrieves an object representing the online comparison or restore operation item attributes.

Cmdlet	Description
Get-RMADReportObjectChildren	Retrieves an object representing the online comparison or restore operation item child items.
Get-RMADReportSession	Retrieves an object representing the online comparison or restore operation report.
Get-RMADSession	Retrieves an object representing Recovery Manager backup sessions.
Get-RMADSessionItem	Gets items from a specified backup creation session.
Get-RMADSessionItemEvent	Gets events from a specified backup creation session item.
Get-RMADStorageServer	Returns a list of registered secure storage servers.
Import-RMADBackup	Reads the backup registration information from the .xml file and returns backup descriptions in the BackupInfo objects.
Install-RMADBackupAgent	Installs Recovery Manager Backup Agent on a specified computer or on each computer in a particular Computer Collection.
New-RMADCollection	Creates a new computer collection.
New-RMADSchedule	Creates a schedule for the backup creation operation you want to perform on a particular computer collection.
Protect-RMADSecureStorageServer	Enables storage server hardening.
Publish-RMADBackupSecurityStatus	Publishes security check information for a specified backup.
Refresh-RMADStorageServer	Refreshes current information of the secure storage server.
Register-RMADSecureStorageBackups	Registers backups on an existing secure storage server in a Recovery Manager database.
Remove-RMADBackup	Allows you to selectively unregister backups from the Recovery Manager backup registration database.
Remove-RMADBackupAgent	Removes Recovery Manager Backup Agent from a specified computer, or its registration information from the Recovery Manager Console.
Remove-RMADCollection	Deletes specified Computer Collections.
Remove-RMADCollectionItem	Removes items from a specified Computer Collection.
Remove-RMADReplicationConsole	Removes an RMAD console from the replication console list.
Remove-RMADReplicationSchedule	Allows you to remove the replication schedule from a specified computer.
Remove-RMADReplicationSession	Deletes replication sessions from the replication history.
Remove-RMADSession	Allows you to selectively delete specified Recovery Manager backup session(s).
Remove-RMADStorageServer	Removes the secure storage server.

Cmdlet	Description
Remove-RMADUnpackedComponent	Allows you to delete components (data) unpacked from specified backups.
Rename-RMADCollection	Renames a computer collection.
Restore-RMADDeletedObject	Restores deleted Active Directory objects. This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA).
Restore-RMADDomainController	Restores a domain controller from backup.
Restore-RMADObject	Restores Active Directory objects from a backup. This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA).
Set-RMADCollection	Sets properties for a computer collection.
Set-RMADGlobalOptions	Sets global application settings
Set-RMADHybridRecoveryDomainOptions	Sets the domain systems associated with the Hybrid Connector.
Set-RMADHybridRecoveryOptions	Sets the domain systems associated with the Hybrid Connector.
Set-RMADReplicationConsole	Sets replication properties of consoles in the replication console list.
Set-RMADReplicationSchedule	Sets replication schedules for a computer.
Start-RMADHybridRecoveryDiscovery	Start the Hybrid Recovery Discovery to update the database with a new domain discovered via the backup. This cmdlet is "for internal use only".
Start-RMADReplication	Performs replication from other computers in the replication console list.
Start-RMADReportViewer	Displays a report about the results of the online comparison or restore operation.
Test-RMADBackup	Checks the integrity of backups registered with Recovery Manager.
Test-RMADSecureStorageBackup	Checks the integrity of a backup on the secure storage server.
Update-RMADBackupAgent	Upgrades Recovery Manager Backup Agent on a specified computer or on each computer in a particular Computer Collection.
Update-RMADLicense	Updates license key file.

PowerShell cmdlets for Recovery Manager for Active Directory Forest Edition (Disaster Recovery Edition)

Cmdlet	Description
Add-RMADFECloudStorage	Registers a cloud storage in the Recovery Manager for Active Directory database, allowing backups to be copied to cloud storage.
Add-RMADFEComputer	Adds a new computer to the RMADFE project.
Backup-RMADFEConsoleConfiguration	Runs console configuration backup.
Close-RMADFEProject	Closes currently opened recovery project.
Export-RMADFECloudStorageBackup	Download a backup file from cloud storage and save it locally.
Export-RMADFECloudStorageServers	Exports cloud storage servers in CSV file.
Export-RMADFERecoveryCertificate	Exports Forest Recovery certificates.
Export-RMADFEResult	Export the verification result of an RMADFE project.
Get-RMADFECloudStorage	Returns cloud storage registered in Recovery Manager for Active Directory.
Get-RMADFECloudStorageCollection	Returns computer collections for the cloud storage registered in Recovery Manager for Active Directory.
Get-RMADFECloudStorageUploadSession	Retrieves the cloud storage upload session details.
Get-RMADFEComputer	Retrieves a list of computer settings from the current RMADFE project.
Get-RMADFEConsole	Gets all registered RMAD FE consoles.
Get-RMADFEConsoleConfigurationBackupSchedule	Returns console configuration backup schedule.
Get-RMADFEDnsCache	Returns cached DNS records in the Forest Recovery project.
Get-RMADFEDomain	Retrieves the domain settings.
Get-RMADFEEvent	Returns recovery events related to the entire Active Directory forest or a specific domain controller.
Get-RMADFEFaultTolerance	Retrieves the fault tolerance settings for the Forest Recovery Console.
Get-RMADFEGlobalOptions	Gets global application settings.
Get-RMADFEOperation	Returns information about the progress of the recovery operations.

Cmdlet	Description
Get-RMADFEProject	Gets the current status of the RMADFE project.
Get-RMADFERecoveryAgent	Returns information about Forest Recovery Agents that are installed and registered in Forest Recovery Console.
Get-RMADFERecoverySchedule	Gets a schedule for the RMADFE project recovery.
Get-RMADFERecoverySessions	Retrieves a list of verification and recovery sessions for the current RMADFE project.
Get-RMADFEReport	Generates an HTML report based on forest recovery project verification or recovery results.
Get-RMADFESchedule	Gets a schedule for the RMADFE project verification.
Get-RMADFEStandbyInstances	Retrieves a list of standby instances for the current RMADFE project.
Get-RMADFEVerifySchedule	Gets a schedule for the RMADFE project verification.
Import-RMADFERecoveryCertificate	Imports Forest Recovery certificates.
Install-RMADFERecoveryAgent	Installs Forest Recovery Agent on a specified domain controller or on each domain controller in the forest.
New-RMADFEProject	Creates a new RMADFE project in the file system.
New-RMADFERecoveryMedia	Creates a new Recovery Media ISO in the file system.
Open-RMADFEProject	Opens the RMADFE project.
Remove-RMADFECloudStorage	Removes a registered cloud storage from Recovery Manager for Active Directory.
Remove-RMADFECloudStorageUploadSession	Removes an existing cloud storage upload session.
Remove-RMADFEComputer	Removes a standalone computer from the RMADFE project.
Remove-RMADFERecoveryAgent	Removes Forest Recovery Agent from a specified domain controller, or its registration information from Forest Recovery Console.
Remove-RMADFERecoverySchedule	Removes an existing recovery schedule for the RMADFE project.
Remove-RMADFESchedule	Removes an existing verification schedule for the RMADFE project.

Cmdlet	Description
<code>Remove-RMADFESubbyInstance</code>	Removes the standby instance.
<code>Remove-RMADFEVerifySchedule</code>	Removes an existing verification schedule for the RMADFE project.
<code>Restart-RMADFECloudStorageUploadSession</code>	Restart a failed or canceled cloud storage upload session.
<code>Restore-RMADFEConsoleConfiguration</code>	Restores console configuration from backup.
<code>Resume-RMADFEOperation</code>	Resumes paused recovery process operation.
<code>Resume-RMADFERecovery</code>	Resumes recovery process.
<code>Save-RMADFEProject</code>	Saves the RMADFE project.
<code>Send-RMADFEConsoleConfigurationBackupToSecureStorage</code>	Copies a console configuration backup from a local storage or a network share to the secure storage server.
<code>Set-RMADFECloudStorage</code>	Updates cloud storage in the Recovery Manager.
<code>Set-RMADFECloudStorageCollection</code>	Configure a computer collection to use a registered cloud storage.
<code>Set-RMADFEComputer</code>	Applies computer settings to the RMADFE project.
<code>Set-RMADFEConsoleConfigurationBackupSchedule</code>	Sets console configuration schedule.
<code>Set-RMADFEDnsCache</code>	Updates cached DNS records in the Forest Recovery project.
<code>Set-RMADFEDomain</code>	Sets the domain settings for the current RMADFE project.
<code>Set-RMADFEFaultTolerance</code>	Sets fault tolerance settings for the Forest Recovery Console.
<code>Set-RMADFEGlobalOptions</code>	Sets global settings for recovery projects.
<code>Set-RMADFERecoveryMode</code>	Sets recovery mode for the current recovery project
<code>Set-RMADFERecoverySchedule</code>	Applies settings to the recovery schedule for the RMADFE project.
<code>Set-RMADFESchedule</code>	Applies settings to the verification schedule for the RMADFE project.
<code>Set-RMADFEVerifySchedule</code>	Applies settings to the verification schedule for the RMADFE project.
<code>Start-RMADFERecovery</code>	Performs the restore operation for the RMADFE project.

Cmdlet	Description
Start-RMADFERecoveryAgentOperation	Starts the agent operation on the remote machine where Forest Recovery agent is installed.
Start-RMADFEStandbyInstance	Starts the standby instance.
Start-RMADFEVerification	Performs verification of the RMADFE project.
Stop-RMADFECloudStorageUploadSession	Cancel queued or running cloud storage upload session.
Stop-RMADFEStandbyInstance	Stops the standby instance.
Stop-RMADFEWorkflow	Stops the verification or recovery workflow of the recovery project.
Update-RMADFEProject	Shows the difference between the current project and live Active Directory and updates the project.

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Add-RMADBackup

SYNOPSIS

Registers a backup in the Recovery Manager database.

SYNTAX

BackupInfo

```
Add-RMADBackup [-InputObject] <BackupInfo[]> [-SkipAlreadyRegistered] [-CheckIntegrity] [-BackupPassword <SecureString>] [-IgnoreReadOnly] [<CommonParameters>]
```

Bkf

```
Add-RMADBackup [-CheckIntegrity] [-Path] <String[]> [-BackupPassword <SecureString>] [-IgnoreReadOnly] [<CommonParameters>]
```

OfflineDit

```
Add-RMADBackup [-Path] <String[]> [-SysvolPath <String[]>] [-ResolveIndexes <Boolean>] [-OfflineDit] [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Registers specified backup in the Recovery Manager database. Use the `-InputObject` parameter to specify the backup to register.

EXAMPLES

Example

```
PS C:\> $b = Get-ChildItem "C:\Backups" -Filter *.bkf -Recurse | Get-  
RMADBackupInfo
```

```
C:\PS>Add-RMADBackup $b
```

The first line of this example gets the backups held in the `C:\Backups` folder and its subfolders, and saves the backup objects in the `$b` variable. The second line of this example registers the backup objects in the Recovery Manager database.

PARAMETERS

-BackupPassword

Specifies the password to access a password-protected backup. This is the same password that is set in the computer collection properties in the Recovery Manager console.

```
Type: SecureString  
Parameter Sets: BackupInfo, Bkf  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-CheckIntegrity

Forces checking the integrity of backups after they are registered in the Recovery Manager database.

```
Type: SwitchParameter  
Parameter Sets: BackupInfo, Bkf  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: False
```

Accept pipeline input: False
Accept wildcard characters: False

-InputObject

Accepts a backup object as input to the cmdlet. Enter a variable that contains the objects or type a command or expression that gets the objects.

Type: BackupInfo[]
Parameter Sets: BackupInfo
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-OfflineDit

Specifies that the application registers the DIT file as a backup.

Type: SwitchParameter
Parameter Sets: OfflineDit
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Path

Path to the backup file.

Type: String[]
Parameter Sets: Bkf, OfflineDit
Aliases: FullName

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False

-ResolveIndexes

Resolve the DIT file index.

Type: Boolean
Parameter Sets: OfflineDit
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SkipAlreadyRegistered

Do not display the error message if the backup is registered.

Type: SwitchParameter
Parameter Sets: BackupInfo
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-SysvolPath

Path to the SYSVOL folder.

Type: String[]
Parameter Sets: OfflineDit
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Add-RMADCollectionItem

SYNOPSIS

Adds a new item to a Computer Collection.

SYNTAX

InputObject

```
Add-RMADCollectionItem [-InputObject] <ComputerCollection> [-DomainController <String>] [-Domain <String>] [-OU <String>] [-Container <String>] [-ADSite <String>] [-AdamSite <String>] [-AdamServer <String>] [-AdamHost <String>] [-Exclusions <String[]>] [-Credentials <PSCredential>] [-IgnoreReadOnly] [<CommonParameters>]
```

Name

```
Add-RMADCollectionItem -Name <String> [-DomainController <String>] [-Domain <String>] [-OU <String>] [-Container <String>] [-ADSite <String>] [-AdamSite <String>] [-AdamServer <String>] [-AdamHost <String>] [-Exclusions <String[]>] [-Credentials <PSCredential>] [-IgnoreReadOnly] [<CommonParameters>]
```

Id

```
Add-RMADCollectionItem -Id <Int32> [-DomainController <String>] [-Domain <String>] [-OU <String>] [-Container <String>] [-ADSite <String>] [-AdamSite <String>] [-AdamServer <String>] [-AdamHost <String>] [-Exclusions <String[]>] [-Credentials <PSCredential>] [-IgnoreReadOnly] [<CommonParameters>]
```

Domain

```
Add-RMADCollectionItem [-Domain <String>] [-Exclusions <String[]>] [-IgnoreReadOnly] [<CommonParameters>]
```

OU

```
Add-RMADCollectionItem [-OU <String>] [-Exclusions <String[]>] [-Credentials <PSCredential>] [-IgnoreReadOnly] [<CommonParameters>]
```

Container

```
Add-RMADCollectionItem [-Container <String>] [-Exclusions <String[]>] [-Credentials <PSCredential>] [-IgnoreReadOnly] [<CommonParameters>]
```

ADSite

```
Add-RMADCollectionItem [-ADSite <String>] [-Exclusions <String[]>] [-Credentials <PSCredential>] [-IgnoreReadOnly] [<CommonParameters>]
```

AdamServer

```
Add-RMADCollectionItem [-AdamSite <String>] [-AdamServer <String>] [-Credentials <PSCredential>] [-IgnoreReadOnly] [<CommonParameters>]
```

AdamSite

```
Add-RMADCollectionItem [-AdamSite <String>] [-Exclusions <String[]>] [-  
Credentials <PSCredential>]  
[-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Adds a new item to the Computer Collection that has the specified name or is represented by the specified objects.

EXAMPLES

Example 1

```
PS C:\> Add-RMADCollectionItem -Name Collection1 -DomainController  
dc1.dom1.local
```

Adds the dc1.dom1.local domain controller to the computer collection named Collection1.

Example 2

```
PS C:\> $c = Get-RMADCollection Collection1
```

```
C:\PS>Add-RMADCollectionItem -InputObject $c -Domain dom1.local
```

In the first line of this example, the Get-RMADCollection cmdlet gets the computer collection object named Collection1 and saves it in the \$c variable. In the second line, the Add-RMCollection cmdlet adds the dom1.local domain to the Computer Collection object saved in the \$c variable.

Example 3

```
PS C:\> Add-RMADCollectionItem -Name Collection1 -OU  
"OU=Tokens,OU=Defender,DC=prod,DC=quest,DC=corp"
```

Adds an OU to the Computer Collection.

Example 4

```
PS C:\> Add-RMADCollectionItem -Name Collection1 -Container  
"CN=Computers,DC=prod,DC=quest,DC=corp"
```

Adds a container to the Computer Collection.

Example 5

```
PS C:\> $dn = "CN=Default-First-Site-  
Name,CN=Sites,CN=Configuration,DC=prod,DC=quest,DC=corp"  
Add-RMADCollectionItem -Name Collection1 -ADSite $dn -Exclusions  
@("ws1.prod.quest.corp:0")
```

Create an ADSite exclude from the domain controller (ws1.prod.quest.corp:0) and add it to the Computer Collection.

Example 6

```
PS C:\> $dn = "CN=Default-First-Site-  
Name,CN=Sites,CN=Configuration,CN={7B1308BE-06B9-4925-BEF5-C323292279F5}"  
Add-RMADCollectionItem -Name Collection1 -AdamServer  
ws1.prod.quest.corp:389 -AdamSite dn
```

Create an AdamSite and add it to the Computer Collection.

PARAMETERS

-AdamHost

Specifies the name of the server for the AD LDS instance installation.

Type: String
Parameter Sets: InputObject, Name, Id
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AdamServer

Name of the AD LDS instance.

Type: String
Parameter Sets: InputObject, Name, Id, AdamServer
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AdamSite

Specifies the distinguished name of the ADAM/AD LDS site to be added to the Computer Collection. Use it in conjunction with AdamServer.

Type: String
Parameter Sets: InputObject, Name, Id, AdamServer, AdamSite
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ADSite

Specifies the distinguished name of the Active Directory site to be added to the Computer Collection.

Type: String
Parameter Sets: InputObject, Name, Id, ADSite
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Container

Specifies the distinguished name of the container to be added to the Computer Collection.

Type: String
Parameter Sets: InputObject, Name, Id, Container
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Credentials

Specifies the credentials for the account with which you want to connect. Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

Type: PSCredential
Parameter Sets: InputObject, Name, Id, OU, Container, ADSite, AdamServer, AdamSite
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Domain

Specifies the DNS name of the domain to be added to the Computer Collection.

Type: String
Parameter Sets: InputObject, Name, Id, Domain
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DomainController

Specifies the DNS name of the domain controller to be added to the Computer Collection.

Type: String
Parameter Sets: InputObject, Name, Id
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Exclusions

Excludes a specified domain controller from the collection items to be added. The parameter must be used in conjunction with other parameters.

Type: String[]
Parameter Sets: InputObject, Name, Id, Domain, OU, Container, ADSite, AdamSite
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Id

Specifies the identifier of the Computer Collection to which you want to add items.

Type: Int32
Parameter Sets: Id
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-InputObject

Specifies the object representing the Computer Collections to which you want to add items. Enter a variable that contains the objects or type a command or expression that gets the objects.

Type: ComputerCollection
Parameter Sets: InputObject
Aliases: Collection

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-Name

Specifies the name of the Computer Collection to which you want to add items.

Type: String
Parameter Sets: Name
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-OU

Specifies the distinguished name of the organizational unit to be added to the Computer Collection.

Type: String

Parameter Sets: InputObject, Name, Id, OU

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Add-RMADFECLOUDStorage

SYNOPSIS

Registers a cloud storage in the Recovery Manager for Active Directory database, allowing backups to be copied to cloud storage.

SYNTAX

AzureConnectionStringProviderSet

```
Add-RMADFECLOUDStorage -Name <String> [-Container <String>] -  
AzureConnectionString <String> [-IgnoreReadOnly]  
[<CommonParameters>]
```

AzureManagedIdentityProviderSet

```
Add-RMADFECLOUDStorage -Name <String> [-Container <String>] -
AzureStorageAccount <String>
  [-AzureClientId <String>] [-IgnoreReadOnly] [<CommonParameters>]
```

AzureServicePrincipalParameterSet

```
Add-RMADFECLOUDStorage -Name <String> [-Container <String>] -
AzureStorageAccount <String>
  -AzureTenantId <String> -AzureClientId <String> -AzureClientSecret
  <String> [-IgnoreReadOnly]
  [<CommonParameters>]
```

AwsIAMUserProviderSet

```
Add-RMADFECLOUDStorage -Name <String> [-Container <String>] -AwsRegion
<String> -AwsAccessKey <String>
  -AwsSecretKey <String> [-IgnoreReadOnly] [<CommonParameters>]
```

AwsInstanceIAMRoleProviderSet

```
Add-RMADFECLOUDStorage -Name <String> [-Container <String>] -AwsRegion
<String> [-IgnoreReadOnly]
  [<CommonParameters>]
```

AwsIAMRoleProviderSet

```
Add-RMADFECLOUDStorage -Name <String> [-Container <String>] -AwsRegion
<String> -AwsAccessKey <String>
  -AwsSecretKey <String> -AwsIAMRole <String> [-IgnoreReadOnly]
  [<CommonParameters>]
```

DESCRIPTION

Registers a cloud storage in the Recovery Manager for Active Directory database, allowing backups to be copied to cloud storage. Use the Connection String parameter to securely connect to the cloud storage and specify the type of storage using the Type parameter.

EXAMPLES

Example 1

```
PS C:\> Add-RMADFECLOUDStorage -Name "MyStorage" -AzureConnectionString
"..." -Container "MyContainer"
```

Registers the Azure Blob Storage container named MyContainer in Recovery Manager for Active Directory.

Example 2

```
PS C:\> Add-RMADFECLOUDStorage -Name "MyStorage" -AwsRegion "us-east-1" -
AwsAccessKey "..."
-AwsSecretKey "..." -Container "MyContainer"
```

Registers the AWS S3 bucket named MyContainer in Recovery Manager for Active Directory using IAM user credential

Example 3

```
PS C:\> Add-RMADFECLOUDStorage -Name "MyStorage" -AwsRegion "us-east-1" -Container "MyContainer"
```

Registers the AWS S3 bucket named MyContainer in Recovery Manager for Active Directory using instance IAM role

Example 4

```
PS C:\> Add-RMADFECLOUDStorage -Name "MyStorage" -AzureStorageAccount "MyStorageAccount" -Container "MyContainer"
```

Registers the Azure Blob Storage container named MyContainer in Recovery Manager for Active Directory using System Managed Identity.

Example 5

```
PS C:\> Add-RMADFECLOUDStorage -Name "MyStorage" -AzureStorageAccount "MyStorageAccount" -AzureClientId "A0C39D59-DE61-4F3A-9C2C-88324E96A7CD" -Container "MyContainer"
```

Registers the Azure Blob Storage container named MyContainer in Recovery Manager for Active Directory using User Managed Identity with Client ID A0C39D59-DE61-4F3A-9C2C-88324E96A7CD.

Example 6

```
PS C:\> Add-RMADFECLOUDStorage -Name "MyStorage" -AzureStorageAccount "MyStorageAccount" -AzureTenantId "A95DDF49-E64C-474D-A53F-2D05C9A17311" -AzureClientId "A0C39D59-DE61-4F3A-9C2C-88324E96A7CD" -AzureClientSecret "..." -Container "MyContainer"
```

Registers the Azure Blob Storage container named MyContainer in Recovery Manager for Active Directory using Service Principal.

PARAMETERS

-AwsRegion

AWS region

Type: String

Parameter Sets: AwsIAMUserProviderSet, AwsInstanceIAMRoleProviderSet, AwsIAMRoleProviderSet

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-AwsAccessKey

AWS access key ID

Type: String

Parameter Sets: AwsIAMUserProviderSet, AwsIAMRoleProviderSet

Aliases:

Required: True

Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AwsSecretKey

AWS secret key ID

Type: String
Parameter Sets: AwsIAMUserProviderSet, AwsIAMRoleProviderSet
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AwsIAMRole

AWS IAM role ARN

Type: String
Parameter Sets: AwsIAMRoleProviderSet
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AzureClientId

Client ID value for user managed identity. If not specified, system managed identity is used. Or Service Principal Client ID.

Type: String
Parameter Sets: AzureManagedIdentityProviderSet
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
Type: String
Parameter Sets: AzureServicePrincipalParameterSet
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AzureClientSecret

Service Principal secret value.

Type: String
Parameter Sets: AzureServicePrincipalParameterSet

Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AzureConnectionString

Microsoft Azure connection string

Type: String
Parameter Sets: AzureConnectionStringProviderSet
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AzureStorageAccount

Storage account name

Type: String
Parameter Sets: AzureManagedIdentityProviderSet,
AzureServicePrincipalParameterSet
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AzureTenantId

Tenant ID value.

Type: String
Parameter Sets: AzureServicePrincipalParameterSet
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Container

Name of container in storage account. Backups will be copied to this location.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Name

Cloud storage display name for the registered storage in Recovery Manager for Active Directory.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Add-RMADFEComputer

SYNOPSIS

Adds a new computer to the RMADFE project.

SYNTAX

```
Add-RMADFEComputer [-ComputerName] <String> -Domain <String> -Site <String>
[<CommonParameters>]
```

DESCRIPTION

This cmdlet adds a new computer settings to the current RMADFE project.

EXAMPLES

Example 1

```
Add-RMADFEComputer -Name dc1.acme.com -Domain acme.com -Site Default-First-
Site-Name
```

This command adds a new dc1.acme.com standalone computer to the current RMADFE project.

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases: Name

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Domain

Specifies the name of the AD domain that the computer will be joined to.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Site

Specifies the name of the AD site that the computer will be joined to.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Add-RMADReplicationConsole

SYNOPSIS

Adds a RMAD console as a replication source.

SYNTAX

```
Add-RMADReplicationConsole [-ComputerName] <String> [-Mode]
<ReplicationMode>
  [-AccessCredential <PSCredential>] [-FallbackCredential <PSCredential>] [-
FileSyncEnabled <Boolean>]
  [-SourceFiles <String>] [-TargetFolder <String>] [<CommonParameters>]
```

DESCRIPTION

RMAD console can synchronize the backups, collections, global options, schedules, Secure Storage servers and backups stored on Secure Storage servers from the consoles in the replication console list manually or on schedule.

EXAMPLES

Example 1

```
PS C:\> C:\>$credential = Get-Credential
C:\>Add-RMADReplicationConsole Hostname1 -AccessCredential $credential
-Mode Backups
```

This command adds the RMAD console on Hostname1 to the replication console list with the Backups mode enabled.

Example 2

```
PS C:\> C:\>Add-RMADReplicationConsole -ComputerName Hostname1 -Mode Full
```

This command adds the RMAD console on Hostname1 to the replication console list with the Full mode enabled.

Example 3

```
PS C:\> C:\>$fallbackAccount = Get-Credential
C:\>Add-RMADReplicationConsole -ComputerName Hostname1 -Mode Full
-FallbackCredential $fallbackAccount
```

This command adds the RMAD console on Hostname1 to the replication console list with the Full mode enabled and with the specified fallback account.

Example 4

```
PS C:\> C:\>Add-RMADReplicationConsole -ComputerName Hostname1 -Mode Full -
FileSyncEnabled $true -SourceFiles "C:\MyProjectFiles\*.frproj" -
TargetFolder "C:\MyProjectFiles"
```

This command adds the RMAD console on Hostname1 to the replication console list with the Full mode enabled and with replication of the forest recovery project files.

PARAMETERS

-AccessCredential

Specifies the user credentials to read data from the target computer. The user must be a local Administrator on the target computer. To obtain the user credentials, create a PSCredential object using the Get-Credential cmdlet provided by Windows PowerShell.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ComputerName

Specifies the hostname of the computer on which the RMAD console you want to add is installed.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-FallbackCredential

Supplies a fallback account for replacing the account that is used by the backup schedule task. The account must have administrator privileges on the system(s) to be backed up. You can use this parameter only when Full mode is specified for the console.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-FileSyncEnabled

Enables replication of forest recovery project files.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Mode

Specifies the console mode: Full (to replicate backups, collections, global options and schedule) or Backups (to replicate backups only).

Type: ReplicationMode
Parameter Sets: (All)
Aliases:
Accepted values: Full, Backups

Required: True
Position: 1

Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SourceFiles

Specifies which forest recovery project files to replicate from the source console.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-TargetFolder

Specifies the folder to store the forest recovery project files replicated from the source console.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Add-RMADStorageServer

SYNOPSIS

Adds a secure storage server, optionally remotely installs a storage server agent.

SYNTAX

```
Add-RMADStorageServer [-Name] <String> [-Port <Int32>] [-Credential  
<PSCredential>] [-RegisterBackups]  
[-InstallAgent] [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Registers a secure storage server in Recovery Manager for Active Directory.

EXAMPLES

Example 1

```
PS C:\> Add-RMADStorageServer -Name "backupsrv01.acme.test" -Port 48001
```

Registers the secure storage server with given name and connection port.

PARAMETERS

-Credential

Server credentials used for remote agent installation. Ignored if the '-InstallAgent' switch is not set.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False

Accept wildcard characters: False

-InstallAgent

If set, automatically installs storage server agent.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Name

DNS name or IP address of the server.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-Port

Port used to connect to the secure storage agent.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-RegisterBackups

If set, backups on an existing storage server will be registered.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: **-Debug**, **-ErrorAction**, **-ErrorVariable**, **-InformationAction**, **-InformationVariable**, **-OutVariable**, **-OutBuffer**, **-PipelineVariable**, **-Verbose**, **-WarningAction**, and **-WarningVariable**. For more information, see [about_CommonParameters](#).

INPUTS

System.String

OUTPUTS

IStorageServer

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Backup-RMADCollection

SYNOPSIS

Backs up an existing computer collection.

SYNTAX

InputObject

```
Backup-RMADCollection [-InputObject] <ComputerCollection> [-AsJob] [-IgnoreReadOnly] [<CommonParameters>]
```

Name

```
Backup-RMADCollection [-Name] <String> [-AsJob] [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Backs up the existing computer collection that has the specified name or is represented by the specified objects.

EXAMPLES

Example 1

```
PS C:\> Backup-RMADCollection -Name "Collection1"
```

Backs up the Computer Collection named Collection1.

Example 2

```
PS C:\> Get-RMADCollection -Id 1 | Backup-RMADCollection
```

Gets the Computer Collection whose identifier is 1, and then backs up that Computer Collection.

Example 3

```
PS C:\> $c = Get-RMADCollection -Name col
```

```
C:\PS>Backup-RMADCollection -InputObject $c -AsJob
```

In the first line of this command, the Get-RMADCollection cmdlet gets the computer collection named col. The computer collection object is then stored in the \$c variable.

PARAMETERS

-AsJob

Runs the command as a background job. You can use this parameter to run commands that take a significant time to complete.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-InputObject

Backs up the existing Computer Collection represented by the specified collection object. Enter a variable that contains the object or type a command or expression that gets the object.

Type: ComputerCollection
Parameter Sets: InputObject
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-Name

Specifies the name of the existing Computer Collection to be backed up.

Type: String

Parameter Sets: Name

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Close-RMADFEPProject

SYNOPSIS

Closes currently opened recovery project.

SYNTAX

```
Close-RMADFEPProject [<CommonParameters>]
```

DESCRIPTION

This cmdlet allows you to close previously opened recovery project in the current PowerShell session.

EXAMPLES

Example 1

```
PS C:\> Close-RMADFEProject
```

Closes currently opened by Open-RMADFEProject recovery project.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Compare-RMADObject

SYNOPSIS

Compares Active Directory objects. This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA).

SYNTAX

Default (Default)

```
Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-  
Server <String>]  
[-Credential <PSCredential>] [-Backup <Guid>] [-Backup1 <Guid>] [-Backup2  
<Guid>]  
[-Backup1Password <SecureString>] [-Backup2Password <SecureString>] [-  
KeepBackupUnpacked] [-Id] <String[]>
```

```

[-ProcessChildren] [-ChildObjectClass <String[]>] [-
ReportUnchangedAttributes] [-ReportUnchangedObjects]
[-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential
<PSCredential>] [-RestoreUsingChangeAuditor]
[-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly]
[<CommonParameters>]

```

ADAndBackup

```

Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-
Server <String>]
[-Credential <PSCredential>] -Backup <Guid> [-BackupPassword
<SecureString>] [-KeepBackupUnpacked]
[-Id] <String[]> [-ProcessChildren] [-ChildObjectClass <String[]>] [-
ReportUnchangedAttributes]
[-ReportUnchangedObjects] [-ChangeAuditorDbName <String>] [-
ChangeAuditorDbCredential <PSCredential>]
[-RestoreUsingChangeAuditor] [-Partition <String>] [-Port <Int32>] [-
IgnoreReadOnly] [<CommonParameters>]

```

ADLds

```

Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-
Server <String>]
[-Credential <PSCredential>] [-Backup <Guid>] [-BackupPassword
<SecureString>] [-KeepBackupUnpacked]
[-Id] <String[]> [-ProcessChildren] [-ChildObjectClass <String[]>] [-
ReportUnchangedAttributes]
[-ReportUnchangedObjects] [-AdLds] -AdLdsInstance <String> [-
ChangeAuditorDbName <String>]
[-ChangeAuditorDbCredential <PSCredential>] [-RestoreUsingChangeAuditor]
[-Partition <String>] [-Port <Int32>]
[-IgnoreReadOnly] [<CommonParameters>]

```

Firewall

```

Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-
Server <String>]
[-Credential <PSCredential>] [-Backup <Guid>] [-BackupPassword
<SecureString>] [-KeepBackupUnpacked]
[-Id] <String[]> [-ProcessChildren] [-ChildObjectClass <String[]>] [-
ReportUnchangedAttributes]
[-ReportUnchangedObjects] [-AdLds] [-ChangeAuditorDbName <String>] [-
ChangeAuditorDbCredential <PSCredential>]
[-ConfigureFirewall] [-RestoreUsingChangeAuditor] [-Partition <String>] [-
Port <Int32>] [-IgnoreReadOnly]
[<CommonParameters>]

```

Agentless

```

Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-
Server <String>]
[-Credential <PSCredential>] [-Backup <Guid>] [-BackupPassword
<SecureString>] [-KeepBackupUnpacked]
[-Id] <String[]> [-UseAgentlessMethod] [-ProcessChildren] [-
ChildObjectClass <String[]>]
[-ReportUnchangedAttributes] [-ReportUnchangedObjects] [-AdLds] [-
ChangeAuditorDbName <String>]
[-ChangeAuditorDbCredential <PSCredential>] [-RestoreUsingChangeAuditor]
[-Partition <String>] [-Port <Int32>]
[-IgnoreReadOnly] [<CommonParameters>]

```

TwoBackups

```
Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-Server <String>] [-Credential <PSCredential>] -Backup1 <Guid> -Backup2 <Guid> [-Backup1Password <SecureString>] [-Backup2Password <SecureString>] [-KeepBackupUnpacked] [-Id <String[]>] [-ProcessChildren] [-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-ReportUnchangedObjects] [-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential <PSCredential>] [-RestoreUsingChangeAuditor] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Allows you to compare the following:

- Live Active Directory objects against their versions in a backup
- Active Directory objects held in two backups.

To fill in the 'ModifyBy' field for a report, use the ChangeAuditorDbName parameter. To view a report about the compare operation performed by this cmdlet, use the Start-RMADReportViewer cmdlet. You can only use this cmdlet when Windows PowerShell is started using MTA. To start Windows PowerShell using MTA, run this command: PowerShell -mta

EXAMPLES

Example

```
PS C:\> $b = (Get-RMADBackup -Domain dom1.local | Sort-Object -Property Date)[-1]
C:\PS>Compare-RMADObject -Backup $b.Path -Id "ou=oul,dc=dom1,dc=local" -ProcessChildren -ChangeAuditorDbName ".\ChangeAuditor"
```

In this example, the Get-RMADBackup cmdlet gets all backups existing for the dom1.local domain.

PARAMETERS

-AdLds

Specifies that the AD LDS instance is used as a data storage.

Type: SwitchParameter
Parameter Sets: ADLds
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
Type: SwitchParameter
Parameter Sets: Firewall, Agentless
Aliases:

Required: False
Position: Named

Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-AdLdsInstance

If you compare the object changes in AD LDS (ADAM), you should specify the AD LDS (ADAM) instance whose backup you want to use.

Type: String
Parameter Sets: ADLds
Aliases: AdamInstance

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Attribute

Specifies the display names of the object attributes to compare. When specifying multiple display names, use a comma as a separator.

Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Backup

Specifies the backup that contains the AD objects to be compared. Use this parameter if you want to compare AD objects in a backup with their counterparts in Active Directory.

Type: Guid
Parameter Sets: Default, ADLds, Firewall, Agentless
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
Type: Guid
Parameter Sets: ADAndBackup
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Backup1

Specifies the first backup that contains the AD objects to be compared. Use this parameter if you want to compare AD objects held in backups. The backup specified in this parameter must be registered in the Recovery Manager database.

Type: Guid
Parameter Sets: Default
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
Type: Guid
Parameter Sets: TwoBackups
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Backup1Password

Specifies the password to access the first backup, if the backup is password-protected. This is the same password that is set for the backup in the Recovery Manager console.

Type: SecureString
Parameter Sets: Default, TwoBackups
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Backup2

Specifies the second backup that contains the AD objects to be compared. Use this parameter if you want to compare AD objects held in backups. The backup specified in this parameter must be registered in the Recovery Manager database.

Type: Guid
Parameter Sets: Default
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
Type: Guid
Parameter Sets: TwoBackups
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False

Accept wildcard characters: False

-Backup2Password

Specifies the password to access the second backup, if the backup is password-protected. This is the same password that is set for the backup in the Recovery Manager console.

Type: SecureString
Parameter Sets: Default, TwoBackups
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupPassword

Specifies the password to access a password-protected backup. This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString
Parameter Sets: ADAndBackup, ADLds, Firewall, Agentless
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ChangeAuditorDbCredential

Specifies the credentials for connecting to the Change Auditor SQL database. If this parameter is omitted, the credentials of the current logged in user will be used.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ChangeAuditorDbName

Specifies a location of the Change Auditor SQL database. If this parameter is omitted, the 'ModifyBy' cell in AD reports will be empty.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ChildObjectClass

Specifies the child object classes to process. When specifying multiple classes, use a comma as a separator.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-ConfigureFirewall

Specifies whether Recovery Manager automatically configures Windows Firewall on domain controllers to allow compare and restore operations.

Type: SwitchParameter

Parameter Sets: Firewall

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-Credential

The user name and password of the user account with which you want to connect, in the form of a `PSCredential` object. Use the `Get-Credential` cmdlet provided by Windows PowerShell to pass a `PSCredential` object to this parameter. Use this parameter if you want to compare AD objects in a backup with their counterparts in Active Directory. If this parameter is omitted, the credentials of current user account are used. This parameter is ignored if you compare AD objects in a backup with their counterparts in another backup.

Type: `PSCredential`

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Id

Specifies the objects to compare. To specify an object, you can use object GUID, distinguished name (DN), `sAMAccountName`, or user principal name (UPN).

Type: String[]

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-KeepBackupUnpacked

Determines whether to save the unpacked backup after the search operation. If this parameter is not set, the unpacked backup will be deleted after the search operation is completed.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Partition

Specifies the AD LDS (ADAM) partition where you want to compare objects.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Port

Specifies the port on which to access the AD LDS (ADAM) instance that hosts the objects you want to compare.

Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ProcessChildren

When present, specifies to process children of the objects specified in the Id attribute.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ProcessRecycledObjects

When present, specifies to process recycled objects.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ReportUnchangedAttributes

Includes the object attributes that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ReportUnchangedObjects

Includes the objects that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-RestoreUsingChangeAuditor

Specifies if Change Auditor is used to restore the latest changes to the object.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Server

Specifies the domain controller or ADAM instance host from which objects are to be retrieved. The domain controller can be specified by its computer name, IP address, or domain name. If you specify a domain name, deleted objects are retrieved from any available domain controller in the specified domain. The ADAM instance host can be specified by its computer name or IP address. If this parameter is omitted, objects are retrieved from any available domain controller in the current domain.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-UseAgentlessMethod

Specifies to use the agentless method to access a domain controller. Use this parameter if you want to compare AD objects in a backup with their counterparts in Active Directory. If this parameter is omitted, the domain controller is accessed by using Restore Agent. This parameter is ignored if you compare AD objects in a backup with their counterparts in another backup.

Type: SwitchParameter
Parameter Sets: Agentless
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

The Backup 1 and Backup 2 parameters must specify backups for the same domain controller. In the DomainController parameter, you must specify the same domain controller whose backup you specified in the Backup parameter.

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Convert-RMADBackup

SYNOPSIS

Converts Windows Server backups into RMAD Bare Metal Recovery backups.

SYNTAX

```
Convert-RMADBackup [-WindowsServerBackupLocation] <String> [-BareMetalRecoveryPath] <String> [-AsJob] [  
  <CommonParameters>]
```

DESCRIPTION

Converts Windows Server Backups into RMAD Bare Metal Recovery backups.

EXAMPLES

Example 1

```
PS C:\> Convert-RMADBackup \\backup_srv01\wsb\WindowsImageBackup  
\\backup_srv01\rmad\bmr.vhdx
```

Synchronously starts the conversion of the Windows Server backup to the bmr.vhdx file located on the network share.

Example 2

```
PS C:\> Convert-RMADBackup \\backup_srv01\wsb\WindowsImageBackup  
\\backup_srv01\rmad\bmr.vhdx | Add-RMADBackup
```

Synchronously starts the conversion of the Windows Server backup located at the remote network share, puts the result into the bmr.vhdx file, and then registers the resulting backup.

Example 3

```
PS C:\> $job = Convert-RMADBackup D:\WindowsImageBackup D:\bmr.vhdx  
-AsJob $job.StatusMessage
```

Runs conversion as a background job and shows the current status message.

PARAMETERS

-AsJob

Runs the conversion process as a background job.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False

Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-BareMetalRecoveryPath

Specifies the full path to the RMAD Bare Metal Recovery backup file.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-WindowsServerBackupLocation

Specifies the full path to the Windows Server backup. You must specify the path including the WindowsImageBackup folder.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

String

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

ConvertTo-RMADRecycledObject

SYNOPSIS

Recycles specific deleted Active Directory objects.

SYNTAX

```
ConvertTo-RMADRecycledObject -Name <String[]> [-Force] [-Server <String>]
[-Credential <PSCredential>]
[-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [-WhatIf] [-
Confirm] [<CommonParameters>]
```

DESCRIPTION

Allows you to manually recycle specific deleted Active Directory objects held in Microsoft's Active Directory Recycle Bin in the forest where Recovery Manager is installed. This cmdlet overrides the deleted object lifetime setting that applies to the deleted objects being recycled. You can only use this cmdlet if Microsoft's Active Directory Recycle Bin feature is enabled in the forest where Recovery Manager is installed.

EXAMPLES

Example 1

```
PS C:\> (Get-RMADDeletedObject dc1.dom1.lab.local) |
Where-Object { $_.objectclass -contains "user" } |
Foreach-Object { ConvertTo-RMADRecycledObject -Name $_.Name -Server
dc1.dom1.lab.local }
```

This example shows how to recycle all user objects held in Microsoft's Active Directory Recycle Bin. The Get-RMADDeletedObject cmdlet gets all deleted objects from Microsoft's Active Directory Recycle Bin by connecting to the dc1.dom1.lab.local domain controller. Then the Get-RMADDeletedObject cmdlet pipes the objects to the Where-Object cmdlet that filters out user objects. Then, the Foreach-Object cmdlet uses the ConvertTo-RMADRecycledObject cmdlet to transfer each user object to the recycled state.

Example 2

```
PS C:\> ConvertTo-RMADRecycledObject -Name "User 1\0ADEL:7dbac5c7-f38d-
4270-8ac2-7a0674bc246b"
```

Converts the deleted object "User 1\0ADEL:7dbac5c7-f38d-4270-8ac2-7a0674bc246b" to recycled state.

PARAMETERS

-Credential

The user name and password of the user account with which you want to connect, in the form of a PSCredential object. Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

Type: PSCredential
Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Force

Suppresses the cmdlet prompt for confirmation. When this parameter is omitted, the cmdlet prompts you for confirmation before recycling objects.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Name

Allows you to specify the deleted object you want to recycle. To specify a deleted object, enter the value of the object's Name attribute in this parameter. The Name attribute provides the object's relative distinguished name (RDN) that looks similar to the following: User 1\0ADEL:7dbac5c7-f38d-4270-8ac2-7a0674bc246b
To view the value of the Name attribute for a deleted object, you can use the Get-RMADDeletedObject cmdlet.

Type: String[]
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-Partition

Specifies the distinguished name of the Active Directory partition from which deleted objects are to be retrieved. If this parameter is omitted, the default naming context is used. This parameter is required if you specify an ADAM instance host in the DirectoryHost parameter.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Port

Specifies the port number to be used for connection. If this parameter is set to 0 or not specified, the default LDAP port (389) is used.

Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Server

Specifies the Active Directory domain, domain controller, or AD LDS (ADAM) instance host from which you want the cmdlet to retrieve objects. If this parameter is omitted, the cmdlet retrieves objects from any available domain controller in the current domain. To specify a domain controller or AD LDS (ADAM) instance host, use the computer name or IP address. If you specify an Active Directory domain name in this parameter, the cmdlet retrieves objects from any available domain controller in the specified domain.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts for a confirmation before executing the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False

Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Create-RMADStorageAgentSetup

SYNOPSIS

Creates storage server agent setup.

SYNTAX

```
Create-RMADStorageAgentSetup [-Path] <String> [-Port <Int32>]  
[<CommonParameters>]
```

DESCRIPTION

Create storage server agent setup bundle packed to the ZIP archive that contains required components to deploy the storage server agent.

EXAMPLES

Example 1

```
PS C:\> Create-RMADStorageAgentSetup -Path "C:\Setup.zip" -StorageAgentPort 48001
```

Creates a setup bundle and puts it in the specified file.

PARAMETERS

-Path

Path to the result file in which the setup will be created.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-Port

Port that will be used to run storage agent on.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.String

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Expand-RMADBackup

SYNOPSIS

Extracts the contents of a specified backup file.

SYNTAX

BackupInfo (Default)

```
Expand-RMADBackup [-InputObject] <BackupInfo[]> [-BackupPassword  
<SecureString>] [-TargetFolder] <String>  
  [[-Components] <BackupComponentBits>] [-AsJob] [<CommonParameters>]
```

Bkf

```
Expand-RMADBackup [-Path] <String[]> [-BackupPassword <SecureString>] [-  
TargetFolder] <String>  
  [[-Components] <BackupComponentBits>] [-AsJob] [<CommonParameters>]
```

Id

```
Expand-RMADBackup [-Id] <Int32[]> [-BackupPassword <SecureString>] [-  
TargetFolder] <String>  
  [[-Components] <BackupComponentBits>] [-AsJob] [<CommonParameters>]
```

DESCRIPTION

Allows you to selectively extract the contents of a backup file created with Recovery Manager for Active Directory to the location you want.

EXAMPLES

Example 1

```
PS C:\> Expand-RMADBackup -InputObject (Get-RMADBackup | where {$_.Date -gt (Get-Date).AddDays(-2)}) -TargetFolder 'C:\UnpackedBackups'
```

This command extracts the contents of all backups created within last two days to the local folder C:\UnpackedBackups.

PARAMETERS

-AsJob

Runs the command as a background job. You can use this parameter to run commands that take a significant time to complete.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-BackupPassword

If the backup is password-protected, specifies the password to open the backup. The parameter value must be a SecureString object.

Type: SecureString
Parameter Sets: (All)
Aliases: Password

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Components

Specifies the backup components you want to extract. When specifying multiple backup components in this parameter, use a comma as a separator. This parameter accepts the following values for backup components:

- Sam - Specifies to extract the SAM registry hive.
- Security - Specifies to extract the Security registry hive.
- Software - Specifies to extract the Software registry hive.
- System - Specifies to extract the System registry hive.
- Default - Specifies to extract the Default registry hive.
- NTUserDat - Specifies to extract the NTUser.dat registry hive.
- Components - Specifies to extract the Components registry hive.

- SchemaDat - Specifies to extract the Schema.dat.
- ActiveDirectoryDatabase - Specifies to extract the DIT database.
- Sysvol - Specifies to extract SYSVOL.
- EnterpriseServices - Specifies to extract the COM+ Class Registration database.
- BootFiles - Specifies to extract the boot files.
- IISMetabase - Specifies to extract IIS metabase.
- PerformanceCounters - Specifies to extract performance counters.
- CertificateServer - Specifies to extract certificate server.
- ClusterQuorum - Specifies to extract the cluster quorum.
- Adam - Specifies to extract all instances of AD LDS (ADAM).
- GroupMembership - Specifies to extract cross-domain group membership information.
- ActiveDirectory - Specifies to extract the components represented by the following parameters: ActiveDirectoryDatabase and SYSVOL.
- Registry - Specifies to extract the components represented by the following parameters: Sam, Security, Software, System, Default, NTUserDat, Components, and SchemaDat.

Type: BackupComponentBits

Parameter Sets: (All)

Aliases:

Accepted values: Sam, Security, Software, System, Default, NTUserDat, ActiveDirectoryDatabase, Sysvol, ActiveDirectory, EnterpriseServices, BootFiles, SystemProtectedFiles, BootIni, CertificateServer, IisMetabase, PerformanceCounters, ClusterQuorum, Adam, GroupMembership, BootFilesExt, CryptoKeys, ForestRecoveryMetadata, Components, SchemaDat, Registry, VirtualImage, HardLinks, LdapsCerts

Required: False

Position: 2

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Id

Specifies the identifier of the backup you want to extract.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-InputObject

Accepts a backup object as input to the cmdlet. Enter a variable that contains the object or type a command or expression that gets the object.

Type: BackupInfo[]

Parameter Sets: BackupInfo

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-Path

Path to the backup file.

Type: String[]

Parameter Sets: Bkf

Aliases: FullName

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-TargetFolder

Specifies the target folder to which you want to extract the backup.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Export-RMADBackup

SYNOPSIS

Exports registration information for a backup into an .xml file.

SYNTAX

InputObject

```
Export-RMADBackup [-InputObject] <BackupInfo[]> [-Path] <String> [-PassThru] [<CommonParameters>]
```

Id

```
Export-RMADBackup [-Id] <Int32[]> [-Path] <String> [-PassThru] [<CommonParameters>]
```

DESCRIPTION

This cmdlet exports the registration information for the specified backup into an .xml file. You can then use the Import-RMADBackup cmdlet to transform the registration information saved in the .xml file into an object.

EXAMPLES

Example 1

```
PS C:\> $b = Get-RMADBackup  
Export-RMADBackup -Path Backups.xml -InputObject $b
```

Exports registration information for all backups registered in the Recovery Manager for Active Directory backup registration database located on the computer where you are using this cmdlet. The backup registration information is saved in the Backups.xml file.

Example 2

```
PS C:\> Export-RMADBackup -Id 1 -Path C:\ExportedBackups
```

Exports the registration information of the backup whose ID 1 to an XML file in the folder C:\ExportedBackups.

PARAMETERS

-Id

Specifies the identifiers of one or more backups to export. This parameter accepts an array of integers.

```
Type: Int32[]  
Parameter Sets: Id  
Aliases:
```

```
Required: True
```

Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-InputObject

Accepts a backup object as input to the cmdlet. Enter a variable that contains the object or type a command or expression that gets the object.

Type: BackupInfo[]
Parameter Sets: InputObject
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-PassThru

Passes the registration information for the specified backup along the pipeline. If this parameter is omitted, the registration information is not passed along the pipeline.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Path

Specifies the path to the .xml file where you want to save registration information for the backup.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Export-RMADFECLOUDStorageBackup

SYNOPSIS

Download a backup file from cloud storage and save it locally.

SYNTAX

UploadSessionId

```
Export-RMADFECLOUDStorageBackup [-UploadSessionId] <Int32> [-Path] <String>  
[<CommonParameters>]
```

InputObject

```
Export-RMADFECLOUDStorageBackup [-InputObject] <UploadSession> [-Path]  
<String> [<CommonParameters>]
```

DESCRIPTION

This cmdlet allows you to download an Active Directory or BMR backup from cloud storage. Use the Path parameter to specify a local path for the download. Specify the upload session Id for the UploadSession parameter. The upload session Id can be found in the list of upload sessions for each backup file.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFECLOUDStorageUploadSession
```

```
Id                : 2  
StorageId         : 1
```

```
BackupId : 7143538
SourceBackupPath : \\mycomputer.company.ca\Backups\MyBackup_123456.bkf
TargetBackupPath : mycomputer.company.ca\Backups\MyBackup_123456.bkf
ErrorMessage :
CreationTimestamp : 10/28/2022 4:23:47 PM
ModificationTimestamp : 10/28/2022 4:24:17 PM
Status : UploadStatusCompleted
```

```
Id : 1
StorageId : 1
BackupId : 5439573
SourceBackupPath : \\mycomputer.company.ca\Backups\MyBackup_123456.bkf
TargetBackupPath : mycomputer.company.ca\Backups\MyBackup_123456.bkf
ErrorMessage :
CreationTimestamp : 10/28/2022 4:14:10 PM
ModificationTimestamp : 10/28/2022 4:14:17 PM
Status : UploadStatusCompleted
```

```
PS C:\> Export-RMADFECLOUDStorageBackup -UploadSessionId 2 -Path
C:\Backups\MyBackup_123456.bkf
```

Download the backup file uploaded by the session with Id 2 to the local path specified.

PARAMETERS

-InputObject

Specifies the UploadSession object representing the cloud storage upload session.

```
Type: UploadSession
Parameter Sets: InputObject
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

-Path

The full local path for the downloaded backup file.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-UploadSessionId

The Upload session Id for the backup to be downloaded.

```
Type: Int32
Parameter Sets: UploadSessionId
Aliases:
```

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

QuestSoftware.RecoveryManager.AD.FE.PowerShell.UploadSession

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Export-RMADFECLOUDSTORAGESERVERS

SYNOPSIS

Exports cloud storage servers in CSV file.

SYNTAX

```
Export-RMADFECLOUDSTORAGESERVERS [-Path] <String> [-IgnoreReadOnly]  
[<CommonParameters>]
```

DESCRIPTION

Exports currently registered cloud storage servers and their current statuses in CSV file.

EXAMPLES

Example 1

```
PS C:\> Export-RMADFECloudStorageServers -Path C:\SecureStorageServers.csv
```

Saves all current cloud storage servers to C:\SecureStorageServers.csv file

PARAMETERS

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Path

Path to file where to save cloud storage servers information.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.String

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Export-RMADFERecoveryCertificate

SYNOPSIS

Exports Forest Recovery certificates.

SYNTAX

```
Export-RMADFERecoveryCertificate [-Path] <String> [-Password]  
<SecureString> [<CommonParameters>]
```

DESCRIPTION

This cmdlet exports Forest Recovery certificates to the specified location. You must also supply the password that is used to protect the certificates.

EXAMPLES

EXAMPLE 1

```
PS C:\> Export-RMADFERecoveryCertificate -Path  
C:\Certificates\RMADFeCertificates.pfx" -Password (ConvertTo-SecureString  
"protection password" -AsPlainText -Force)
```

This command exports Forest Recovery certificates to the specified location.

PARAMETERS

-Password

Specifies the password that is used to protect the Forest Recovery certificates.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Path

Specifies the full path to the Forest Recovery certificate file.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Export-RMADFEResult

SYNOPSIS

Exports verification or recovery results.

SYNTAX

```
Export-RMADFEResult [-Results] <ProjectSummary> [-Path] <String>  
[<CommonParameters>]
```

DESCRIPTION

This cmdlet exports the results of a forest recovery project verification or a completed forest recovery to an XML file. To export the results, first retrieve the current status of the forest recovery project, and then specify the file path where the XML file should be saved.

EXAMPLES

Example 1

```
PS C:\> Open-RMADFEProject -Path C:\RMADFeProjects\SampleProject.frproj -  
Password (ConvertTo-SecureString "project password" -AsPlainText -Force)  
Start-RMADFEVerification  
$results = Get-RMADFEProject  
Export-RMADFEResult -Results $results -Path "C:\VerificationResults.xml"
```

This example illustrates how to export verification results to an XML file.

Example 2

```
PS C:\> Open-RMADFEProject -Path C:\RMADFeProjects\SampleProject.frproj -  
Password (ConvertTo-SecureString "project password" -AsPlainText -Force)  
Start-RMADFEVerification  
Get-RMADFEProject | Export-RMADFEResult -Path "C:\VerificationResults.xml"
```

This example illustrates how to export verification results using the pipeline.

PARAMETERS

-Path

Specifies the path to the XML file where the results will be saved.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Results

Specifies the current status of the forest recovery project.

Type: ProjectSummary

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Export-RMADSecureStorageBackup

SYNOPSIS

Exports a backup on a Secure Storage server to a remote network share.

SYNTAX

InputObject

```
Export-RMADSecureStorageBackup [-InputObject] <BackupInfo[]> [-TargetRemoteFolder] <String> [-TargetCredentials] <PSCredential> [-PassThru] [<CommonParameters>]
```

Id

```
Export-RMADSecureStorageBackup [-Id] <Int32[]> [-TargetRemoteFolder]
<String>
  [-TargetCredentials] <PSCredential> [-PassThru] [<CommonParameters>]
```

DESCRIPTION

Exports a backup on a Secure Storage server to a remote network share.

EXAMPLES

Example 1

```
$credential = Get-Credential
$backup = Get-RMADBackup -OnlySecureStorage -ComputerName 'dcl.rmad.local'
| Select-Object -First 1
Export-RMADSecureStorageBackup -InputObject $backup -TargetRemoteFolder
'\\192.168.0.1\BackupsNew\Temp' -TargetCredentials $credential
```

Example 2

```
$credential = Get-Credential
Export-RMADSecureStorageBackup -Id @(2, 4, 6) -TargetRemoteFolder
'\\192.168.0.1\BackupsNew\Temp' -TargetCredentials $credential
```

PARAMETERS

-Id

Specifies the identifiers of one or more backups to export. This parameter accepts an array of integers.

```
Type: Int32[]
Parameter Sets: Id
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

-InputObject

Accepts a backup object as input to the cmdlet. Enter a variable that contains the object or type a command or expression that gets the object.

```
Type: BackupInfo[]
Parameter Sets: InputObject
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

-PassThru

Passes the registration information for the specified backup along the pipeline. If this parameter is omitted, the registration information is not passed along the pipeline.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-TargetCredentials

Credentials to access the target network location.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: True

Position: 2

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-TargetRemoteFolder

Remote network share where backup should be exported.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Export-RMADStorageServers

SYNOPSIS

Exports secure storage servers in CSV file.

SYNTAX

```
Export-RMADStorageServers [-Path] <String> [-IgnoreReadOnly]  
[<CommonParameters>]
```

DESCRIPTION

Exports currently registered secure storage servers and their current statuses in CSV file.

EXAMPLES

Example 1

```
PS C:\> Export-RMADStorageServers -Path C:\SecureStorageServers.csv
```

Saves all current storage servers to C:\SecureStorageServers.csv file

PARAMETERS

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Path

Path to file where to save secure storage servers information.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.String

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADBackup

SYNOPSIS

Gets backups registered with Recovery Manager.

SYNTAX

Id (Default)

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [[-Id]
<Int32[]>] [-ComputerName <String>]
  [-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
  [-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
AfterModifiedDate <DateTime>] [-First <Int32>]
  [-Skip <Int32>] [-SourceConsole <String>] [<CommonParameters>]
```

Id_IncludeSecureStorage

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-Id]
<Int32[]> [-ComputerName <String>]
  [-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
  [-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
IncludeSecureStorage]
  [-AfterModifiedDate <DateTime>] [-First <Int32>] [-Skip <Int32>] [-
SourceConsole <String>]
  [<CommonParameters>]
```

Id_OnlySecureStorage

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-Id]
<Int32[]> [-ComputerName <String>]
  [-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
  [-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
OnlySecureStorage] [-AfterModifiedDate <DateTime>]
  [-First <Int32>] [-Skip <Int32>] [-SourceConsole <String>]
  [<CommonParameters>]
```

Guid

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [[-Guid]
<Guid[]>] [-ComputerName <String>]
  [-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
  [-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
AfterModifiedDate <DateTime>] [-First <Int32>]
  [-Skip <Int32>] [-SourceConsole <String>] [<CommonParameters>]
```

Guid_IncludeSecureStorage

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-Guid]
<Guid[]> [-ComputerName <String>]
  [-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
  [-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
IncludeSecureStorage]
  [-AfterModifiedDate <DateTime>] [-First <Int32>] [-Skip <Int32>] [-
SourceConsole <String>]
  [<CommonParameters>]
```

Guid_OnlySecureStorage

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-Guid]
<Guid[]> [-ComputerName <String>]
  [-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
  [-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
OnlySecureStorage] [-AfterModifiedDate <DateTime>]
  [-First <Int32>] [-Skip <Int32>] [-SourceConsole <String>]
[<CommonParameters>]
```

IncludeSecureStorage

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-
ComputerName <String>] [-MaxDate <DateTime>]
  [-MinDate <DateTime>] [-Site <String>] [-CollectionId <Int32>] [-
BackupComponents <BackupComponents>]
  [-IncludeDeleted] [-IncludeSecureStorage] [-AfterModifiedDate <DateTime>]
[-First <Int32>] [-Skip <Int32>]
  [-SourceConsole <String>] [<CommonParameters>]
```

OnlySecureStorage

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-
ComputerName <String>] [-MaxDate <DateTime>]
  [-MinDate <DateTime>] [-Site <String>] [-CollectionId <Int32>] [-
BackupComponents <BackupComponents>]
  [-IncludeDeleted] [-OnlySecureStorage] [-AfterModifiedDate <DateTime>] [-
First <Int32>] [-Skip <Int32>]
  [-SourceConsole <String>] [<CommonParameters>]
```

DESCRIPTION

Retrieves the backup object for the backups registered in the Recovery Manager backup registration database.

EXAMPLES

Example 1

```
PS C:\> Get-RMADBackup | Where-Object {$_.ComputerName -eq
"dc1.dom1.local"}
```

This command retrieves all backup objects and passes them to the Where-Object cmdlet. The Where-Object cmdlet outputs the backup objects whose ComputerName property value is dc1.dom1.local.

Example 2

```
PS C:\> Get-RMADBackup -Id 12345
```

Retrieves the backup whose identifier is 12345.

Example 3

```
PS C:\> Get-RMADBackup | Where-Object {($_.Date -gt (Get-Date).AddDays(-5))
-and ($_.Path -like "*Toronto*")}
```

This command retrieves objects that represent backups created by Recovery Manager for Active Directory in the last 5 days. The command retrieves only those backups whose file path includes the word "Toronto".

Example 4

```
PS C:\> Get-RMADBackup -Skip 10 -First 100
```

This command skips the first 10 backups and starts retrieving 100 backups from the 11th one.

PARAMETERS

-AfterModifiedDate

Retrieves the backup objects that were last modified after this date.

Type: DateTime

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-All

When this parameter is present, the cmdlet gets all backup objects registered in the Recovery Manager backup registration database, including those whose file is physically missing. When this parameter is omitted, the cmdlet gets only those backup objects registered in the Recovery Manager backup registration database whose file is physically present.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-BackupComponents

Retrieves the backup objects with the specified components only. If this parameter is not specified, all backup objects are retrieved from the Recovery Manager backup registration database.

Type: BackupComponents

Parameter Sets: (All)

Aliases:

Accepted values: None, ActiveDirectory, Adam, BootFiles, CertificateServer, ClusterQuorum, EnterpriseServices, ForestRecoveryMetadata, GroupMembership, IisMetabase, PerformanceCounters, Registry, CryptoKeys, LdapsCerts, All

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-CollectionId

Retrieves the backup objects for the specified collection only.

Type: Int32

Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ComputerName

Retrieves the backup objects from the specified computer only.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Domain

Retrieves the backup objects for the specified domain only. If this parameter is not specified, all backup objects are retrieved from the Recovery Manager backup registration database.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: True (ByPropertyName)
Accept wildcard characters: False

-Guid

Specifies the GUID of the backup to get.

Type: Guid[]
Parameter Sets: Guid
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
Type: Guid[]
Parameter Sets: Guid_IncludeSecureStorage, Guid_OnlySecureStorage
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Id

Specifies the identifier of the backup to get.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: False

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

Type: Int32[]

Parameter Sets: Id_IncludeSecureStorage, Id_OnlySecureStorage

Aliases:

Required: True

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-IncludeDeleted

When this parameter is present, the cmdlet gets all backup objects from the Recovery Manager backup registration database, including those objects whose status has been marked as Deleted or Unregistered.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-IncludeSecureStorage

When this parameter is present, the cmdlet gets all backup objects from the Recovery Manager backup registration database, including backups stored on Secure Storage servers.

Type: SwitchParameter

Parameter Sets: Id_IncludeSecureStorage, Guid_IncludeSecureStorage

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

Type: SwitchParameter

Parameter Sets: IncludeSecureStorage

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-MaxDate

Retrieves the backup objects after the specified date.

Type: DateTime

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-MinDate

Retrieves the backup objects before the specified date.

Type: DateTime

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-MinimumId

Retrieves backups with identifier greater than a specified number.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-OnlySecureStorage

Return backups stored on a Secure Storage servers.

Type: SwitchParameter

Parameter Sets: Id_OnlySecureStorage, Guid_OnlySecureStorage

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

Type: SwitchParameter

Parameter Sets: OnlySecureStorage

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-Site

Retrieves the backup objects from the specified AD site

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-SourceConsole

Retrieves backups replicated from a specified console.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Skip

Specifies the number of backups to skip before starting retrieving.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-First

Specifies the number of backups to retrieve.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Get-RMADBackupAgent

SYNOPSIS

Retrieves objects that represent Recovery Manager Backup Agents, or discovers manually preinstalled Recovery Manager Backup Agents.

SYNTAX

```
Get-RMADBackupAgent [-Discover] [-UpdateInfo] [<CommonParameters>]
```

DESCRIPTION

Allows you to retrieve a list of installed and registered in the Recovery Management Console Backup Agents. It also allows you to discover all Backup Agent instances that were manually preinstalled on computers.

EXAMPLES

Example 1

```
PS C:\> Get-RMADBackupAgent
```

This code returns a list of installed and registered in the Recovery Management Console Backup Agents.

Example 2

```
PS C:\> Get-RMADBackupAgent -Discover
```

This code discovers all Backup Agent instances that were manually preinstalled on computers. Note that after the discover operation completes, you can view and manage the discovered Backup Agent instances using the corresponding cmdlets or from the Backup Agent Management node in the Recovery Manager Console.

PARAMETERS

-Discover

Specifies whether Backup Agent instances that were manually preinstalled on computers should be discovered.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-UpdateInfo

Specifies whether Backup Agents information should be re-requested.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Get-RMADBackupInfo

SYNOPSIS

Gets the content of the backups held at a specified location.

SYNTAX

Bkf

```
Get-RMADBackupInfo [-Path] <String[]> [-BackupPassword <SecureString>] [-IgnoreReadOnly] [<CommonParameters>]
```

OfflineDit

```
Get-RMADBackupInfo [-Path] <String[]> [-SysvolPath <String[]>] [-ResolveIndexes <Boolean>] [-OfflineDit] [-IgnoreReadOnly] [<CommonParameters>]
```

BackupInfo

```
Get-RMADBackupInfo [-BackupPassword <SecureString>] [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

The Get-RMADBackupInfo cmdlet gets the content of the backups created with Recovery Manager and held at the location specified by the path.

EXAMPLES

Example 1

```
PS C:\> $b = Get-ChildItem C:\Backups -Filter *.bkf -Recurse | Get-RMADBackupInfo
```

```
C:\PS>Where-Object -InputObject $b { $_.Contents -band 64 } | Add-RMADBackup
```

This command gets the content of all backups held in the C:\Backups folder and its subfolders, and saves the content in the \$b variable. The Where-Object cmdlet then passes the Active Directory backups from the \$b variable to the Add-Backup cmdlet (the number 64 stands for the Active Directory component.) Add-RMADBackup then registers the passed Active Directory backups in the Recovery Manager database.

Example 2

```
PS C:\> $p = Read-Host "Backup Password" -AsSecureString
```

```
C:\PS>Get-RMADBackupInfo C:\Backups\password-protected_backup1.bkf -BackupPassword $p
```

In this example, the Read-Host cmdlet provided by Windows PowerShell gets the backup password as a SecureString object and saves it in the \$p variable. The Get-RMADBackupInfo then uses the password saved in the \$p variable to access the password-protected backup C:\Backups\password-protected_backup1.bkf.

PARAMETERS

-BackupPassword

Specifies the password to access a password-protected backup. This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString
Parameter Sets: Bkf, BackupInfo
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-OfflineDit

Specifies that the application registers the DIT file as a backup.

Type: SwitchParameter
Parameter Sets: OfflineDit
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Path

Specifies the path to the backups whose content is to be retrieved.

Type: String[]
Parameter Sets: Bkf, OfflineDit
Aliases: FullName

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-ResolveIndexes

Reindexes the DIT file in case of invalid index data.

Type: Boolean

Parameter Sets: OfflineDit

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-SysvolPath

Path to the SYSVOL folder.

Type: String[]

Parameter Sets: OfflineDit

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Get-RMADBackupObject

SYNOPSIS

Get objects from backups

SYNTAX

InputObject+Name (Default)

```
Get-RMADBackupObject -InputObject <BackupInfo[]> [-Name <String[]>] [-BackupPassword <SecureString>] [-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-KeepBackupUnpacked] [-AdLdsInstance <String[]>] [<CommonParameters>]
```

InputObject+Id

```
Get-RMADBackupObject -InputObject <BackupInfo[]> [-Id <String[]>] [-BackupPassword <SecureString>] [-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-KeepBackupUnpacked] [-AdLdsInstance <String[]>] [<CommonParameters>]
```

InputObject+Filter

```
Get-RMADBackupObject -InputObject <BackupInfo[]> [-Filter <String>] [-BackupPassword <SecureString>] [-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-KeepBackupUnpacked] [-AdLdsInstance <String[]>] [<CommonParameters>]
```

BackupGuid+Id

```
Get-RMADBackupObject -BackupGuid <Guid[]> [-Id <String[]>] [-BackupPassword <SecureString>] [-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-KeepBackupUnpacked] [-AdLdsInstance <String[]>] [<CommonParameters>]
```

BackupGuid+Name

```
Get-RMADBackupObject -BackupGuid <Guid[]> [-Name <String[]>] [-BackupPassword <SecureString>] [-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-KeepBackupUnpacked] [-AdLdsInstance <String[]>] [<CommonParameters>]
```

BackupGuid+Filter

```
Get-RMADBackupObject -BackupGuid <Guid[]> [-Filter <String>] [-BackupPassword <SecureString>] [-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-KeepBackupUnpacked]
```

```
[-AdLdsInstance <String[]>] [<CommonParameters>]
```

DESCRIPTION

Retrieves specific objects from certain backups registered with Recovery Manager for Active Directory.

EXAMPLES

Example 1

```
PS C:\> Get-RMADBackup | Get-RMADBackupObject -Name "Adm" -Attribute *
```

Retrieves a list of all backups that are registered in Recovery Manager for Active Directory and then search for the object using ambiguous name resolution. In this example, you will get a list of all objects that have 'Adm' in the beginning of any naming attribute from the 'ANR attribute Set'.

Example 2

```
PS C:\> Get-RMADBackup | Get-RMADBackupObject -SearchBase  
'CN=Partitions,CN=Configuration,DC=CONTOSO,DC=COM' -Filter  
"objectClass='crossRef'"
```

Retrieves a list of objects from the container that is specified in the 'SearchBase' parameter. The objects are filtered by the 'objectClass' attribute.

Example 3

```
PS C:\> Get-RMADBackup | Get-RMADBackupObject -Filter "givenName=Name  
1|Name 2,cn=Smith"
```

Retrieves a list of all registered backups and all objects that have 'Name 1' or 'Name 2' value for the 'givenName' attribute and 'Smith' for the 'CN' attribute.

Example 4

```
PS C:\> Get-RMADObject -Filter  
"distinguishedName='CN=name1,DC=mydomain,DC=com'"
```

Retrieves a list of all registered backups and all objects that have the following distinguished name: CN=name1,DC=mydomain,DC=com.

Example 5

```
PS C:\> Get-RMADBackup | Get-RMADBackupObject -AdLdsInstance  
'ContosoApplication' -Filter  
"distinguishedName='CN=Users,CN=Roles,CN=App1,DC=contoso,DC=com'"
```

Retrieves the object with the specified distinguished name from the backup of the 'ContosoApplication' AD LDS instance.

PARAMETERS

-AdLdsInstance

If you search in the AD LDS instance backup, you should specify a list of AD LDS instances in which you want to search.

```
Type: String[]  
Parameter Sets: (All)  
Aliases: AdamInstance
```

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Attribute

Specifies the object attributes to retrieve in addition to the attributes the cmdlet retrieves by default. If this parameter is omitted or empty, the cmdlet retrieves the following default set of object attributes:

- distinguishedName
- name
- objectClass
- objectguid

Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupGuid

GUID of the registered backup.

Type: Guid[]
Parameter Sets: BackupGuid+Id, BackupGuid+Name, BackupGuid+Filter
Aliases: Guid

Required: True
Position: Named
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False

-BackupPassword

Specifies the password to access a password-protected backup. This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Count

Limits the maximum number of objects to retrieve.

Type: Int32
Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Filter

Allows you to filter objects by attribute names and attribute values. For details, see the examples provided for this cmdlet.

Type: String
Parameter Sets: InputObject+Filter, BackupGuid+Filter
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Id

Specifies the identifier of the object to retrieve. This parameter accepts one of the following:

- GUID
- Distinguished name (DN)
- samAccountName
- userLogonName

Type: String[]
Parameter Sets: InputObject+Id, BackupGuid+Id
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-InputObject

Specifies backups that contain the retrieved object. To get the backup, use the Get-RMADBackup cmdlet.

Type: BackupInfo[]
Parameter Sets: InputObject+Name, InputObject+Id, InputObject+Filter
Aliases: Backup, Backups

Required: True
Position: Named
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-KeepBackupUnpacked

Determines whether to save the unpacked backup after the search operation. If this parameter is not set, the unpacked backup will be deleted after the search operation is completed.

Type: SwitchParameter

Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Name

Retrieves objects whose Name attribute value is equal to the value specified in this parameter.

Type: String[]
Parameter Sets: InputObject+Name, BackupGuid+Name
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SearchBase

Specifies an Active Directory container in which to search for objects. The search is performed in the specified container and all its subcontainers. Specify the distinguished name (DN) of the container in which you want to search.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADBackupSecurityStatus

SYNOPSIS

Gets security check information for a specified backup.

SYNTAX

```
Get-RMADBackupSecurityStatus [-BackupGuid <Guid[]>] [-From <DateTime>]  
[<CommonParameters>]
```

DESCRIPTION

Retrieves security check information for a specified backup registered with Recovery Manager for Active Directory.

EXAMPLES

Example 1

```
PS C:\> $bkf = (Get-RMADBackup -ComputerName dc.DomainName.local)[-1]  
$status = New-Object -TypeName  
QuestSoftware.RecoveryManager.AD.PowerShell.BackupSecurityStatus  
$status.Summary = "Passed"  
$status.Details = "all successful"  
$status.CheckDate = Get-Date  
Publish-RMADBackupSecurityStatus -BackupGuid $bkf.backupGuid -  
SecurityStatus $status  
Get-RMADBackup -ComputerName dc.DomainName.local | %{  
    Get-RMADBackupSecurityStatus -BackupGuid $_.BackupGuid  
}
```

For troubleshooting only. This command retrieves information related to antimalware scan results for all backups registered with Recovery Manager for Active Directory.

PARAMETERS

-BackupGuid

This is the GUID of the backup for which a user wants to get the antimalware scan results.

Type: Guid[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named

Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-From

Specifies the time point to get statuses.

Type: DateTime
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADCollection

SYNOPSIS

Retrieves Recovery Manager computer collection objects or default computer collection settings.

SYNTAX

Name (Default)

```
Get-RMADCollection [[-Name] <String[]>] [<CommonParameters>]
```

Id

```
Get-RMADCollection [-Id] <Int32[]> [<CommonParameters>]
```

Default

```
Get-RMADCollection [-Default] [<CommonParameters>]
```

DESCRIPTION

Allows you to retrieve an existing Recovery Manager computer collection by its name or ID. This cmdlet retrieves all existing computer collections if no collection name or ID is specified. You can also use this cmdlet to retrieve the default computer collection settings that apply to each new computer collection.

EXAMPLES

Example 1

```
PS C:\> Get-RMADCollection
```

This command retrieves all Recovery Manager computer collections.

Example 2

```
PS C:\> (Get-RMADCollection Coll1).Schedule
```

This command retrieves the line containing the schedule for the collection named Coll1.

PARAMETERS

-Default

Allows you to retrieve the default computer collection settings that apply to each new computer collection. Do not use the Name or ID parameter along with this parameter.

```
Type: SwitchParameter  
Parameter Sets: Default  
Aliases:
```

```
Required: True  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Id

Specifies the identifier of the Computer Collection to retrieve.

```
Type: Int32[]  
Parameter Sets: Id  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False
```

-Name

Specifies the name of the computer collection you want to retrieve. In the computer collection name that you type in this parameter, you can use an asterisk as a wildcard symbol for any number of any characters. Do not use the Default parameter along with this parameter.

Type: String[]

Parameter Sets: Name

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Get-RMADCollectionItem

SYNOPSIS

Retrieves information about items contained in specified Recovery Manager for Active Directory computer collections.

SYNTAX

InputObject

```
Get-RMADCollectionItem [-InputObject] <ComputerCollection[]> [-UseCache] [-ComputerInfo] [<CommonParameters>]
```

Name

```
Get-RMADCollectionItem [-UseCache] [-Name] <String[]> [-ComputerInfo]
[<CommonParameters>]
```

Id

```
Get-RMADCollectionItem [-UseCache] [-Id] <Int32[]> [-ComputerInfo]
[<CommonParameters>]
```

DESCRIPTION

Retrieves information about items contained in specified Recovery Manager for Active Directory computer collections. You can use this cmdlet to retrieve information about one of the following:

- Items that were explicitly added to computer collections (such as domain controllers, Active Directory domains, Active Directory sites, organizational units, AD LDS (ADAM) hosts, AD LDS (ADAM) instances, and AD LDS (ADAM) sites).
- Domain controllers and AD LDS (ADAM) hosts that are explicitly or implicitly added to computer collections.

EXAMPLES

Example 1

```
PS C:\> Get-RMADCollectionitem "Computer Collection 02"
```

```
Name           : hal-test-dc.hal-test.dev.hal.ca.qsft
DisplayName     : hal-test-dc.hal-test.dev.hal.ca.qsft
Type           : 4
Domain         : hal-test.dev.hal.ca.qsft
TargetGuid     : 00000000000000000000000000000000
Id             : 2
Components     : 0
ComputerName   : hal-test-dc.hal-test.dev.hal.ca.qsft
Exclusions     : {}
Port           : 0
```

This example retrieves information about items that are explicitly contained in the computer collection named **Computer Collection 02**. These items can include domain controllers, Active Directory domains, Active Directory sites, organizational units, AD LDS (ADAM) hosts, AD LDS (ADAM) instances, and AD LDS (ADAM) sites.

Example 2

```
PS C:\> Get-RMADCollectionitem -Id 2
```

```
Name           : hal-test-dc.hal-test.dev.hal.ca.qsft
DisplayName     : hal-test-dc.hal-test.dev.hal.ca.qsft
Type           : 4
Domain         : hal-test.dev.hal.ca.qsft
TargetGuid     : 00000000000000000000000000000000
Id             : 2
Components     : 0
ComputerName   : hal-test-dc.hal-test.dev.hal.ca.qsft
Exclusions     : {}
Port           : 0
```

Each computer added to the computer collection has an associated identification or **Id**. This example retrieves information about items that are explicitly contained in the Computer Collection identified by the **Id**.

Example 3

```
PS C:\> Get-RMADCollectionitem "Computer Collection 02" -Computerinfo
```

Id	Name	Domain	Components
2	hal-test-dc.hal-test.dev.hal.ca.qsft	hal-test.dev.hal.ca.qsft	63966463

```
PS C:\> Get-RMADCollectionitem "Computer Collection 01" -Computerinfo
```

Id	Name	Domain	Components
2	hal-test-dc.hal-test.dev.hal.ca.qsft	hal-test.dev.hal.ca.qsft	59770111
4	hal-test-srv.hal-test.dev.hal.ca.qsft	hal-test.dev.hal.ca.qsft	524288

These examples retrieve information about the computer items that is explicitly contained in the computer collection named **Computer Collection 02**.

Example 4

```
PS C:\> Get-RMADCollectionitem -Name "Computer Collection 02"
```

```
Name           : hal-test-dc.hal-test.dev.hal.ca.qsft
DisplayName    : hal-test-dc.hal-test.dev.hal.ca.qsft
Type           : 4
Domain        : hal-test.dev.hal.ca.qsft
TargetGuid    : 00000000000000000000000000000000
Id            : 2
Components    : 0
ComputerName  : hal-test-dc.hal-test.dev.hal.ca.qsft
Exclusions    : {}
Port          : 0
```

This example retrieves information about items that are explicitly contained in the computer collection when the **-Name** option is used indicating **Computer Collection 02**.

Example 5

```
PS C:\> $B = "Computer Collection 02"
PS C:\> Get-RMADCollectionitem $B -ComputerInfo
```

Id	Name	Domain	Components
2	hal-test-dc.hal-test.dev.hal.ca.qsft	hal-test.dev.hal.ca.qsft	63966463

This example retrieves information about items that are explicitly contained in the computer collection when the **-InputObject** option is used indicating **Computer Collection 02**.

Example 6

```
PS C:\> Get-RMADCollectionitem -Name "Computer Collection 01" -UseCache
```

```
Name           : hal-test-dc.hal-test.dev.hal.ca.qsft
DisplayName    : hal-test-dc.hal-test.dev.hal.ca.qsft
Type           : 4
Domain        : hal-test.dev.hal.ca.qsft
TargetGuid    : 00000000000000000000000000000000
Id            : 1
```

```

Components      : 0
ComputerName    : hal-test-dc.hal-test.dev.hal.ca.qsft
Exclusions      : {}
Port            : 0

Name            : hal-test-srv.hal-test.dev.hal.ca.qsft
DisplayName     : hal-test-srv.hal-test.dev.hal.ca.qsft
Type            : 5120
Domain          :
TargetGuid      : 00000000000000000000000000000000
Id              : 3
Components      : 0
ComputerName    : hal-test-srv.hal-test.dev.hal.ca.qsft
Exclusions      : {}
Port            : 0

```

This example retrieves information about items that are explicitly contained in the Computer Collection named **Computer Collection 02**. These items returned are a domain controllers, AD LDS (ADAM) host and AD LDS (ADAM) instance. The **-UseCache** options returns any additional data from cache.

PARAMETERS

-ComputerInfo

When present, specifies to retrieve information about the domain controllers and AD LDS (ADAM) hosts that are explicitly or implicitly added to the computer collections you specified in the Collection parameter.

```

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

```

```

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

```

-Id

Specifies the identifier of the computer collection that includes the items you want to retrieve.

```

Type: Int32[]
Parameter Sets: Id
Aliases:

```

```

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

```

-InputObject

Specifies the object representing the computer collections that include the items you want to retrieve.

```

Type: ComputerCollection[]
Parameter Sets: InputObject
Aliases: Collection

```

```

Required: True
Position: 0

```

Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-Name

Specifies the name of the computer collection that includes the items you want to retrieve.

Type: String[]
Parameter Sets: Name
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-UseCache

Specifies to return the data from cache

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADConsoleConfigurationBackup

SYNOPSIS

Retrieves console configuration backups registered for a specified Secure Storage server.

SYNTAX

StorageServerName

```
Get-RMADConsoleConfigurationBackup [-StorageServerName] <String>  
[<CommonParameters>]
```

Server

```
Get-RMADConsoleConfigurationBackup [-Server] <StorageServer>  
[<CommonParameters>]
```

DESCRIPTION

Returns console configuration backups associated with a specified Secure Storage server. For each console configuration backup, the command provides details including the remote file path and the creation timestamp.

EXAMPLES

Example 1

```
PS C:\> Get-RMADStorageServer | Get-RMADConsoleConfigurationBackup
```

Returns console configuration backups for all registered secure storage servers.

Example 2

```
PS C:\> Get-RMADConsoleConfigurationBackup -StorageServerName "storage.srv"
```

Returns console configuration backups for the specified secure storage server.

PARAMETERS

-StorageServerName

Specifies the name of the secure storage server.

Type: String

Parameter Sets: StorageServerName

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-Server

Specifies the secure storage server. Use `Get-RMADStorageServer` to get a list of all secure storage servers.

Type: StorageServer

Parameter Sets: Server

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

System.String

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Get-RMADDeletedObject

SYNOPSIS

Retrieves deleted Active Directory objects.

SYNTAX

Name (Default)

```
Get-RMADDeletedObject [-All] [-Restorable] [-Computer <String>] [-RetrieveOnlyUnpackedBackups] [-ForceBackupRetrieving] [-Name <String[]>] [-Count <Int32>] [-Attribute <String[]>] [-SearchBase <String>] [-Timeout <Int32>] [-UseSsl] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

Identity

```
Get-RMADDeletedObject [-All] [-Restorable] [-Computer <String>] [-RetrieveOnlyUnpackedBackups] [-ForceBackupRetrieving] [-Id <String[]>] [-Attribute <String[]>] [-UseSsl] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

Filter

```
Get-RMADDeletedObject [-All] [-Restorable] [-Computer <String>] [-RetrieveOnlyUnpackedBackups] [-ForceBackupRetrieving] [-Filter <String>] [-Count <Int32>] [-Attribute <String[]>] [-SearchBase <String>] [-Timeout <Int32>] [-UseSsl] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Allows you to retrieve specific deleted or recycled Active Directory objects. The cmdlet retrieves objects from the default naming context or the Active Directory partition you specify. You can only retrieve recycled objects when Microsoft's Active Directory Recycle Bin is enabled in your environment. By default, for each deleted object, this cmdlet retrieves the following attributes:

- GUID
- Distinguished name (DN)
- Name
- objectClass

You can also specify additional attributes you want to retrieve.

EXAMPLES

Example 1

```
PS C:\> Get-RMADDeletedObject
```

This command retrieves all deleted Active Directory objects in the current domain.

Example 2

```
PS C:\> Get-RMADDeletedObject -Name "User 1"
```

This command uses ambiguous name resolution (ANR) to look for and retrieve the deleted objects whose Name attribute value is User 1.

Example 3

```
PS C:\> Get-RMADDeletedObject -Name "User 1" -Attribute usnChanged, usnCreated
```

This command uses ambiguous name resolution (ANR) to look for and retrieve the deleted objects whose Name attribute value is User 1. In addition to the default set of object attributes (that is, GUID, Distinguished name (DN), Name, and objectClass), this command also retrieves the attributes usnChanged and usnCreated.

Example 4

```
PS C:\> Get-RMADDeletedObject -Filter "whenCreated>=20220601123000.0Z"
```

This command retrieves all deleted objects that were created on 1 June 2022 at 12:30:00 or after this date.

Example 5

```
PS C:\> Get-RMADDeletedObject -Filter "whenCreated=20220601000000.0Z"
```

This command retrieves all deleted objects that were created on 1 June 2022 between 00:00:00 and 23:59:59.

Example 6

```
PS C:\> Get-RMADDeletedObject -Filter "distinguishedName='CN=user1\0ADEL:b0806312-d320-41fb-9e4d-ebad82706a74,CN=Deleted Objects,DC=mydomain,DC=com'"
```

Retrieves the deleted object whose distinguished name (DN) is CN=user1\0ADEL:b0806312-d320-41fb-9e4d-ebad82706a74,CN=Deleted Objects,DC=mydomain,DC=com.

Example 7

```
PS C:\> Get-RMADDeletedObject -Name user1 -SearchBase 'OU=Users,DC=domain,DC=com'
```

Gets the deleted object whose Name attribute value is user1 and that was deleted from the container with DN OU=Users,DC=domain,DC=com or from any of its subcontainers.

PARAMETERS

-All

Specifies to retrieve all deleted and recycled Active Directory objects.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases: ShowRecycled
```

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Attribute

Specifies the object attributes to retrieve in addition to the attributes retrieved by default. If this parameter is omitted or empty, the cmdlet retrieves the following default set of object attributes:

- GUID
- Distinguished name (DN)
- Name

- `objectClassTo` specify all available object attributes, type an asterisk (*) in this parameter.

Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Computer

Specifies the computer whose backups contain the deleted object to retrieve.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Count

Limits the maximum number of objects to retrieve.

Type: Int32
Parameter Sets: Name, Filter
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Credential

The user name and password of the user account with which you want to connect, in the form of a `PSCredential` object. Use the `Get-Credential` cmdlet provided by Windows PowerShell to pass a `PSCredential` object to this parameter.

Type: `PSCredential`
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Filter

Allows you to filter objects by attribute names and attribute values. For the syntax this parameter accepts, see the examples provided for this cmdlet.

Type: String
Parameter Sets: Filter

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ForceBackupRetrieving

Retrieves the ID of the backup that contains the deleted object even if this object can be restored using the Active Directory Recycle Bin.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Id

Specifies the identifier of the object to retrieve. This parameter accepts one of the following:

- GUID
- Distinguished name (DN)
- samAccountName
- userLogonName

Type: String[]
Parameter Sets: Identity
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Name

Retrieves objects whose Name attribute value is equal to the value specified in this parameter. The Name attribute stores object's relative distinguished name (RDN) which looks similar to the following:

User 1\0ADEL:7dbac5c7-f38d-4270-8ac2-7a0674bc246b

Type: String[]
Parameter Sets: Name
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Partition

Specifies the distinguished name of the Active Directory partition from which you want to retrieve objects. If this parameter is omitted, the default naming context is used. This parameter is required if you specify an AD LDS (ADAM) instance host in the Server parameter.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Port

Specifies the port number to connect to. If this parameter is set to 0 or omitted, the default LDAP port (389) is used.

Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Restorable

Specifies to retrieve only those objects that can be completely restored. That is, objects located in Microsoft's Active Directory Recycle Bin or in a backup registered with Recovery Manager for Active Directory.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-RetrieveOnlyUnpackedBackups

Retrieves the deleted objects only from the unpacked backups.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-SearchBase

Specifies an Active Directory container in which to search for deleted objects. This is the container from which the objects you want to find were deleted. The search is performed in the specified container and all its subcontainers, including the deleted ones. Specify the distinguished name (DN) of the container in which you want to search.

Type: String
Parameter Sets: Name, Filter
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Server

Specifies the Active Directory domain, domain controller, or AD LDS (ADAM) instance host from which you want the cmdlet to retrieve objects. If this parameter is omitted, the cmdlet retrieves objects from any available domain controller in the current domain. To specify a domain controller or AD LDS (ADAM) instance host, use the computer name or IP address. If you specify an Active Directory domain name in this parameter, deleted objects are retrieved from any available domain controller in the specified domain.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Timeout

Specifies the maximum wait time for retrieving the objects, in seconds. The default value is 30.

Type: Int32
Parameter Sets: Name, Filter
Aliases:

Required: False
Position: Named
Default value: 30
Accept pipeline input: False
Accept wildcard characters: False

-UseSsl

Specifies whether use Secure Sockets Layer (SSL) to encrypt the connection.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFECLOUDStorage

SYNOPSIS

Returns cloud storage registered in Recovery Manager for Active Directory.

SYNTAX

```
Get-RMADFECLOUDStorage [-Id <Int32>] [<CommonParameters>]
```

DESCRIPTION

Returns cloud storage registered in Recovery Manager for Active Directory specified by the Id parameter. Display name, container and type of cloud storage is returned. If no Id parameter provided all registered cloud storages will be returned.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFECLOUDStorage
```

Id	DisplayName	Container	Type
1	MyCloudStorage	adbackups	CloudStorageAzure
2	CompanyStorage	bmrbackups	CloudStorageAzure

Returns all registered cloud storages in Recovery Manager for Active Directory.

Example 2

```
PS C:\> Get-RMADFECLOUDStorage -Id 1
```

Id	DisplayName	Container	Type
1	MyCloudStorage	adbackups	CloudStorageAzure

Retrieve a cloud storage specified by the Id parameter. If no Id parameter provided all registered cloud storages will be returned.

PARAMETERS

-Id

Cloud storage Id that is registered in Recovery Manager for Active Directory.

Type: Int32

Parameter Sets: (All)

Aliases: StorageId

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Get-RMADFECLOUDStorageCollection

SYNOPSIS

Returns computer collections for the cloud storage registered in Recovery Manager for Active Directory.

SYNTAX

Id

```
Get-RMADFECLOUDStorageCollection [-Id] <Int32[]> [-IgnoreReadOnly]
[<CommonParameters>]
```

InputObject

```
Get-RMADFECLOUDStorageCollection [-InputObject] <CloudStorage[]> [-IgnoreReadOnly]
[<CommonParameters>]
```

DESCRIPTION

Returns computer collections for the cloud storage specified in the parameter Id. Each computer collection is returned with collection name, last status result, last run date, next run date and schedule.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFECLOUDStorage
```

Id	DisplayName	Container	Type
1	CloudStorageAF	adbackups	CloudStorageAzure

```
PS C:\>Get-RMADFECLOUDStorageCollection -Id 1
```

Name	LastResult	LastRunDate	NextRunDate	Schedule
Coll01	Success	10/28/2022 16:45	10/28/2022 13:55	{At 4:55 PM every day}

Returns all computer collections for the cloud storage with Id 1.

PARAMETERS

-Id

Cloud storage Id that is registered in Recovery Manager for Active Directory.

Type: Int32[]

Parameter Sets: Id

Aliases: StorageId

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-InputObject

Specifies the CloudStorage object representing the storage.

Type: CloudStorage[]

Parameter Sets: InputObject

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFECLOUDStorageUploadSession

SYNOPSIS

Retrieves the cloud storage upload session details.

SYNTAX

```
Get-RMADFECLOUDStorageUploadSession [-Id <Int32>] [-StorageId <Int32>] [-Limit <Int32>] [<CommonParameters>]
```

DESCRIPTION

Returns the upload sessions details for the specified cloud storage. Each upload session is returned with a status, creation timestamp and error message if available. Using the Limit parameter specify the number of upload sessions to be returned.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFECLOUDStorageUploadSession -StorageId 1 -Limit 1
```

```
Id                : 1  
StorageId         : 1  
BackupId          : 248
```

```
SourceBackupPath      : \\mycomputer.company.ca\Backups\mycomputer-2022-10-28 16-13-51.bkf
TargetBackupPath      : mycomputer.company.ca\Backups\mycomputer-2022-10-28 16-13-51.bkf
ErrorMessage          :
CreationTimestamp     : 10/28/2022 4:14:10 PM
ModificationTimestamp : 10/28/2022 4:14:17 PM
Status                : UploadStatusCompleted
```

Retrieve the latest upload session for the cloud storage with Id 1.

PARAMETERS

-Id

Specifies the upload session Id.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Limit

Maximum number of session to return. When not specified all upload sessions will be returned.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-StorageId

Specifies the cloud storage Id.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Get-RMADFEComputer

SYNOPSIS

Retrieves a list of computer settings from the current RMADFE project.

SYNTAX

```
Get-RMADFEComputer [[-ComputerName] <String>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet retrieves the computer settings for one or more computers from the current RMADFE project. By default, this cmdlet retrieves the following information for each computer:

- Computer Name
- User Name
- DSRM User Name
- Network Share User Name
- Use of Default Domain Settings
- Advanced Settings

EXAMPLES

EXAMPLE 1

```
PS C:\> Get-RMADFEComputer -Name dc1.acme.com
```

This command retrieves information about the specified computer from the current RMADFE project.

EXAMPLE 2

```
PS C:\> Get-RMADFEComputer
```

This command retrieves information about all computers from the current RMADFE project.

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases: Name

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Get-RMADFEConsole

SYNOPSIS

Gets all registered RMAD FE consoles.

SYNTAX

```
Get-RMADFEConsole [<CommonParameters>]
```

DESCRIPTION

Gets all registered in the persistence database RMAD FE consoles.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFEConsole
```

This command gets a list of all FR Console instances registered in the persistence database.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Get- RMADFEConsoleConfigurationBackupSchedule

SYNOPSIS

Returns console configuration backup schedule.

SYNTAX

```
Get-RMADFEConsoleConfigurationBackupSchedule [<CommonParameters>]
```

DESCRIPTION

Returns console configuration backup schedule settings including path and password.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFEConsoleConfigurationBackupSchedule
```

Returns console configuration backup settings.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFEDnsCache

SYNOPSIS

Returns cached DNS records in the Forest Recovery project.

SYNTAX

```
Get-RMADFEDnsCache [<CommonParameters>]
```

DESCRIPTION

This cmdlet returns a list of DNS records saved in the Forest Recovery project.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFEDnsCache
```

This command returns a list of DNS records saved in the Forest Recovery project.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Get-RMADFEDomain

SYNOPSIS

Retrieves the domain settings.

SYNTAX

```
Get-RMADFEDomain [-Domain <String>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet gets the domain settings for one or more domains from the RMADFE project. By default, this cmdlet retrieves the following information for each domain:

- Domain Name
- User Name
- DSRM User Name
- Password Resetting

- Advanced Actions

EXAMPLES

EXAMPLE 1

```
PS C:\> Get-RMADFEDomain -Domain acme.com
```

```
Domain : acme.com
Recover : True
AuthoritativeSysvolRestoreComputer : dcl.acme.com
UserName : Administrator
DsrmsUserName : Administrator
ResetPasswords : False
Groups : {}
Exclusions : {}
PerformMalwareScan : False
DsrmsPause : False
RunDsrmsScriptAction :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.RunScriptDsrmsAction
QuarantineSysvolFilesAction :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.QuarantineFilesDsrms
Action
DoNotRecoverSysvolFilesAction :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.DoNotRecoverFilesDs
rmsAction
```

This command retrieves the domain settings for the specified domain.

EXAMPLE 2

```
PS C:\> Get-RMADFEDomain
```

```
Domain : acme.com
Recover : True
AuthoritativeSysvolRestoreComputer : dcl.acme.com
UserName : Administrator
DsrmsUserName : Administrator
ResetPasswords : False
Groups : {}
Exclusions : {}
PerformMalwareScan : False
DsrmsPause : False
RunDsrmsScriptAction :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.RunScriptDsrmsAction
QuarantineSysvolFilesAction :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.QuarantineFilesDsrms
Action
DoNotRecoverSysvolFilesAction :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.DoNotRecoverFilesDs
rmsAction

Domain : child.acme.com
Recover : True
AuthoritativeSysvolRestoreComputer :
UserName :
DsrmsUserName :
ResetPasswords : True
Groups : {}
Exclusions : {}
```

```

PerformMalwareScan           : True
Dsrmpause                    : False
RunDsrmscriptaction         :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.RunScriptDsrmpauseAction
QuarantineSysvolFilesAction  :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.QuarantineFilesDsrmpauseAction
DoNotRecoverSysvolFilesAction :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.DoNotRecoverFilesDsrmpauseAction

Domain                        : resource.acme.com
Recover                       : True
AuthoritativeSysvolRestoreComputer : dcl.acme.com
Username                      :
Dsrmpause                     :
ResetPasswords                : True
Groups                        : {Group_A, Group_B, Group_C}
Exclusions                    : {User_01, User_02}
PerformMalwareScan           : True
Dsrmpause                    : True
RunDsrmscriptaction         :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.RunScriptDsrmpauseAction
QuarantineSysvolFilesAction  :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.QuarantineFilesDsrmpauseAction
DoNotRecoverSysvolFilesAction :
QuestSoftware.RecoveryManager.AD.ForestRecovery.Project.DoNotRecoverFilesDsrmpauseAction

```

This command retrieves information about all domains from the current RMADFE project.

PARAMETERS

-Domain

Specifies the fully qualified domain name.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Get-RMADFEEEvent

SYNOPSIS

Returns recovery events related to the entire Active Directory forest or a specific domain controller.

SYNTAX

```
Get-RMADFEEvent [[-ComputerName] <String>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet returns recovery events related to the entire Active Directory forest or a specific domain controller.

EXAMPLES

EXAMPLE 1

```
PS C:\> Get-RMADFEEvent -ComputerName dc5.child.acme.test | select -  
ExpandProperty EventDescription | Format-Table  
EventKind,EventMessage,MessageCode
```

This command returns a list of recovery events related to dc5.child.acme.test.

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases:

Required: False
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFEFaultTolerance

SYNOPSIS

Retrieves the fault tolerance settings for the Forest Recovery Console.

SYNTAX

```
Get-RMADFEFaultTolerance [<CommonParameters>]
```

DESCRIPTION

Retrieves the fault tolerance settings that allow recovery to be resumed on another instance of the Forest Recovery Console from the point at which it was interrupted.

EXAMPLES

Example 1

```
PS C:\> $creds = New-Object PSCredential("sa", (ConvertTo-SecureString
"Password" -AsPlainText -Force))
Set-RMADFEFaultTolerance -DataSource "SQLSERVER\SQLEXPRESS" -Credentials
$creds
Set-RMADFEFaultTolerance -Enable
Get-RMADFEFaultTolerance
```

This command configures fault tolerance so that the forest recovery state is saved in the specified Microsoft SQL Server instance, then retrieves the settings.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFEGlobalOptions

SYNOPSIS

Gets global application settings.

SYNTAX

```
Get-RMADFEGlobalOptions [[-Name] <String>] [<CommonParameters>]
```

DESCRIPTION

Retrieves global settings that are applied to all recovery projects by default.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFEGlobalOptions -Name "SMTPServer"
```

This command returns the address of SMTP server.

PARAMETERS

-Name

Specifies the name of the parameter whose value will be returned by the command.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Get-RMADFEOperation

SYNOPSIS

Returns information about the progress of the recovery operations.

SYNTAX

```
Get-RMADFEOperation [[-ComputerName] <String>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet shows progress information for the recovery stages and steps that are applicable to the selected domain controller.

EXAMPLES

EXAMPLE 1

```
PS C:\> Get-RMADFEOperation -ComputerName DC1.rmad.local
```

This command gets the errors that occurred during the recovery session.

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFEPProject

SYNOPSIS

Gets the current status of the RMADFE project.

SYNTAX

```
Get-RMADFEPProject [-ProjectInfo] [<CommonParameters>]
```

DESCRIPTION

This cmdlet gets the current status of the RMADFE project.

EXAMPLES

EXAMPLE 1

```
PS C:\> Get-RMADFEPProject | Format-List *
```

This command gets the current status of the RMADFE project.

PARAMETERS

-ProjectInfo

Specifies to return special project information container

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False

Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFERecoveryAgent

SYNOPSIS

Returns information about Forest Recovery Agents that are installed and registered in Forest Recovery Console.

SYNTAX

ProjectSpecificParameters (Default)

```
Get-RMADFERecoveryAgent [[-ComputerName] <String>] [<CommonParameters>]
```

ProjectlessDomain

```
Get-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential  
<PSCredential> [<CommonParameters>]
```

ProjectlessDsrms

```
Get-RMADFERecoveryAgent [-ComputerName] <String> -DsrmsCredential  
<PSCredential> [<CommonParameters>]
```

ProjectlessLocal

```
Get-RMADFERecoveryAgent [-ComputerName] <String> [-LocalCredential  
<PSCredential>] [<CommonParameters>]
```

ProjectlessAll

```
Get-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential  
<PSCredential> -DsrnCredential <PSCredential>  
[-LocalCredential <PSCredential>] [<CommonParameters>]
```

DESCRIPTION

Allows you to retrieve a list of Forest Recovery Agent instances that are installed and registered in Forest Recovery Console. You can get the agent information for an existing RMADFE project using the user credentials specified in the project or by providing credentials as parameters.

EXAMPLES

EXAMPLE 1

```
PS C:\> Open-RMADFEProject -Path C:\rmadfe.frproj -Password (ConvertTo-  
SecureString "password" -AsPlainText -Force)
```

```
Get-RMADFERecoveryAgent
```

Returns information about all Forest Recovery Agents installed and registered in the RMADFE project.

EXAMPLE 2

```
PS C:\> Open-RMADFEProject -Path C:\rmadfe.frproj -Password (ConvertTo-  
SecureString "password" -AsPlainText -Force)
```

```
Get-RMADFERecoveryAgent -name dc1.RMAD.local
```

Returns information about the Forest Recovery Agent installed on the specified domain controller in the RMADFE project.

EXAMPLE 3

```
PS C:\> $credentials = New-Object PSCredential(".\Administrator",  
(ConvertTo-SecureString 'Password' -AsPlainText -Force))
```

```
Get-RMADFERecoveryAgent -name dc1.RMAD.local -DcCredential $credentials -  
DsrnCredential $credentials
```

Returns information about the Forest Recovery Agent installed on the specified domain controller (either in Normal or DSRM mode). In this example, you should use only domain credentials or DSRM credentials, or both.

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: ProjectSpecificParameters

Aliases:

Required: False

Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
Type: String
Parameter Sets: ProjectlessDomain, ProjectlessDsrn, ProjectlessLocal, ProjectlessAll
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DcCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers in the Normal mode.

Type: PSCredential
Parameter Sets: ProjectlessDomain, ProjectlessAll
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DsrnCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access domain controllers in the selected domain in Directory Services Restore Mode (DSRM).

Type: PSCredential
Parameter Sets: ProjectlessDsrn, ProjectlessAll
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-LocalCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access standalone machines.

Type: PSCredential
Parameter Sets: ProjectlessLocal, ProjectlessAll
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFERecoverySchedule

SYNOPSIS

Gets a schedule for the RMADFE project recovery.

SYNTAX

```
Get-RMADFERecoverySchedule [<CommonParameters>]
```

DESCRIPTION

This cmdlet returns a schedule for recovery of the current RMADFE project.

EXAMPLES

EXAMPLE 1

```
PS C:\> Get-RMADFERecoverySchedule
```

Returns the current project schedule or nothing if the schedule is not configured.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFERecoverySessions

SYNOPSIS

Retrieves a list of verification and recovery sessions for the current RMADFE project.

SYNTAX

```
Get-RMADFERecoverySessions [<CommonParameters>]
```

DESCRIPTION

Retrieves a list of verification and recovery sessions for the current RMADFE project.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFERecoverySessions
```

```
SessionId           : 2025-10-09 01-55-31  
ProjectName         : C:\RMAD_TEMP\FullForestRecovery.frproj  
RecoveryStartDate   : 10/9/2025 1:55:31 AM  
RecoveryFinishDate  :
```

```
SessionState      : InProgress
IsTestMode       : 0
```

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFEReport

SYNOPSIS

Generates an HTML report based on forest recovery project verification or recovery results.

SYNTAX

```
Get-RMADFEReport [-Results] <ProjectSummary> [-Show] [<CommonParameters>]
```

DESCRIPTION

This cmdlet creates an HTML report based on the current status of a forest recovery project. You can generate a verification report or a post-recovery report depending on the project state. If the -Show parameter is specified, the generated report is opened in the default web browser.

EXAMPLES

Example 1

```
PS C:\> Open-RMADFEProject -Path C:\RMADFeProjects\SampleProject.frproj -
Password (ConvertTo-SecureString "project password" -AsPlainText -Force)
Start-RMADFEVerification
$results = Get-RMADFEProject
Get-RMADFEReport -Results $results
```

This example shows how to generate an HTML report from verification results.

Example 2

```
PS C:\> Open-RMADFEProject -Path C:\RMADFeProjects\SampleProject.frproj -
Password (ConvertTo-SecureString "project password" -AsPlainText -Force)
Start-RMADFEVerification
Get-RMADFEProject | Get-RMADFEReport -Show
```

This example creates an HTML report and launches it in the default browser.

PARAMETERS

-Results

Specifies the current status of the forest recovery project.

```
Type: ProjectSummary
Parameter Sets: (All)
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

-Show

Indicates that the generated HTML report should be opened automatically in the default web browser.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

ForestRecovery.Public.ProjectSummary

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFESchedule

SYNOPSIS

Gets a schedule for the RMADFE project verification.

SYNTAX

```
Get-RMADFESchedule [<CommonParameters>]
```

DESCRIPTION

This cmdlet returns a schedule for verification of the current RMADFE project.

EXAMPLES

EXAMPLE 1

```
PS C:\> Get-RMADFESchedule
```

Returns the current project schedule or nothing if the schedule is not configured.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFESTandbyInstances

SYNOPSIS

Retrieves a list of standby instances for the current RMADFE project.

SYNTAX

```
Get-RMADFESTandbyInstances [<CommonParameters>]
```

DESCRIPTION

Retrieves a list of standby instances for the current RMADFE project.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFESTandbyInstances
```

```
SessionId           : 2025-10-09 01-55-31  
ProjectName        : C:\RMAD_TEMP\FullForestRecovery.frproj  
ForestName         : rmad.local  
RecoveryStartDate  : 10/9/2025 1:55:31 AM
```

RecoveryFinishDate :
SessionState : InProgress
DeploymentState : NotDeployed
AzureResourceGroups : forest-recovery-at-standby-2022-sv-20251009-015554
AzureLocations : eastus

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Get-RMADFEVerifySchedule

SYNOPSIS

Gets a schedule for the RMADFE project verification.

SYNTAX

```
Get-RMADFEVerifySchedule [<CommonParameters>]
```

DESCRIPTION

This cmdlet returns a schedule for verification of the current RMADFE project.

EXAMPLES

EXAMPLE 1

```
PS C:\> Get-RMADFEVerifySchedule
```

Returns the current project schedule or nothing if the schedule is not configured.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADGlobalOptions

SYNOPSIS

Sets global settings for the application.

SYNTAX

```
Get-RMADGlobalOptions [[-Name] <String>] [<CommonParameters>]
```

DESCRIPTION

Sets Recovery Manager for Active Directory global settings.

EXAMPLES

Example 1

```
PS C:\> Get-RMADGlobalOptions -Name "UnpackingPath"
```

This cmdlet returns the value of the "UnpackingPath" global option.

Example 2

```
PS C:\> Get-RMADGlobalOptions "UnpackingPath"
```

This cmdlet also can return the value of the "UnpackingPath" global option.

Example 3

```
PS C:\> Get-RMADGlobalOptions
```

This code returns a HashTable which contains the name and value of all global options.

PARAMETERS

-Name

Specifies the name to the option whose value is retrieved.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Get-RMADHybridRecoveryDomainOptions

SYNOPSIS

Gets the domain systems associated with the Hybrid Connector.

SYNTAX

```
Get-RMADHybridRecoveryDomainOptions [<CommonParameters>]
```

DESCRIPTION

Returns the domain and associated systems used in the Hybrid Connector.

EXAMPLES

Example 1

```
PS C:\>Get-RMADHybridRecoveryDomainOptions
```

```
Id                : 6
Name              : hal-test.dev.hal.ca.qsft
PrimaryComputerId : 5
Username         : hal-test\master
Computers        : {ID: 5, Name: hal-test-dc.hal-test.dev.hal.ca.qsft,
                  ID: 7, Name: hal-test-srv.hal-test.dev.hal.ca.qsft}
```

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADHybridRecoveryOptions

SYNOPSIS

Gets the information related to the Hybrid Connector.

SYNTAX

```
Get-RMADHybridRecoveryOptions [<CommonParameters>]
```

DESCRIPTION

Returns the information related to the Hybrid Connector. This includes the data contained in the file received or exported from On Demand Recovery (ODR) used to establish the connection. Also included is the host name of the system that is connected to the ODB via the Hybrid Connector and the status of the connector.

EXAMPLES

Example 1

```
PS C:\>Get-RMADHybridRecoveryOptions
```

```
Enabled           : True
RelayUrl          : https://backupaad-rmaz-hybrid-
                  us.servicebus.windows.net/org-
                  05843ce6-cdde-a9c1-d228-70
                  983618c6cb
RelayKeyName      : listenKey
AADConnectHost    : hal-test-dc
AADConnectUsername : hal-test\master
```

```
UseAgentlessMethod           : True
UsePackedBackups             : True
SkipReplication              : False
AutomaticallyConfigureFirewall : False
Status                       : Completed: True, Failed: False, Relay
                              Error: '', AAD Connect Error: ''
```

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADLicenseInfo

SYNOPSIS

Retrieves information about the installed license key file.

SYNTAX

```
Get-RMADLicenseInfo [<CommonParameters>]
```

DESCRIPTION

Allows you to retrieve information about the installed license key file including the following fields:

- aboutText
- purchased
- allocated
- expirationDate
- managedUsers
- isDemo
- isForestRecoveryLicensed
- isOrwAgentModeDisabled

EXAMPLES

Example 1

```
PS C:\> Get-RMADLicenseInfo
```

```
AboutText           :
Purchased           : 6000
Allocated            : 4980
ExpirationDate       : 12/30/2025 12:00:00 AM
IsDemo               : False
IsForestRecoveryLicensed : True
IsDisasterRecoveryLicensed : True
LicenseNumber        : 123-456-789
IsInstalled          : True
ManagedUsers        : -1
```

This code returns all information about the license.

Example 2

```
PS C:\> (Get-RMADLicenseInfo).Allocated
4980
```

This code returns the number of already allocated licenses.

Example 3

```
PS C:\> (Get-RMADLicenseInfo).Purchased
6000
```

This code returns the number of purchased licenses.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Get-RMADObject

SYNOPSIS

Retrieves specific objects from Active Directory or certain backups registered with Recovery Manager for Active Directory.

SYNTAX

Name (Default)

```
Get-RMADObject [-KeepBackupUnpacked] [-State <ObjectState>] [-Backup <Guid[]>] [-BackupPassword <SecureString>] [-DisableADSearch] [-Name <String[]>] [-Count <Int32>] [-Attribute <String[]>] [-SearchBase <String>] [-Timeout <Int32>] [-UseSsl] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

Identity

```
Get-RMADObject [-KeepBackupUnpacked] [-State <ObjectState>] [-Backup <Guid[]>] [-BackupPassword <SecureString>] [-DisableADSearch] [-Id <String[]>] [-Attribute <String[]>] [-UseSsl] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

Filter

```
Get-RMADObject [-KeepBackupUnpacked] [-State <ObjectState>] [-Backup <Guid[]>] [-BackupPassword <SecureString>] [-DisableADSearch] [-Filter <String>] [-Count <Int32>] [-Attribute <String[]>] [-SearchBase <String>]
```

```
[-Timeout <Int32>] [-UseSsl] [-Server <String>] [-Credential  
<PSCredential>] [-Partition <String>]  
[-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Allows you to retrieve specific objects from Active Directory or certain backups registered with Recovery Manager for Active Directory. By default, with each object, this cmdlet retrieves the following attributes:

- distinguishedName
- name
- objectClass
- objectguid
- isDeleted
- isRecycled

If the object is deleted, in addition to the above-listed attributes, the cmdlet also retrieves the following attributes:

- whenchanged
- whencreated
- lastKnownParent
- msDS
- LastKnownRDN

You can also specify additional attributes to retrieve.

EXAMPLES

Example 1

```
PS C:\> Get-RMADObject -Name "User 1"
```

This command uses ambiguous name resolution (ANR) to look for and retrieve the objects whose Name attribute value is User 1.

Example 2

```
PS C:\> $b = Get-RMADBackup
```

```
C:\PS>Get-RMADObject -DisableADSearch -Backup $b -Name "User 1"  
-Attribute *
```

In the first line of this command, the Get-RMADBackup gets all backups registered with Recovery Manager for Active Directory and stores the backup objects in the \$b variable.

Example 3

```
PS C:\> Get-RMADObject -Name "User 1" -State Live, Deleted -Attribute  
usnChanged, usnCreated
```

This command uses ambiguous name resolution (ANR) to look for and retrieve objects whose Name attribute value is User 1 and whose state is either live or deleted. In addition to the default attribute set, the command retrieves the usnChanged and usnCreated attributes for each object.

Example 4

```
PS C:\> Get-RMADObject -Filter "givenName=User 1|User 2,sn=Smith"
```

This command retrieves the objects whose givenName attribute value is either User 1 or User 2 and whose sn attribute value is Smith.

Example 5

```
PS C:\> Get-RMADObject -Filter "whenCreated>=20220601123000.0Z"
```

This command retrieves all objects that were created on 1 June 2022 at 12:30:00 or after this date.

Example 6

```
PS C:\> Get-RMADObject -Filter "whenCreated=20220601000000.0Z"
```

This command retrieves all objects that were created on 1 June 2022 between 00:00:00 and 23:59:59.

Example 7

```
PS C:\> Get-RMADObject -Filter  
"distinguishedName='CN=user1,DC=mydomain,DC=com'"
```

Retrieves the object whose distinguished name (DN) is CN=user1,DC=mydomain,DC=com.

Example 8

```
PS C:\> Get-RMADObject -Name user1 -State live -SearchBase  
'OU=Users,DC=domain,DC=com'
```

Gets the object whose Name attribute value is user1 and that is located in the container with DN OU=Users,DC=domain,DC=com or in any of its subcontainers.

PARAMETERS

-Attribute

Specifies the object attributes to retrieve in addition to the attributes the cmdlet retrieves by default. If this parameter is omitted or empty, the cmdlet retrieves the following default set of object attributes:

- distinguishedName
- name
- objectClass
- objectguid
- isDeleted
- isRecycled

To specify all available object attributes, type an asterisk (*) in this parameter.

```
Type: String[]  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Backup

Specifies the backup that contains the object to retrieve. To specify a backup, type the backup GUID in this parameter or use the Get-RMADBackup cmdlet.

```
Type: Guid[]  
Parameter Sets: (All)  
Aliases:
```

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupPassword

Specifies the password to access the password-protected backup that contains the object you want to retrieve.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Count

Limits the maximum number of objects to retrieve.

Type: Int32
Parameter Sets: Name, Filter
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Credential

The user name and password of the user account with which you want to connect, in the form of a `PSCredential` object. Use the `Get-Credential` cmdlet provided by Windows PowerShell to pass a `PSCredential` object to this parameter.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DisableADSearch

When present, specifies to search Active Directory for objects to retrieve.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Filter

Allows you to filter objects by attribute names and attribute values. For the syntax this parameter accepts, see the examples provided for this cmdlet.

Type: String
Parameter Sets: Filter
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Id

Specifies the identifier of the object to retrieve. This parameter accepts one of the following:

- GUID
- Distinguished name (DN)
- samAccountName
- userLogonName

Type: String[]
Parameter Sets: Identity
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-KeepBackupUnpacked

Determines whether to save the unpacked backup after the search operation. If this parameter is not set, the unpacked backup will be deleted after the search operation is completed.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Name

Retrieves objects whose Name attribute value is equal to the value specified in this parameter. The Name attribute stores object's relative distinguished name (RDN) which looks similar to the following:

User 1\0ADEL:7dbac5c7-f38d-4270-8ac2-7a0674bc246b

Type: String[]

Parameter Sets: Name

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Partition

Specifies the distinguished name of the Active Directory partition from which you want to retrieve objects. If this parameter is omitted, the default naming context is used. This parameter is required if you specify an AD LDS (ADAM) instance host in the Server parameter

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Port

Specifies the port number to connect to. If this parameter is set to 0 or omitted, the default LDAP port (389) is used.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-SearchBase

Specifies an Active Directory container in which to search for objects. The search is performed in the specified container and all its subcontainers. Specify the distinguished name (DN) of the container in which you want to search.

Type: String

Parameter Sets: Name, Filter

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Server

Specifies the Active Directory domain, domain controller, or AD LDS (ADAM) instance host from which you want the cmdlet to retrieve objects. If this parameter is omitted, the cmdlet retrieves objects from any available domain controller in the current domain. To specify a domain controller or AD LDS (ADAM) instance host, use the computer name or IP address. If you specify an Active Directory domain name in this parameter, the cmdlet retrieves objects from any available domain controller in the specified domain.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-State

Retrieves objects whose state is equal to any of the values specified in this parameter. This parameter can take one of the following values:

- All
- Deleted
- Live
- Recycled

When specifying multiple values in this parameter, use a comma as a separator.

Type: ObjectState

Parameter Sets: (All)

Aliases:

Accepted values: Live, Deleted, Recycled, All

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Timeout

Specifies the maximum wait time for retrieving the objects, in seconds. The default value is 30.

Type: Int32

Parameter Sets: Name, Filter

Aliases:

Required: False

Position: Named

Default value: 30

Accept pipeline input: False

Accept wildcard characters: False

-UseSsl

Specifies whether use Secure Sockets Layer (SSL) to encrypt the connection.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADReplicationConsole

SYNOPSIS

Gets all the RMAD consoles in the replication console list.

SYNTAX

```
Get-RMADReplicationConsole [<CommonParameters>]
```

DESCRIPTION

Gets all the RMAD consoles in the replication console list.

EXAMPLES

Example 1

```
PS C:\> C:\>Get-RMADReplicationConsole
```

This command gets all the RMAD consoles in the replication console list.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADReplicationSchedule

SYNOPSIS

Allows you to get the replication schedule from a specified computer.

SYNTAX

```
Get-RMADReplicationSchedule [<CommonParameters>]
```

DESCRIPTION

Allows you to get the replication schedule from a specified computer.

EXAMPLES

Example 1

```
PS C:\> Get-RMADReplicationSchedule
```

This example illustrates how to get the replication schedule from a specified computer.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADReplicationSession

SYNOPSIS

Retrieves information about replication sessions.

SYNTAX

```
Get-RMADReplicationSession [[-Id] <Int32[]>] [<CommonParameters>]
```

DESCRIPTION

Retrieves replication sessions. Each replication session contains a set of properties including the session start time, end time, and replication result.

EXAMPLES

Example 1

```
PS C:\> Get-RMADReplicationSession
```

This command retrieves all the replication sessions.

Example 2

```
PS C:\> Get-RMADReplicationSession -Id 1
```

This command retrieves the replication session by session ID.

PARAMETERS

-Id

Specifies the IDs of the replication sessions.

Type: Int32[]

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Get-RMADReplicationSessionItem

SYNOPSIS

Retrieves a list of remote consoles that are involved in the specified replication session.

SYNTAX

Session

```
Get-RMADReplicationSessionItem [-Session] <ReplicationSession>  
[<CommonParameters>]
```

Id

```
Get-RMADReplicationSessionItem [-SessionId] <Int32> [<CommonParameters>]
```

DESCRIPTION

Retrieves a list of remote consoles that are involved in the specified replication session.

EXAMPLES

Example 1

```
PS C:\> Get-RMADReplicationSession -Id 1 | Get-RMADReplicationSessionItem
```

This command retrieves the remote consoles that are involved in the replication session whose ID is 1.

PARAMETERS

-Session

Specifies the replication session for which you want to return a list of remote consoles.

```
Type: ReplicationSession  
Parameter Sets: Session  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

-SessionId

Specifies the replication session ID for which you want to return a list of remote consoles.

```
Type: Int32  
Parameter Sets: Id  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADReportObject

SYNOPSIS

Retrieves an object representing the online comparison or restore operation item.

SYNTAX

```
Get-RMADReportObject [-SessionId <Int32[]>] [<CommonParameters>]
```

DESCRIPTION

Retrieves an object representing the online comparison or restore operation item.

EXAMPLES

Example 1

```
PS C:\> Get-RMADReportObject
```

This command retrieves an object representing the online comparison or restore operation item.

Example 2

```
PS C:\> Get-RMADReportObject | Get-RMADReportObjectAttributes
```

This command retrieves an object representing the online comparison operation item attributes.

PARAMETERS

-SessionId

Specifies the compare or restore session identifier from which to get changed or restored objects. If this parameter is not set, the latest compare or restore session will be used.

Type: Int32[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: True (ByPropertyName)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Get-RMADReportObjectAttributes

SYNOPSIS

Retrieves an object representing the online comparison or restore operation item attributes.

SYNTAX

```
Get-RMADReportObjectAttributes -ObjectId <Int32[]> [<CommonParameters>]
```

DESCRIPTION

Retrieves an object representing the online comparison or restore operation item attributes.

EXAMPLES

Example 1

```
PS C:\> Get-RMADReportObject | Get-RMADReportObjectAttributes
```

This command retrieves an object representing the online comparison operation item attributes.

PARAMETERS

-ObjectId

Specifies changed or restored object identifier. To get the object, use the `Get-RMADReportObject` cmdlet.

Type: `Int32[]`

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: True (ByPropertyName)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: `QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml`

Module Name: `Quest.RecoveryManager.AD.PowerShell`

online version:

schema: 2.0.0

Get-RMADReportObjectChildren

SYNOPSIS

Retrieves an object representing the online comparison or restore operation item child items.

SYNTAX

```
Get-RMADReportObjectChildren -ObjectId <Int32[]> [<CommonParameters>]
```

DESCRIPTION

Retrieves an object representing the online comparison or restore operation item child items.

EXAMPLES

Example 1

```
PS C:\> Get-RMADReportObject | Get-RMADReportObjectChildren
```

This command retrieves an object representing the online comparison or restore operation item child items.

PARAMETERS

-ObjectId

Specifies changed or restored object identifier. To get the object, use the `Get-RMADReportObject` cmdlet.

Type: Int32[]

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: True (ByPropertyName)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Get-RMADReportSession

SYNOPSIS

Retrieves an object representing the online comparison or restore operation report.

SYNTAX

```
Get-RMADReportSession [-SessionId <Int32>] [<CommonParameters>]
```

DESCRIPTION

Retrieves an object representing the online comparison or restore operation report.

EXAMPLES

Example 1

```
PS C:\> Get-RMADReportSession | Sort OperationDate
```

This command retrieves an object representing the online comparison or restore operation report. The report data is sorted by date.

PARAMETERS

-SessionId

Specifies the compare or restore session identifier.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADSession

SYNOPSIS

Retrieves an object representing Recovery Manager backup sessions.

SYNTAX

collection (Default)

```
Get-RMADSession [[-Collection] <ComputerCollection[]>] [-Result  
<SessionResult[]>] [-UseCache]  
[-DayCount <Int32>] [-StartType <SessionStartType>] [<CommonParameters>]
```

collectionId

```
Get-RMADSession [[-CollectionId] <Int32[]>] [-Result <SessionResult[]>] [-  
UseCache] [-DayCount <Int32>]  
[-StartType <SessionStartType>] [<CommonParameters>]
```

collectionName

```
Get-RMADSession [[-CollectionName] <String[]>] [-Result <SessionResult[]>]
[-UseCache] [-DayCount <Int32>]
[-StartType <SessionStartType>] [<CommonParameters>]
```

DESCRIPTION

Retrieves an object representing one or more Recovery Manager backup sessions for a specified Computer Collection. The retrieved object has such properties as names of the domain controllers that participated in the backup session, names of the domains to which the domain controllers belong, backup session result, and error messages, if any, encountered during the backup session.

EXAMPLES

Example 1

```
PS C:\> Get-RMADSession -CollectionName coll -Result Error,Warning
-DayCount 5
```

Returns backup sessions that ended with an error or warning and started in the recent 5 days for the Computer Collection named coll.

Example 2

```
PS C:\> Get-RMADSession -CollectionName "Collection1"
```

Returns all backup sessions for the Computer Collection named Collection1.

PARAMETERS

-Collection

Specifies the name of the computer collection for which you want to retrieve backup sessions.

```
Type: ComputerCollection[]
Parameter Sets: collection
Aliases:
```

```
Required: False
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

-CollectionId

Specifies the ID of the computer collection for which you want to retrieve backup sessions.

```
Type: Int32[]
Parameter Sets: collectionId
Aliases:
```

```
Required: False
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-CollectionName

Specifies the name of the computer collection for which you want to retrieve backup sessions.

Type: String[]
Parameter Sets: collectionName
Aliases:

Required: False
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DayCount

Specifies the number of days within which the sessions you want to retrieve started. If you omit this parameter, sessions are retrieved regardless of when they started.

Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Result

Retrieves backup sessions based on their result. If you omit this parameter, sessions are retrieved regardless of their result. This parameter can take one of the following values:

- Success
- Error
- Warning
- Unknown
- Running
- Canceled
- Abandoned
- Pending
- Verifying
- Installing
- Working

Type: SessionResult[]
Parameter Sets: (All)
Aliases:
Accepted values: Success, Error, Warning, Unknown, Running, Canceled, Abandoned, Pending, Verifying, Installing, Working

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-StartType

Specifies to return either scheduled backup sessions or backup sessions that were started manually. This parameter can take one of the following values:

- Manual - Specifies to return backup sessions that were started manually.
- Scheduled - Specifies to return scheduled backup sessions.

Type: SessionStartType
Parameter Sets: (All)
Aliases:
Accepted values: Manual, Scheduled

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-UseCache

Specifies to return the data from the cache.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADSessionItem

SYNOPSIS

Gets items from a specified backup creation session.

SYNTAX

session (Default)

```
Get-RMADSessionItem [-Session <Session[]>] [-Result <SessionResult[]>]  
[<CommonParameters>]
```

sessionId

```
Get-RMADSessionItem [-SessionId <Int32[]>] [-Computer <String[]>] [-Result  
<SessionResult[]>]  
[<CommonParameters>]
```

DESCRIPTION

Gets items from a specified backup creation session.

EXAMPLES

Example 1

```
PS C:\> Get-RMADSessionItem -Computer "Comp*"
```

This command gets all session items from all backup creation sessions created for the computers whose name starts with Comp.

PARAMETERS

-Computer

Gets items from the backup creation sessions run for the computer whose name specified in this parameter. This parameter accepts the asterisk (*) wildcard.

```
Type: String[]  
Parameter Sets: sessionId  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Result

Gets items from the backup creation sessions that completed with the result specified in this parameter.

Type: SessionResult[]

Parameter Sets: (All)

Aliases:

Accepted values: Success, Error, Warning, Unknown, Running, Canceled, Abandoned, Pending, Verifying, Installing, Working

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Session

Specifies the backup creation session from which to get session items.

Type: Session[]

Parameter Sets: session

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-SessionId

Specifies the identifier of the backup creation session from which to get session items.

Type: Int32[]

Parameter Sets: sessionId

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADSessionItemEvent

SYNOPSIS

Gets events from a specified backup creation session item.

SYNTAX

sessionItem (Default)

```
Get-RMADSessionItemEvent [[-SessionItem] <SessionItem[]>] [-Type  
<EventType[]>] [<CommonParameters>]
```

sessionItemId

```
Get-RMADSessionItemEvent [[-SessionItemId] <Int32[]>] [-Type <EventType[]>]  
[<CommonParameters>]
```

DESCRIPTION

Gets events from a specified backup creation session item.

EXAMPLES

Example 1

```
PS C:\> Get-RMADSessionItemEvent -Type Warning
```

Gets all Warning events for all backup creation sessions.

PARAMETERS

-SessionItem

Specifies the backup creation session item from which to get events.

Type: SessionItem[]
Parameter Sets: sessionItem
Aliases:

Required: False
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-SessionItemId

Specifies the identifier of the backup creation session item from which to get events.

Type: Int32[]
Parameter Sets: sessionItemId
Aliases:

Required: False
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Type

Specifies the types of events to get. This parameter accepts the following values for event types:

- Information
- Warning
- Error

When specifying multiple event types, use a comma as a separator.

Type: EventType[]
Parameter Sets: (All)
Aliases:
Accepted values: Information, Warning, Error

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Get-RMADStorageServer

SYNOPSIS

Returns a list of registered secure storage servers.

SYNTAX

```
Get-RMADStorageServer [[-Name] <String>] [<CommonParameters>]
```

DESCRIPTION

Returns a list of currently registered secure storage servers.

EXAMPLES

Example 1

```
PS C:\> Get-RMADStorageServer
```

Displays the list of currently registered storage servers.

Example 2

```
PS C:\> Get-RMADStorageServer -Name storage.local
```

Displays a secure storage server with the 'storage.local' name, if any.

PARAMETERS

-Name

Specifies the name of a secure storage server to display.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

String

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Import-RMADBackup

SYNOPSIS

Reads the backup registration information from the .xml file and returns backup descriptions in the BackupInfo objects.

SYNTAX

Paths

```
Import-RMADBackup [-Path] <String[]> [-IgnoreReadOnly] [<CommonParameters>]
```

Definition

```
Import-RMADBackup -Definition <String> [-IgnoreReadOnly]
[<CommonParameters>]
```

DESCRIPTION

Reads the backup registration information from the .xml file and returns backup descriptions in the BackupInfo objects. After you import backups, you need to register them with Recovery Manager so that the backups become available in the Recovery Manager user interface. To register the backups, use the Add-RMADBackup cmdlet.

EXAMPLES

Example 1

```
PS C:\> Import-RMADBackup C:\ImportedBackups\RMADBackups.xml | Add-
RMADBackup
```

Imports backups from the C:\ImportedBackups\RMADBackups.xml file to the Recovery Manager for Active Directory backup registration database on the computer where you are using this cmdlet.

Then, the Add-RMADBackup registers the imported backups with Recovery Manager for Active Directory.

PARAMETERS

-Definition

Specifies the registration information about the backups you want to import into the Recovery Manager for Active Directory backup registration database.

```
Type: String
Parameter Sets: Definition
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-Path

Specifies the path to the .xml file that contains the registration information about the backups you want to import into the Recovery Manager for Active Directory backup registration database.

```
Type: String[]
```

Parameter Sets: Paths
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Import-RMADFERecoveryCertificate

SYNOPSIS

Imports Forest Recovery certificates.

SYNTAX

```
Import-RMADFERecoveryCertificate [-Path] <String> [-Password]  
<SecureString> [<CommonParameters>]
```

DESCRIPTION

This cmdlet imports Forest Recovery certificates from the specified location. You must also supply the password that is used to protect the certificates.

EXAMPLES

EXAMPLE 1

```
PS C:\> Import-RMADFERecoveryCertificate -Path  
C:\Certificates\RMADFeCertificates.pfx" -Password (ConvertTo-SecureString  
"protection password" -AsPlainText -Force)
```

This command imports Forest Recovery certificates from the specified location.

PARAMETERS

-Password

Specifies the password that is used to access the Forest Recovery certificates.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Path

Specifies the full path to the Forest Recovery certificate file.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Install-RMADBackupAgent

SYNOPSIS

Installs Recovery Manager Backup Agent on a specified computer or on each computer in a particular Computer Collection.

SYNTAX

DC

```
Install-RMADBackupAgent [-Computer] <String> [[-Credentials]  
<PSCredential>] [[-ConfigureFirewall] <Boolean>  
[-IgnoreReadOnly] [<CommonParameters>]
```

Collection

```
Install-RMADBackupAgent [[-Credentials] <PSCredential>] [[-  
ConfigureFirewall] <Boolean>  
[-CollectionName] <String> [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Allows you to install the Recovery Manager Backup Agent on a specified computer which can be a domain controller or AD LDS (ADAM) host, or on each computer in a particular Computer Collection.

EXAMPLES

Example 1

```
PS C:\> $credential = Get-Credential  
Install-RMADBackupAgent -Computer dc1 -Credentials $credential
```

This code connects to the computer "dc1" under the user represented by the "credential" object and installs Recovery Manager Backup Agent there.

Example 2

```
PS C:\> Install-RMADBackupAgent -CollectionName "New Computer Collection"
```

This code installs the Recovery Manager Backup Agent on each computer in the collection named "New Computer Collection".

PARAMETERS

-CollectionName

Specifies the name of the Computer Collection that includes the computers on which Backup Agent should be installed.

Type: String
Parameter Sets: Collection
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Computer

Specifies the name of the computer which can be domain controller or AD LDS (ADAM) host, where to install a Recovery Manager Backup Agent.

Type: String
Parameter Sets: DC
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ConfigureFirewall

Specifies whether Recovery Manager automatically configures Windows Firewall on domain controllers to allow backup operations.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Credentials

Specifies the user name and the password of the user account to use for connecting to the target computer and installing Backup Agent. Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Notes:

- The user should be a local Administrator on the target computer.
- If you omit this parameter, Backup Agent will be installed under the current user account.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Install-RMADFERecoveryAgent

SYNOPSIS

Installs Forest Recovery Agent on a specified domain controller or on each domain controller in the forest.

SYNTAX

ProjectSpecificParameters (Default)

```
Install-RMADFERecoveryAgent [-ComputerName] <String> [<CommonParameters>]
```

ProjectlessDomain

```
Install-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential  
<PSCredential> [<CommonParameters>]
```

ProjectlessAll

```
Install-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential  
<PSCredential>  
-DsrnCredential <PSCredential> -LocalCredential <PSCredential>  
[<CommonParameters>]
```

ProjectlessDsrn

```
Install-RMADFERecoveryAgent [-ComputerName] <String> -DsrnCredential  
<PSCredential> [<CommonParameters>]
```

ProjectlessLocal

```
Install-RMADFERecoveryAgent [-ComputerName] <String> -LocalCredential  
<PSCredential> [<CommonParameters>]
```

DESCRIPTION

Allows you to install Forest Recovery Agent on a specified domain controller or on each domain controller in the forest.

EXAMPLES

EXAMPLE 1

```
PS C:\> Open-RMADFEProject -Path C:\rmadfe.frproj -Password (ConvertTo-  
SecureString "password" -AsPlainText -Force)
```

```
Install-RMADFERecoveryAgent -Name dc1.RMAD.local
```

Installs Forest Recovery Agent on the specified domain controller in the RMADFE project.

EXAMPLE 2

```
PS C:\> $credentials = New-Object PSCredential(".\Administrator",  
(ConvertTo-SecureString 'Password' -AsPlainText -Force))
```

```
Install-RMADFERecoveryAgent -name dc1.RMAD.local -DcCredential $credentials  
-DsrnCredential $credentials
```

Installs Forest Recovery Agent on the specified domain controller (either in Normal or DSRM mode). In this example, you should use only domain credentials or DSRM credentials, or both.

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DcCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers in the Normal mode.

Type: PSCredential
Parameter Sets: ProjectlessDomain, ProjectlessAll
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DsrnCredentia

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access domain controllers in the selected domain in Directory Services Restore Mode (DSRM).

Type: PSCredential
Parameter Sets: ProjectlessAll, ProjectlessDsrn
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-LocalCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access standalone machines.

Type: PSCredential
Parameter Sets: ProjectlessAll, ProjectlessLocal
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

New-RMADCollection

SYNOPSIS

Creates a new computer collection.

SYNTAX

```
New-RMADCollection [[-Name] <String>] [-Temporary] [-IgnoreReadOnly]
[<CommonParameters>]
```

DESCRIPTION

Creates a new computer collection with a default name or with the name you specify. The new computer collection is created using the default computer collection parameters set in the Recovery Manager console.

EXAMPLES

Example 1

```
PS C:\> New-RMADCollection -Name Collection1
```

This command creates a new computer collection named Collection1.

Example 2

```
PS C:\> New-RMADCollection Collection1 -Temporary
```

This command creates a new temporary computer collection from the existing collection named Collection1.

PARAMETERS

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-Name

Allows you to specify a name for the computer collection to be created.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-Temporary

Creates a new temporary computer collection.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

New-RMADFEProject

SYNOPSIS

Creates a new RMADFE project in the file system.

SYNTAX

AD (Default)

```
New-RMADFEProject -Domain <String> -Credential <PSCredential>  
[<CommonParameters>]
```

Backup

```
New-RMADFEProject -Backup <BackupInfo> [-BackupPassword <SecureString>]  
[<CommonParameters>]
```

DESCRIPTION

This cmdlet creates a new RMADFE project in the file system.

EXAMPLES

EXAMPLE 1

```
PS C:\> $backupInfo = Get-RMADBackupInfo -Path "C:\RMAD_TEMP\backup.bak"
```

```
New-RMADFEProject -Backup $backupInfo -BackupPassword (ConvertTo-  
SecureString "Backup Password " -AsPlainText -Force)
```

This example demonstrates how to create a new project from a backup.

PARAMETERS

-Backup

Specifies the backup that contains the data to be restored.

Type: BackupInfo
Parameter Sets: Backup
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupPassword

Specifies the password to access a password-protected backup.

Type: SecureString
Parameter Sets: Backup
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Credential

Specifies credentials to access the domain controller.

Type: PSCredential
Parameter Sets: AD
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Domain

Specifies the fully qualified domain name.

Type: String
Parameter Sets: AD
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

New-RMADFERecoveryMedia

SYNOPSIS

Creates a new Recovery Media ISO in the file system.

SYNTAX

FromWsb (Default)

```
New-RMADFERecoveryMedia -IsoPath <String> -WsbPath <String> [-IpAddress <String>] [-DriversFolder <String>] [-SubnetMask <String>] [-DefaultGateway <String>] [-AllowAddCustomDrivers <Boolean>] [-AllowAddCustomDriversFromBackup <Boolean>] [<CommonParameters>]
```

FromWim

```
New-RMADFERecoveryMedia -IsoPath <String> -WimPath <String> [-IpAddress <String>] [-DriversFolder <String>] [-SubnetMask <String>] [-DefaultGateway <String>] [-AllowAddCustomDrivers <Boolean>] [-AllowAddCustomDriversFromBackup <Boolean>] [<CommonParameters>]
```

FromBmr

```
New-RMADFERecoveryMedia -IsoPath <String> -BmrPath <String> [-BackupPassword <SecureString>]
```

```
[-IpAddress <String>] [-DriversFolder <String>] [-SubnetMask <String>] [-DefaultGateway <String>] [-AllowAddCustomDrivers <Boolean>] [-AllowAddCustomDriversFromBackup <Boolean>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet creates a new Recovery Media ISO in the file system.

EXAMPLES

Example 1

```
PS C:\> New-RMADFERecoveryMedia -WimPath C:\Recovery\WindowsRE\WinRe.wim -IsoPath C:\ProgramData\Quest\RecoveryMedia\QuestWinRe.iso
```

This example illustrates how to create the Recovery Media from the Windows Recovery Environment image.

Example 2

```
PS C:\> New-RMADFERecoveryMedia -WsbPath \\BackupServer\Storage\Backup1 -IsoPath C:\ProgramData\Quest\RecoveryMedia\QuestWinRe.iso
```

This example illustrates how to create the Recovery Media from the Windows Server backup.

PARAMETERS

-AllowAddCustomDrivers

Turns on the ability to set up custom drivers.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-AllowAddCustomDriversFromBackup

Turns on the ability to set up custom drivers from the backup.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-BackupPassword

Specifies the password to access a password-protected backup. This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString
Parameter Sets: FromBmr
Aliases: Password

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BmrPath

Specifies a path to Bare Metal Recovery backup.

Type: String
Parameter Sets: FromBmr
Aliases: Bmr

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DefaultGateway

Specifies the preconfigured Default Gateway to be used for the generated Recovery Media Bare Metal Console.

Type: String
Parameter Sets: (All)
Aliases: Gateway

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DriversFolder

Specifies the folder for custom drivers.

Type: String
Parameter Sets: (All)
Aliases: Drivers

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IpAddress

Specifies the preconfigured IP Address to be used for the generated Recovery Media Bare Metal Console.

Type: String
Parameter Sets: (All)
Aliases: Ip

Required: False
Position: Named
Default value: None

Accept pipeline input: False
Accept wildcard characters: False

-IsoPath

Path to the output Quest Recovery Environment image file

Type: String
Parameter Sets: (All)
Aliases: Iso, Output

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SubnetMask

Specifies the preconfigured Subnet Mask to be used for the generated Recovery Media Bare Metal Console.

Type: String
Parameter Sets: (All)
Aliases: Subnet

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-WimPath

Path to Windows Image file

Type: String
Parameter Sets: FromWim
Aliases: Wim

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-WsbPath

Path to Windows Server Backup

Type: String
Parameter Sets: FromWsb
Aliases: Wsb

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

New-RMADSchedule

SYNOPSIS

Creates a schedule for the backup creation operation you want to perform on a particular computer collection.

SYNTAX

Once

```
New-RMADSchedule [-Once] -StartDate <DateTime> [-MinutesDuration <UInt32>]
[-MinutesInterval <UInt32>]
[<CommonParameters>]
```

Daily

```
New-RMADSchedule [-Daily] -DaysInterval <Int32> -StartDate <DateTime> [-
EndDate <DateTime>]
[-MinutesDuration <UInt32>] [-MinutesInterval <UInt32>]
[<CommonParameters>]
```

Weekly

```
New-RMADSchedule [-Weekly] -WeeksInterval <Int32> -DaysOfWeek
<DaysOfTheWeek> -StartDate <DateTime>
[-EndDate <DateTime>] [-MinutesDuration <UInt32>] [-MinutesInterval
<UInt32>] [<CommonParameters>]
```

MonthlyDate

```
New-RMADSchedule [-MonthlyDate] -Day <Int32> [-Months <Months>] -StartDate <DateTime> [-EndDate <DateTime>] [-MinutesDuration <UInt32>] [-MinutesInterval <UInt32>] [<CommonParameters>]
```

MonthlyDOW

```
New-RMADSchedule [-MonthlyDOW] [-DaysOfWeek <DaysOfTheWeek>] [-Months <Months>] -Week <WhichWeek> -StartDate <DateTime> [-EndDate <DateTime>] [-MinutesDuration <UInt32>] [-MinutesInterval <UInt32>] [<CommonParameters>]
```

DESCRIPTION

Creates a schedule to perform the backup creation operation a particular computer collection. You can use the parameters of this cmdlet to set a recurring or non-recurring schedule for the backup creation operation.

EXAMPLES

Example 1

```
PS C:\> New-RMADSchedule -Once -StartDate "2/20/2022 1:00"
```

Runs the backup creation operation at 1:00 a.m. on the 20th February 2022.

Example 2

```
PS C:\> New-RMADSchedule -Daily -StartDate "2/20/2022 1:00" -DaysInterval 3
```

Runs the backup creation operation every 3 days, starting from 1:00 a.m. on the 20th February 2022.

Example 3

```
PS C:\> New-RMADSchedule -Weekly -StartDate "2/20/2022 1:00" -WeeksInterval 2 -DaysOfWeek Monday, Friday
```

Runs the backup creation operation on Monday and Friday of every second week, starting from 1:00 a.m. on the 20th February 2022.

Example 4

```
PS C:\> New-RMADSchedule -MonthlyDate -StartDate "2/20/2022 1:00" -Day 1
```

Runs the backup creation operation on every first day of each month (the Months parameter is omitted, therefore the backup creation operation is invoked each month), starting from 1:00 a.m. on the 20th February 2022.

Example 5

```
PS C:\> New-RMADSchedule -MonthlyDOW -StartDate "2/20/2022 1:00" -DaysOfWeek 1,5 -Week 1
```

Runs the backup creation operation on every first Monday and Friday of each month, starting from 1:00 a.m. on the 20th February 2022.

PARAMETERS

-Daily

Runs the backup creation operation on a daily basis.

Type: SwitchParameter
Parameter Sets: Daily
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Day

Sets the day of the month when you want to run the backup creation operation.

Type: Int32
Parameter Sets: MonthlyDate
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DaysInterval

Sets an interval (in number of days) between invocations of the backup creation operation.

Type: Int32
Parameter Sets: Daily
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DaysOfWeek

Runs the backup creation operation on particular days of week. To set the weeks when you want to run the backup creation operation, use the Weekly or MonthlyDOW parameter.

Type: DaysOfTheWeek
Parameter Sets: Weekly
Aliases:
Accepted values: Sunday, Monday, Tuesday, Wednesday, Thursday, Friday, Saturday, Sunday, Monday, Tuesday, Wednesday, Thursday, Friday, Saturday

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
Type: DaysOfTheWeek
Parameter Sets: MonthlyDOW

Aliases:
Accepted values: Sunday, Monday, Tuesday, Wednesday, Thursday, Friday, Saturday, Sunday, Monday, Tuesday, Wednesday, Thursday, Friday, Saturday

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-EndDate

Specifies the date when the backup creation operation schedule expires.

Type: DateTime
Parameter Sets: Daily, Weekly, MonthlyDate, MonthlyDOW
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-MinutesDuration

Specifies the time period (in minutes) during which you want to repeatedly run (invoke) the backup creation operation. To set the time interval between invocations of the backup creation operation, use the MinutesInterval parameter.

Type: UInt32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-MinutesInterval

Specifies the time interval (in minutes) between invocations of the backup creation operation. To set the time period during which you want to repeatedly run (invoke) the backup creation operation, use the MinutesDuration parameter.

Type: UInt32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-MonthlyDate

Runs the backup creation operation on particular day of month. To set the months and day of month when you want to run the backup creation operation, use the Months and Day parameters respectively.

Type: SwitchParameter
Parameter Sets: MonthlyDate

Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-MonthlyDOW

Runs the backup creation operation on particular days of week in particular months. To set the months, weeks, and days of week, use the Months, Week, and DaysOfWeek parameters respectively.

Type: SwitchParameter
Parameter Sets: MonthlyDOW
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Months

Sets the months when you want to run the backup creation operation.

Type: Months
Parameter Sets: MonthlyDate, MonthlyDOW
Aliases:
Accepted values: January, February, March, April, May, June, July, August, September, October, November, December

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Once

Runs the backup creation operation only once.

Type: SwitchParameter
Parameter Sets: Once
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-StartDate

Specifies the date when the backup creation operation schedule comes into effect.

Type: DateTime
Parameter Sets: (All)
Aliases:

Required: True
Position: Named

Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Week

Sets the week of the month when you want to run the backup creation operation. This parameter accepts the following values:

- 1. Specifies the first week of the month.
- 2. Specifies the second week of the month.
- 3. Specifies the third week of the month.
- 4. Specifies the fourth week of the month.
- 5. Specifies the fifth week of the month.

Type: WhichWeek
Parameter Sets: MonthlyDOW
Aliases:
Accepted values: None, FirstWeek, SecondWeek, ThirdWeek, FourthWeek, LastWeek

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Weekly

Runs the backup creation operation on a weekly basis.

Type: SwitchParameter
Parameter Sets: Weekly
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-WeeksInterval

Sets an interval (in number of weeks) between invocations of the backup creation operation.

Type: Int32
Parameter Sets: Weekly
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Open-RMADFEProject

SYNOPSIS

Opens the RMADFE project.

SYNTAX

```
Open-RMADFEProject [-Path] <String> [-Password] <SecureString>  
[<CommonParameters>]
```

DESCRIPTION

This cmdlet opens the RMADFE project from the specified location.
You must also supply the password that is used to access the project content.

EXAMPLES

EXAMPLE 1

```
PS C:\> Open-RMADFEProject -Path C:\RMADFeProjects\SampleProject.frproj -  
Password (ConvertTo-SecureString "project password" -AsPlainText -Force)
```

This command opens SampleProject.frproj from the specified location.

PARAMETERS

-Password

Specifies the password that is used to access the RMADFE project content.

Type: SecureString
Parameter Sets: (All)

Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Path

Specifies the path to the existing RMADFE project file.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Protect-RMADSecureStorageServer

SYNOPSIS

Enables storage server hardening.

SYNTAX

Name

```
Protect-RMADSecureStorageServer [-IgnoreReadOnly] [-Name] <String> [-WhatIf] [-Confirm] [<CommonParameters>]
```

Server

```
Protect-RMADSecureStorageServer [-IgnoreReadOnly] [-Server] <StorageServer> [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Enables storage server hardening.

EXAMPLES

Example 1

```
PS C:\> Get-RMADStorageServer | Protect-RMADSecureStorageServer
```

Enables hardening on all registered secure storage servers.

Example 2

```
PS C:\> Protect-RMADSecureStorageServer -Name "storage.srv"
```

Enables hardening on the specified storage server.

PARAMETERS

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Name

Specifies the name of the secure storage server.

```
Type: String  
Parameter Sets: Name  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)
```

Accept wildcard characters: False

-Server

Specifies the secure storage server. Use `Get-RMADStorageServer` to get a list of all secure storage servers.

Type: StorageServer
Parameter Sets: Server
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-Confirm

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Shows what would happen if the cmdlet runs.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

System.String

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Publish-RMADBackupSecurityStatus

SYNOPSIS

Publishes security check information for a specified backup.

SYNTAX

```
Publish-RMADBackupSecurityStatus -BackupGuid <Guid[]> -SecurityStatus  
<BackupSecurityStatus>  
[<CommonParameters>]
```

DESCRIPTION

Saves security check information for a specified backup registered with Recovery Manager for Active Directory.

EXAMPLES

Example 1

```
PS C:\> $bkf = (Get-RMADBackup -ComputerName DC.DomainName.local) [-1]  
$status = New-Object -TypeName  
QuestSoftware.RecoveryManager.AD.PowerShell.BackupSecurityStatus  
$status.Summary = "Passed"  
$status.Details = "some passed"  
$status.CheckDate = Get-Date  
Publish-RMADBackupSecurityStatus -BackupGuid $bkf.backupGuid -  
SecurityStatus $status  
Get-RMADBackupSecurityStatus -BackupGuid $bkf.BackupGuid
```

For troubleshooting only. This command saves antimalware scan results for a specified backup registered with Recovery Manager for Active Directory.

PARAMETERS

-BackupGuid

This is the GUID of the backup for which a user wants to get the antimalware scan results.

Type: Guid[]

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-SecurityStatus

Result information about the security check of a particular backup.

Type: BackupSecurityStatus

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Refresh-RMADStorageServer

SYNOPSIS

Refreshes current information of the secure storage server.

SYNTAX

Name

```
Refresh-RMADStorageServer [-IgnoreReadOnly] [-Name] <String>  
[<CommonParameters>]
```

Server

```
Refresh-RMADStorageServer [-IgnoreReadOnly] [-Server] <StorageServer>  
[<CommonParameters>]
```

DESCRIPTION

Connects to the secure storage server and retrieves the current status (agent state and hardening state).

EXAMPLES

Example 1

```
PS C:\> Get-RMADStorageServer | Refresh-RMADStorageServer
```

Updates statuses of all registered secure storage servers.

Example 2

```
PS C:\> Refresh-RMADStorageServer -Name "storage.srv"
```

Refreshes the status of the specified secure storage server.

PARAMETERS

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Name

Specifies the name of the secure storage server.

Type: String

Parameter Sets: Name

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-Server

Specifies the secure storage server. Use `Get-RMADStorageServer` to get a list of all secure storage servers.

Type: StorageServer

Parameter Sets: Server

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

System.String

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Register-RMADSecureStorageBackups

SYNOPSIS

Registers backups on an existing secure storage server in a Recovery Manager database.

SYNTAX

Name

```
Register-RMADSecureStorageBackups [-IgnoreReadOnly] [-Name] <String>  
[<CommonParameters>]
```

Server

```
Register-RMADSecureStorageBackups [-IgnoreReadOnly] [-Server]  
<StorageServer> [<CommonParameters>]
```

DESCRIPTION

Registers backups on an existing secure storage server in a Recovery Manager database so that the backups become available in the Recovery Manager user interface.

EXAMPLES

Example 1

```
PS C:\> Register-RMADSecureStorageBackups -Name "storage.srv"
```

Registers backups on a specified storage server.

PARAMETERS

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Name

Specifies the name of the secure storage server.

Type: String
Parameter Sets: Name
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-Server

Specifies the secure storage server. Use `Get-RMADStorageServer` to get a list of all secure storage servers.

Type: StorageServer
Parameter Sets: Server
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

System.String

QuestSoftware.RecoveryManager.AD.PowerShell.Cmdlets.StorageServersManagement.StorageServer

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Remove-RMADBackup

SYNOPSIS

Allows you to selectively unregister backups from the Recovery Manager backup registration database.

SYNTAX

Instance

```
Remove-RMADBackup [-InputObject] <BackupInfo[]> [-Delete <Boolean>] [-ShareCredential <PSCredential>] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

Id

```
Remove-RMADBackup [-Id] <Int32[]> [-Delete <Boolean>] [-ShareCredential <PSCredential>] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Allows you to selectively unregister backups from the Recovery Manager backup registration database. Optionally, you can delete the unregistered backups from their location.

EXAMPLES

Example 1

```
PS C:\> Get-RMADBackup | Where-Object {$_.Date -lt (Get-Date).AddDays(-15)} | Remove-RMADBackup -Delete $true
```

Gets all backups created by Recovery Manager for Active Directory in the last 15 days, unregisters these backups from the backup registration database, and then deletes the backup files.

PARAMETERS

-Delete

Specifies to delete the backups being unregistered from their locations. This parameter can take one of the following values:

- \$true
- \$false

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Id

Specifies the IDs of the backups you want to unregister from the Recovery Manager backup registration database. If you use this parameter, omit the InputObject parameter of this cmdlet.

Type: Int32[]
Parameter Sets: Id
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-InputObject

Specifies the IBackupInfo objects representing the backups you want to unregister from the Recovery Manager backup registration database. If you use this parameter, omit the Id parameter of this cmdlet.

Type: BackupInfo[]
Parameter Sets: Instance
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-ShareCredential

Specifies credential for share folder that contains the backup in case of -delete flag is true.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts for a confirmation before executing the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Remove-RMADBackupAgent

SYNOPSIS

Removes Recovery Manager Backup Agent from a specified computer, or its registration information from the Recovery Manager Console.

SYNTAX

```
Remove-RMADBackupAgent [-Computer] <String> [[-Credentials] <PSCredential>]  
[-Uninstall] [-IgnoreReadOnly]  
 [<CommonParameters>]
```

DESCRIPTION

Allows you to completely remove Recovery Manager Backup Agent from a specified computer. You can also select to remove only registration information that relates to a particular Backup Agent from the Recovery Manager Console. This may be useful if you removed Backup Agent from a computer manually but the related agent entry remains on the Backup Agent Management node of the Recovery Manager Console.

EXAMPLES

Example 1

```
PS C:\> Remove-RMADBackupAgent -Computer "dc1"
```

This code removes registration information that relates to Backup Agent installed on the computer "dc1" from the Recovery Management Console.

Example 2

```
PS C:\> $credential = Get-Credential  
Remove-RMADBackupAgent -Computer "dc1" -Credentials $credential -Uninstall
```

This code connects to the computer "dc1" under the user represented by the "credential" object and removes Backup Agent from it. Note that corresponding Backup Agent registration information is removed from the Recovery Management Console as well.

PARAMETERS

-Computer

Specifies the name of the computer from which to remove Recovery Manager Backup Agent.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Credentials

Specifies the user name and the password of the user account to use for connecting to the target computer and removing Backup Agent. Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Notes:

- The user should be a local Administrator on the target computer.
- If you omit this parameter, Backup Agent will be removed under the current user account.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Uninstall

Specifies whether the Recovery Manager Backup Agent should be completely removed. If this parameter is omitted, only the agent registration information will be removed.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Remove-RMADCollection

SYNOPSIS

Deletes specified Computer Collections.

SYNTAX

Name (Default)

```
Remove-RMADCollection [-Name] <String[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

InputObject

```
Remove-RMADCollection [-InputObject] <ComputerCollection[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

Id

```
Remove-RMADCollection [-Id] <Int32[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Deletes the Computer Collections that have the specified name or are represented by the specified objects.

EXAMPLES

Example 1

```
PS C:\> Remove-RMADCollection -Name "New Computer Collection"
```

Deletes the computer collection named New Computer Collection.

Example 2

```
PS C:\> Get-RMADCollection | Where-Object {$_.Schedule.Count -eq 0} |  
Remove-RMADCollection
```

The Get-RMADCollection cmdlet gets all computer collections. The Where-Object cmdlet then filters out the collections for which no backup creation operation is scheduled. The pipeline operator passes the filtered collection objects to the Remove-RMADCollection cmdlet, which deletes these collection objects.

PARAMETERS

-Id

Specifies the identifier of the Computer Collection to delete.

```
Type: Int32[]  
Parameter Sets: Id  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

-InputObject

Deletes Computer Collections represented by the specified collection objects. Enter a variable that contains the objects or type a command or expression that gets the objects.

```
Type: ComputerCollection[]  
Parameter Sets: InputObject  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

-Name

Specifies the name of the Computer Collection to be deleted.

```
Type: String[]  
Parameter Sets: Name
```

Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName)
Accept wildcard characters: False

-Confirm

Prompts for confirmation before executing the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Remove-RMADCollectionItem

SYNOPSIS

Removes items from a specified Computer Collection.

SYNTAX

```
Remove-RMADCollectionItem [-Collection] <String[]> [-Item] <String[]> [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Allows you to selectively remove items from the Computer Collection you specify.

EXAMPLES

Example 1

```
PS C:\> Remove-RMADCollectionItem -Collection Collection1 -Item Comp1
```

Removes the item named Comp1 from the Computer Collection named Collection1.

PARAMETERS

-Collection

Specifies the Computer Collection from which to remove items. To specify a Computer Collection, type the Computer Collection name in this parameter.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-Item

Specifies items to remove from the Computer Collection. To specify an item, type the item name in this parameter.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: True

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Remove-RMADFECLOUDStorage

SYNOPSIS

Removes a registered cloud storage from Recovery Manager for Active Directory.

SYNTAX

Id

```
Remove-RMADFECLOUDStorage [-Id] <Int32[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

InputObject

```
Remove-RMADFECLOUDStorage [-InputObject] <CloudStorage[]> [-IgnoreReadOnly]
[-WhatIf] [-Confirm]
[<CommonParameters>]
```

DESCRIPTION

Removes a registered cloud storage from Recovery Manager for Active Directory. Only storage registration in Recovery Manager will be removed; backup and any other data on the cloud storage is not affected.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFECLOUDStorage
PS C:\> Remove-RMADFECLOUDStorage -Id 1
```

Removes cloud storage specified by the Id parameter.

Example 2

```
PS C:\> Get-RMADFECLOUDStorage | Remove-RMADFECLOUDStorage -Confirm:$false
```

Remove all registered cloud storages without a confirmation.

PARAMETERS

-Id

Specifies the cloud storage Id representing the storage you want to unregister from the Recovery Manager.

Type: Int32[]

Parameter Sets: Id

Aliases: StorageId

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-InputObject

Specifies the CloudStorage object representing the storage you want to unregister from the Recovery Manager. If you use this parameter, omit the Id parameter of this cmdlet.

Type: CloudStorage[]
Parameter Sets: InputObject
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-Confirm

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Shows what would happen if the cmdlet runs.
The cmdlet is not run.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.Int32[]

QuestSoftware.RecoveryManager.AD.FE.PowerShell.CloudStorage[]

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Remove-RMADFECLOUDStorageUploadSession

SYNOPSIS

Removes an existing cloud storage upload session.

SYNTAX

Id

```
Remove-RMADFECLOUDStorageUploadSession [-Id] <Int32[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [  
  <CommonParameters>]
```

InputObject

```
Remove-RMADFECLOUDStorageUploadSession [-InputObject] <UploadSession[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [  
  <CommonParameters>]
```

DESCRIPTION

Removes an existing cloud storage upload session. Only session information in Recovery Manager for Active Directory will be removed; backup and any other data on the cloud storage is not affected.

EXAMPLES

Example 1

```
PS C:\> Get-RMADFECLOUDStorageUploadSession | Remove-RMADFECLOUDStorageUploadSession
```

Removes all registered upload sessions without a confirmation.

Example 2

```
PS C:\> Remove-RMADFECLOUDStorageUploadSession -Id 1
```

Removes a specific registered upload session with the session Id of 1.

PARAMETERS

-Id

Specifies the upload session Id representing the upload session you want to remove from the history in Recovery Manager for Active Directory.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-InputObject

Specifies the UploadSession object representing the cloud storage upload session you want to unregister from Recovery Manager for Active Directory. If you use this parameter, omit the Id parameter of this cmdlet.

Type: UploadSession[]

Parameter Sets: InputObject

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-Confirm

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Shows what would happen if the cmdlet runs.
The cmdlet is not run.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.Int32[]

QuestSoftware.RecoveryManager.AD.FE.PowerShell.UploadSession[]

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Remove-RMADFEComputer

SYNOPSIS

Removes a standalone computer from the RMADFE project.

SYNTAX

```
Remove-RMADFEComputer [-ComputerName] <String> [<CommonParameters>]
```

DESCRIPTION

This cmdlet removes a standalone computer from the current RMADFE project.

EXAMPLES

Example 1

```
Remove-RMADFEComputer -Name dc1.acme.com
```

This command removes a dc1.acme.com standalone computer from the current RMADFE project.

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases: Name

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Remove-RMADFERecoveryAgent

SYNOPSIS

Removes Forest Recovery Agent from a specified domain controller, or its registration information from Forest Recovery Console.

SYNTAX

ProjectSpecificParameters (Default)

```
Remove-RMADFERecoveryAgent [-ComputerName] <String> [<CommonParameters>]
```

ProjectlessDomain

```
Remove-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential  
<PSCredential> [<CommonParameters>]
```

ProjectlessAll

```
Remove-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential  
<PSCredential> -DsrnCredential <PSCredential>  
-LocalCredential <PSCredential> [<CommonParameters>]
```

ProjectlessDsrn

```
Remove-RMADFERecoveryAgent [-ComputerName] <String> -DsrnCredential  
<PSCredential> [<CommonParameters>]
```

ProjectlessLocal

```
Remove-RMADFERecoveryAgent [-ComputerName] <String> -LocalCredential  
<PSCredential> [<CommonParameters>]
```

DESCRIPTION

Allows you to completely remove Forest Recovery Agent from a specified domain controller. You can also select to remove only registration information that relates to a particular Forest Recovery Agent from Forest Recovery Console. This may be useful if you removed Forest Recovery Agent from a domain controller manually, but the related agent entry remains in Forest Recovery Console.

EXAMPLES

EXAMPLE 1

```
PS C:\> Open-RMADFEProject -Path C:\rmadfe.frproj -Password (ConvertTo-  
SecureString "password" -AsPlainText -Force)
```

```
Remove-RMADFERecoveryAgent -Name dc1.RMAD.local
```

Removes Forest Recovery Agent from the specified domain controller in the RMADFE project.

EXAMPLE 2

```
PS C:\> $credentials = New-Object PSCredential(".\Administrator",  
(ConvertTo-SecureString 'Password' -AsPlainText -Force))
```

```
Remove-RMADFERecoveryAgent -name dc1.RMAD.local -DcCredential $credentials  
-DsrnCrediential $credentials
```

Removes Forest Recovery Agent from the specified domain controller (either in Normal or DSRM mode). In this example, you should use only domain credentials or DSRM credentials, or both.

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-DcCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers in the Normal mode.

Type: PSCredential

Parameter Sets: ProjectlessDomain, ProjectlessAll

Aliases:

Required: True

Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DsrnCred

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access domain controllers in the selected domain in Directory Services Restore Mode (DSRM).

Type: PSCredential
Parameter Sets: ProjectlessAll, ProjectlessDsrn
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-LocalCred

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access standalone machines.

Type: PSCredential
Parameter Sets: ProjectlessAll, ProjectlessLocal
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Remove-RMADFERecoverySchedule

SYNOPSIS

Removes an existing recovery schedule for the RMADFE project.

SYNTAX

```
Remove-RMADFESchedule [-Credential] <PSCredential> [-WhatIf] [-Confirm]  
[<CommonParameters>]
```

DESCRIPTION

This cmdlet allows you to remove the recovery schedule for the RMADFE project.

EXAMPLES

EXAMPLE 1

```
PS C:\> Remove-RMADFESchedule
```

Removes the current project schedule.

PARAMETERS

-Credential

Specifies credentials that will be used to run the command.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts for confirmation before executing the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-WhatIf

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Remove-RMADFESchedule

SYNOPSIS

Removes an existing verification schedule for the RMADFE project.

SYNTAX

```
Remove-RMADFESchedule [-Credential] <PSCredential> [-WhatIf] [-Confirm]  
[<CommonParameters>]
```

DESCRIPTION

This cmdlet allows you to remove the verification schedule for the RMADFE project.

EXAMPLES

EXAMPLE 1

```
PS C:\> Remove-RMADFESchedule
```

Removes the current project schedule.

PARAMETERS

-Credential

Specifies credentials that will be used to run the command.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts for confirmation before executing the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Remove-RMADFESubbyInstance

SYNOPSIS

Removes the standby instance.

SYNTAX

```
Remove-RMADFESubbyInstance [-StandbyInstance] <StandbyInstanceRecord>  
[<CommonParameters>]
```

DESCRIPTION

Removes the standby instance.

EXAMPLES

EXAMPLE 1

```
PS C:\> $instances = Get-RMADFESubbyInstances  
$latest = $instances | Sort-Object LastUpdatedDate -Descending | Select-  
Object -First 1  
Remove-RMADFESubbyInstance -StandbyInstance $latest
```

PARAMETERS

-StandbyInstance

Standby instance to be removed

Type: StandbyInstanceRecord

Parameter Sets: (All)

Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

ForestRecovery.RecoveryLogic.Sessions.StandbyInstanceRecord

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Remove-RMADFEVerifySchedule

SYNOPSIS

Removes an existing verification schedule for the RMADFE project.

SYNTAX

```
Remove-RMADFEVerifySchedule [-Credential] <PSCredential> [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

This cmdlet allows you to remove the verification schedule for the RMADFE project.

EXAMPLES

EXAMPLE 1

```
PS C:\> Remove-RMADFEVerifySchedule
```

Removes the current project schedule.

PARAMETERS

-Credential

Specifies credentials that will be used to run the command.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts for confirmation before executing the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Remove-RMADReplicationConsole

SYNOPSIS

Removes an RMAD console from the replication console list.

SYNTAX

Id

```
Remove-RMADReplicationConsole [-Id] <Int32[]> [<CommonParameters>]
```

ComputerName

```
Remove-RMADReplicationConsole [-ComputerName] <String[]>  
[<CommonParameters>]
```

InputObject

```
Remove-RMADReplicationConsole [-InputObject] <ReplicationConsole[]>  
[<CommonParameters>]
```

DESCRIPTION

Removes the specified RMAD console or replication consoles from the replication console list.

EXAMPLES

Example 1

```
PS C:\> C:\> Remove-RMADReplicationConsole Hostname1
```

This command removes the RMAD console on Hostname1 from the replication console list.

Example 2

```
PS C:\> C:\> Remove-RMADReplicationConsole -Id 1
```

This command removes the RMAD console with specified ID from the replication console list.

Example 3

```
PS C:\> C:\> Get-RMADReplicationConsole | Remove-RMADReplicationConsole
```

This command removes all the replication consoles from the replication console list.

PARAMETERS

-ComputerName

Specifies the hostname of the replication console you want to remove.

Type: String[]

Parameter Sets: ComputerName

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-Id

Specifies the ID of the replication console you want to remove.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-InputObject

Specifies the replication console object you want to remove.

Type: ReplicationConsole[]

Parameter Sets: InputObject

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Remove-RMADReplicationSchedule

SYNOPSIS

Allows you to remove the replication schedule from a specified computer.

SYNTAX

```
Remove-RMADReplicationSchedule [<CommonParameters>]
```

DESCRIPTION

Allows you to remove the replication schedule from a specified computer.

EXAMPLES

Example 1

```
PS C:\> Remove-RMADReplicationSchedule
```

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Remove-RMADReplicationSession

SYNOPSIS

Deletes replication sessions from the replication history.

SYNTAX

Session

```
Remove-RMADReplicationSession [-Session] <ReplicationSession[]>  
[<CommonParameters>]
```

Id

```
Remove-RMADReplicationSession [-Id] <Int32[]> [<CommonParameters>]
```

DESCRIPTION

Deletes one or more replication sessions from the replication history.

EXAMPLES

Example 1

```
PS C:\> Remove-RMADReplicationSession -Id 1
```

This command deletes the replication session whose ID is 1.

Example 2

```
PS C:\> Get-RMADReplicationSession | Remove-RMADReplicationSession
```

This command clears the replication history.

PARAMETERS

-Id

Specifies the IDs of replication sessions for deleting.

Type: Int32[]
Parameter Sets: Id
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-Session

Specifies the replication sessions for deleting.

Type: ReplicationSession[]
Parameter Sets: Session
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Remove-RMADSession

SYNOPSIS

Allows you to selectively delete specified Recovery Manager backup session(s).

SYNTAX

Instance

```
Remove-RMADSession -InputObject <Session[]> [<CommonParameters>]
```

SessionID

```
Remove-RMADSession -SessionId <Int32[]> [<CommonParameters>]
```

RemoveAll

```
Remove-RMADSession [-RemoveAll] [<CommonParameters>]
```

DESCRIPTION

Allows you to selectively delete specified Recovery Manager backup session(s).

EXAMPLES

Example 1

```
PS C:\> Get-RMADSession | Where-Object {$_.StartDate -gt (Get-Date).AddDays(-15)} | Remove-RMADSession
```

Gets all Recovery Manager backup sessions started by Recovery Manager for Active Directory in the last 15 days, and deletes them.

Example 2

```
PS C:\> Remove-RMADSession -SessionID 1,2,3
```

Deletes the Recovery Manager backup sessions with session IDs 1,2, and 3.

Example 3

```
PS C:\> Remove-RMADSession -RemoveAll
```

Deletes all Recovery Manager backup sessions.

PARAMETERS

-InputObject

Specifies the ISession objects representing the Recovery Manager backup sessions you want to delete. If you use this parameter, omit the SessionId and RemoveAll parameters of this cmdlet.

Type: Session[]
Parameter Sets: Instance
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-RemoveAll

Deletes all Recovery Manager backup sessions. If you use this parameter, omit the SessionId and InputObject parameters of this cmdlet.

Type: SwitchParameter
Parameter Sets: RemoveAll
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SessionId

Specifies the IDs of the Recovery Manager backup sessions you want to delete. If you use this parameter, omit the InputObject and RemoveAll parameters of this cmdlet.

Type: Int32[]
Parameter Sets: SessionID
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

QuestSoftware.RecoveryManager.AD.PowerShell.Session[]

System.Int32[]

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Remove-RMADStorageServer

SYNOPSIS

Removes the secure storage server.

SYNTAX

Name

```
Remove-RMADStorageServer [-IgnoreReadOnly] [-Name] <String> [-WhatIf] [-Confirm] [<CommonParameters>]
```

Server

```
Remove-RMADStorageServer [-IgnoreReadOnly] [-Server] <StorageServer> [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Removes currently registered secure storage servers.

EXAMPLES

Example 1

```
PS C:\> Remove-RMADStorageServer -Name "backupsrv01.acme.test"
```

Removes the specified secure storage server.

Example 2

```
PS C:\> Get-RMADStorageServer | Remove-RMADStorageServer
```

Removes all registered secure storage servers.

PARAMETERS

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Name

Specifies the name of the registered storage server (DNS name or IP address).

Type: String

Parameter Sets: Name

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-Server

Specifies the secure storage server object.

Type: StorageServer

Parameter Sets: Server

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-Confirm

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-WhatIf

Shows what happens when you run the cmdlet. The cmdlet does not actually run.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.String

QuestSoftware.RecoveryManager.AD.PowerShell.Cmdlets.StorageServersManagement.StorageServer

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Remove-RMADUnpackedComponent

SYNOPSIS

Allows you to delete components (data) unpacked from specified backups.

SYNTAX

Instance

```
Remove-RMADUnpackedComponent [-InputObject] <BackupInfo[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

Id

```
Remove-RMADUnpackedComponent [-Id] <Int32[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Allows you to delete all components (data) unpacked from specified backups and saved in the Recovery Manager cache for further use.

EXAMPLES

Example 1

```
PS C:\> Remove-RMADUnpackedComponent (Get-RMADBackup | where{$_.IsUnpacked -eq "true"})
```

Deletes all components unpacked from backups created with Recovery Manager for Active Directory.

PARAMETERS

-Id

Specifies the IDs of the backups whose unpacked components you want to delete. If you use this parameter, omit the InputObject parameter of this cmdlet.

Type: Int32[]
Parameter Sets: Id
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-InputObject

Specifies the IBackupInfo objects representing the backups whose unpacked components you want to delete. If you use this parameter, omit the Id parameter of this cmdlet.

Type: BackupInfo[]
Parameter Sets: Instance
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-Confirm

Prompts for confirmation before executing the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-WhatIf

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Rename-RMADCollection

SYNOPSIS

Renames a computer collection.

SYNTAX

Name (Default)

```
Rename-RMADCollection [-Name] <String> [-Value] <String> [-PassThru] [-  
IgnoreReadOnly] [-WhatIf] [-Confirm]  
[<CommonParameters>]
```

InputObject

```
Rename-RMADCollection [-InputObject] <ComputerCollection> [-Value] <String>  
[-PassThru] [-IgnoreReadOnly]  
[-WhatIf] [-Confirm] [<CommonParameters>]
```

Id

```
Rename-RMADCollection [-Id] <Int32> [-Value] <String> [-PassThru] [-  
IgnoreReadOnly] [-WhatIf] [-Confirm]  
[<CommonParameters>]
```

DESCRIPTION

Renames a computer collection with the name you specify.

EXAMPLES

Example 1

```
PS C:\> Rename-RMADCollection -Name "New Computer Collection" -Value Collection1
```

This command renames the computer collection named "New Computer Collection" to "Collection1".

Example 2

```
PS C:\> $c = Get-RMADCollection -Name "Collection1"
```

```
C:\PS>Rename-RMADCollection -InputObject $c -Value "Collection2"
```

The `Get-RMADCollection` cmdlet retrieves the computer collection named `Collection1`. This collection is then passed to the `Rename-RMADCollection` cmdlet that renames it to `Collection2`.

PARAMETERS

-Id

Specifies the identifier of the computer collection you want to rename.

```
Type: Int32  
Parameter Sets: Id  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

-InputObject

Renames the computer collection represented by the specified collection objects. Specify the name of the variable that contains the objects or type a command or expression that gets the objects.

```
Type: ComputerCollection  
Parameter Sets: InputObject  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)
```

Accept wildcard characters: False

-Name

Specifies the name of the computer collection to be renamed.

Type: String

Parameter Sets: Name

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-PassThru

Passes the renamed collection along the pipeline. If this parameter is omitted, the renamed collection is not passed along the pipeline.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-Value

Specifies the new name you want to assign to the computer collection.

Type: String

Parameter Sets: (All)

Aliases: NewName

Required: True

Position: 1

Default value: None

Accept pipeline input: True (ByPropertyName)

Accept wildcard characters: False

-Confirm

Prompts for a confirmation before executing the command.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: cf

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-Whatif

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Restart-RMADFECLOUDStorageUploadSession

SYNOPSIS

Restart a failed or canceled cloud storage upload session.

SYNTAX

Id

```
Restart-RMADFECLOUDStorageUploadSession [-Id] <Int32[]> [-IgnoreReadOnly]  
[<CommonParameters>]
```

InputObject

```
Restart-RMADFECLOUDStorageUploadSession [-InputObject] <UploadSession[]> [-  
IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Restart a previously failed or canceled cloud storage upload session. The copy of the backup is restarted and the specified session is updated.

EXAMPLES

Example 1

```
PS C:\> Restart-RMADFECloudStorageUploadSession -Id 4
```

Restart upload session with Id 4.

PARAMETERS

-Id

Specifies the upload session Id to restart the copy of the backup to cloud storage.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-InputObject

Specifies the UploadSession object representing the cloud storage upload session you want to restart.

Type: UploadSession[]

Parameter Sets: InputObject

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.Int32[]

QuestSoftware.RecoveryManager.AD.FE.PowerShell.UploadSession[]

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Restore-RMADDeletedObject

SYNOPSIS

Restores deleted Active Directory objects.

This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA).

SYNTAX

Default (Default)

```
Restore-RMADDeletedObject [-ProcessRecycledObjects] [-Backup <Guid>] [-RestoreParent <RestoreParent>] [-Full] [-NoReport] [-SkipReplication] [-ReportUnchangedObjects] [-ReportUnchangedAttributes] [-RestoreTo <String>] [-KeepBackupUnpacked] [-Id] <String[]> [-ProcessChildren] [-ChildObjectClass <String[]>] [-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential <PSCredential>] [-RestoreUsingChangeAuditor] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly]
```

[-WhatIf] [-Confirm] [<CommonParameters>]

ADLds

```
Restore-RMADDeletedObject [-ProcessRecycledObjects] [-Backup <Guid>] [-BackupPassword <SecureString>] [-NoReport] [-SkipReplication] [-ReportUnchangedObjects] [-ReportUnchangedAttributes] [-RestoreTo <String>] [-AsJob] [-KeepBackupUnpacked] [-Id] <String[]> [-ProcessChildren] [-ChildObjectClass <String[]>] [-AdLds] [-AdLdsInstance <String>] [-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential <PSCredential>] [-RestoreUsingChangeAuditor] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

Bkf

```
Restore-RMADDeletedObject [-ProcessRecycledObjects] -Backup <Guid> [-BackupPassword <SecureString>] [-NoReport] [-SkipReplication] [-ReportUnchangedObjects] [-ReportUnchangedAttributes] [-RestoreTo <String>] [-AsJob] [-KeepBackupUnpacked] [-Id] <String[]> [-ProcessChildren] [-ChildObjectClass <String[]>] [-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential <PSCredential>] [-RestoreUsingChangeAuditor] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

Firewall

```
Restore-RMADDeletedObject [-ProcessRecycledObjects] [-Backup <Guid>] [-BackupPassword <SecureString>] [-RestoreParent <RestoreParent>] [-Full] [-NoReport] [-SkipReplication] [-ReportUnchangedObjects] [-ReportUnchangedAttributes] [-RestoreTo <String>] [-AsJob] [-KeepBackupUnpacked] [-Id] <String[]> [-ProcessChildren] [-ChildObjectClass <String[]>] [-AdLds] [-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential <PSCredential>] [-ConfigureFirewall] [-RestoreUsingChangeAuditor] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

Agentless

```
Restore-RMADDeletedObject [-ProcessRecycledObjects] [-Backup <Guid>] [-BackupPassword <SecureString>] [-RestoreParent <RestoreParent>] [-Full] [-NoReport] [-SkipReplication] [-ReportUnchangedObjects] [-ReportUnchangedAttributes] [-RestoreTo <String>] [-AsJob] [-KeepBackupUnpacked] [-Id] <String[]> [-UseAgentlessMethod] [-ProcessChildren] [-ChildObjectClass <String[]>] [-AdLds] [-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential <PSCredential>] [-RestoreUsingChangeAuditor] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly]
```

[-WhatIf] [-Confirm] [<CommonParameters>]

DESCRIPTION

Restores deleted Active Directory objects whose applicable tombstone lifetime or deleted object lifetime has not expired. Depending on your settings and your environment, this cmdlet can restore deleted objects by using the following methods:

- Restore deleted objects from Microsoft's Active Directory Recycle Bin (provided that it is available in your environment).
- Restore deleted objects from a backup registered with Recovery Manager for Active Directory.
- Reanimate object's tombstones.

You can only use this cmdlet when Windows PowerShell is started using MTA. To start Windows PowerShell using MTA, run this command: PowerShell -mta

EXAMPLES

Example 1

```
PS C:\> Restore-RMADDeletedObject -Id d8742dcb-3e6a-4b3c-b3fe-374623cdcf06  
-Backup 2b509d4e-40f5-4337-82f7-458584555d0c -ProcessRecycledObjects -  
Server dc1.mydomain.com
```

Retrieves the recycled object with the specified Id (GUID) from the domain controller dc1.mydomain.com, and then restores the object from the backup with the specified GUID. This command is only applicable to environments where Microsoft's Active Directory Recycle Bin is enabled. In this example, the Server parameter is mandatory.

Example 2

```
PS C:\> Restore-RMADDeletedObject -Id d8742dcb-3e6a-4b3c-b3fe-374623cdcf06  
-Backup 2b509d4e-40f5-4337-82f7-458584555d0c -Server dc1.mydomain.com
```

Retrieves deleted object with the specified Id (GUID) from the domain controller dc1.mydomain.com, and then restores the object from the backup with the specified GUID. In this example, the Server parameter is mandatory.

Example 3

```
PS C:\> Restore-RMADDeletedObject -Id d8742dcb-3e6a-4b3c-b3fe-374623cdcf06  
-Backup 2b509d4e-40f5-4337-82f7-458584555d0c -Server dc1.mydomain.com -  
WindowsServerBackup -AsJob
```

Retrieves deleted object with the specified Id (GUID) from the domain controller dc1.mydomain.com, and then restores the object from the backup with the specified GUID in the background job. In this example, the Server parameter is mandatory.

PARAMETERS

-AdLds

Specifies that the AD LDS instance is used as a data storage.

Type: SwitchParameter
Parameter Sets: ADLds
Aliases:

Required: True
Position: Named
Default value: False

Accept pipeline input: False
Accept wildcard characters: False
Type: SwitchParameter
Parameter Sets: Firewall, Agentless
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-AdLdsInstance

If you restore the backed up AD LDS (ADAM) objects, you should specify the AD LDS instance whose backup you want to use.

Type: String
Parameter Sets: ADLds
Aliases: AdamInstance

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AsJob

Runs the command as a background job. You can use this parameter to run commands that take a significant time to complete.

Type: SwitchParameter
Parameter Sets: ADLds, Bkf, Firewall, Agentless
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Backup

Specifies the backup that contains the deleted object you want to restore. To specify a backup, type the backup GUID in this parameter or use the Get-RMADBackup cmdlet.

Type: Guid
Parameter Sets: Default, ADLds, Firewall, Agentless
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
Type: Guid
Parameter Sets: Bkf
Aliases:

Required: True
Position: Named

Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupPassword

Specifies the password to access the password-protected backup that contains the deleted object you want to restore.

Type: SecureString
Parameter Sets: ADLds, Bkf, Firewall, Agentless
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ChangeAuditorDbCredential

Specifies the credentials for connecting to the Change Auditor SQL database. If this parameter is omitted, the credentials of the current logged in user will be used.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ChangeAuditorDbName

Specifies a location of the Change Auditor SQL database. If this parameter is omitted, the 'ModifyBy' cell in AD reports will be empty.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ChildObjectClass

Allows you to reanimate only those child objects that belong to the classes you specify in this parameter.

Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ConfigureFirewall

Specifies whether Recovery Manager automatically configures Windows Firewall on domain controllers to allow compare and restore operations.

Type: SwitchParameter
Parameter Sets: Firewall
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Credential

The user name and password of the user account with which you want to connect, in the form of a PSCredential object. Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Full

Specifies to restore the deleted objects with all their attributes. When this parameter is present, the cmdlet does one of the following:

- Restores the deleted objects from Microsoft's Active Directory Recycle Bin. This occurs only if the Recycle Bin is available and if you do not specify to restore the deleted objects from a backup.
- Restores the deleted object from the backup whose GUID you specify in the BackupGuid parameter. When this parameter is omitted, the cmdlet does one of the following:
- If Microsoft's Active Directory Recycle Bin is available, the cmdlet completely undeletes the deleted objects from the Recycle Bin.
- If Microsoft's Active Directory Recycle Bin is disabled or not supported, the cmdlet reanimates the objects' tombstones.

Type: SwitchParameter
Parameter Sets: Default, Firewall, Agentless
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Id

Specifies the deleted objects to restore. To specify an object, you can use object GUID, distinguished name (DN), sAMAccountName, or user principal name (UPN).

Type: String[]
Parameter Sets: (All)

Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-KeepBackupUnpacked

Determines whether to save the unpacked backup after the search operation. If this parameter is not set, the unpacked backup will be deleted after the search operation is completed.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-NoReport

Specifies to not create any report about the restore operation.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Partition

Specifies the distinguished name of the Active Directory partition from which deleted objects are to be retrieved. If this parameter is omitted, the default naming context is used. This parameter is required if you specify an ADAM instance host in the DirectoryHost parameter.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named

Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Port

Specifies the port number to be used for connection. If this parameter is set to 0 or not specified, the default LDAP port (389) is used.

Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ProcessChildren

Specifies to process children of the objects specified in the Id attribute.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ProcessRecycledObjects

Specifies to process recycled objects.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ReportUnchangedAttributes

Includes information about the object attributes that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ReportUnchangedObjects

Includes information about the objects that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-RestoreParent

Restores the deleted parents of the deleted objects being recovered.

This parameter can take one of the following values:

- Never - Specifies to not restore deleted parents.
- Always - Specifies to always restore deleted parents.
- Prompt - Prompts you for action.

Type: RestoreParent

Parameter Sets: Default, Firewall, Agentless

Aliases:

Accepted values: Never, Always, Prompt

Required: False

Position: Named

Default value: Prompt

Accept pipeline input: False

Accept wildcard characters: False

-RestoreTo

Specifies a target container for the restore operation. To specify a target container, specify the container's distinguished name (DN) in this parameter. You can use this parameter to specify a target container if the parent container of the object you want to restore has been deleted.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-RestoreUsingChangeAuditor

Specifies if Change Auditor is used to restore the latest changes to the object.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False
Accept wildcard characters: False

-Server

Specifies the domain controller or ADAM instance host from which deleted objects are to be retrieved. The domain controller can be specified by its computer name, IP address, or domain name. If you specify a domain name, deleted objects are retrieved from any available domain controller in the specified domain. The ADAM instance host can be specified by its computer name or IP address. If this parameter is omitted, deleted objects are retrieved from any available domain controller in the current domain.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SkipReplication

Specifies to skip replication during the restore operation.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-UseAgentlessMethod

Specifies to use the agentless method to access the target domain controller. If this parameter is omitted, the target domain controller is accessed via Restore Agent.

Type: SwitchParameter
Parameter Sets: Agentless
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts for a confirmation before executing the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-WhatIf

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Restore-RMADDomainController

SYNOPSIS

Restores a domain controller from backup.

SYNTAX

Default (Default)

```
Restore-RMADDomainController -Backup <BackupInfo> [-BackupComponents  
<BackupComponents>]  
[-BackupPassword <SecureString>] [-ComputerName <String>] [-Credential  
<PSCredential>]
```

```
-DsrnCrediential <PSCredential> [-ResetDsrnPassword] [-ManualRestartToDsrn]
[-ManualRestartToNormal]
[-MarkSysvolPrimary] [-AsJob] [-WhatIf] [<CommonParameters>]
```

AuthoritativeRestore

```
Restore-RMADDomainController -Backup <BackupInfo> [-BackupComponents
<BackupComponents>]
[-BackupPassword <SecureString>] [-ComputerName <String>] [-Credential
<PSCredential>]
-DsrnCrediential <PSCredential> [-ResetDsrnPassword] [-ManualRestartToDsrn]
[-ManualRestartToNormal]
[-MarkSysvolPrimary] -AuthoritativeRestore <Boolean> [-
AuthoritativeRestoreSubtree <String>] [-AsJob]
[-WhatIf] [<CommonParameters>]
```

DESCRIPTION

Restores a domain controller from backup. During the Restore operation, the domain controller would be rebooted to the Directory Service Restore mode.

EXAMPLES

Example 1

```
PS C:\> $backup = (Get-RMADBackup -ComputerName 'DC.Domain.local')[-1]
$dsrcnCrediential = New-Object PSCredential(".\Administrator", (ConvertTo-
SecureString 'DsrnPassword' -AsPlainText -Force))
$job = Restore-RMADDomainController -ComputerName "DC.Domain.local" -Backup
$backup -BackupComponents ActiveDirectory -DsrnCrediential $dsrcnCrediential -
AsJob
$job | Format-List
```

This command restores a domain controller from backup.

PARAMETERS

-AsJob

Runs a command as a background job. You can use this parameter to run commands that take a significant amount of time to complete.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-AuthoritativeRestore

Performs an authoritative restore.

Type: Boolean

Parameter Sets: AuthoritativeRestore

Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AuthoritativeRestoreSubtree

Specifies a subtree that will be marked as authoritative. If this parameter is not specified, the whole Active Directory will be marked as authoritative.

Type: String
Parameter Sets: AuthoritativeRestore
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Backup

Specifies the backup that contains the data to be restored.

Type: BackupInfo
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupComponents

Specifies the components of backup to be restored.

Type: BackupComponents
Parameter Sets: (All)
Aliases:
Accepted values: None, ActiveDirectory, Adam, BootFiles, CertificateServer, ClusterQuorum, EnterpriseServices, ForestRecoveryMetadata, GroupMembership, IisMetabase, PerformanceCounters, Registry, CryptoKeys, LdapsCerts, All

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupPassword

Specifies the password to access a password-protected backup. This is the same password that is set in the properties of the computer collection in the Recovery Manager for Active Directory console.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: False

Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ComputerName

Specifies DNS name or IP address of the domain controller to be restored.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Credential

Specifies credentials to access the domain controller and then deploy and connect to the Restore Agent in the Normal mode.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DsrmsCredential

Specifies credentials for the Directory Service Restore Mode. If ResetDSRMPassword is specified, the password will be reset.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ManualRestartToDsrms

Specifies whether a domain controller will be rebooted to DSRM manually.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ManualRestartToNormal

Specifies whether a domain controller will be rebooted to the Normal mode manually after the Restore operation is completed.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-MarkSysvolPrimary

Specifies to mark SYSVOL as primary.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-ResetDsrmpassword

Specifies whether the DSRM password will be reset to the password from the DSRMCredential parameter.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-Whatif

Tests the connection to the restore agent

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Restore-RMADFECmdletConsoleConfiguration

SYNOPSIS

Restores console configuration from backup.

SYNTAX

```
Restore-RMADFECmdletConsoleConfiguration -Path <String> -Password <SecureString>  
-ProjectFilesFolder <String>  
  [-BackupPath <String>] [-BackupPassword <SecureString>] [-WhatIf] [-  
Confirm] [<CommonParameters>]
```

DESCRIPTION

Restore console registered backup information, secure storage servers, cloud storages and its upload sessions, console authentication keys and Forest Recovery projects. Optionally this cmdlet also backs up current configuration before restore.

EXAMPLES

Example 1

```
PS C:\> $password = ConvertTo-SecureString -String "Password01!"  
-AsPlainText -Force  
PS C:\> Restore-RMADFECmdletConsoleConfiguration -Path "c:\ConsoleConfig.zip"  
-Password $password -RecoveryProjectsDirectory C:\ForestRecoveryProjects  
-Confirm:$false
```

Restores console configuration from backup located to BackupServer share with restoring Forest Recovery projects to C:\ForestRecoveryProjects folder.

PARAMETERS

-BackupPassword

Backup password of backup that will be created prior to restore.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupPath

Backup path of backup that will be created prior to restore.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Password

Password of backup to restore from.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Path

Backup path to restore from.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ProjectFilesFolder

Path to the directory where Forest Recovery projects will be restored.

Type: String

Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Shows what would happen if the cmdlet runs.
The cmdlet is not run.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Restore-RMADObject

SYNOPSIS

Restores Active Directory objects from a backup.
This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA).

SYNTAX

Default (Default)

```
Restore-RMADObject [-Attribute <String[]>] [-NoReport] [-SkipReplication]
[-KeepBackupUnpacked]
  [-Id] <String[]> -Backup <Guid> [-BackupPassword <SecureString>] [-
ProcessChildren]
  [-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-
ReportUnchangedObjects]
  [-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential
<PSCredential>] [-RestoreUsingChangeAuditor]
  [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-
Port <Int32>] [-IgnoreReadOnly]
  [<CommonParameters>]
```

Bkf

```
Restore-RMADObject [-Attribute <String[]>] [-NoReport] [-SkipReplication]
[-KeepBackupUnpacked]
  [-Id] <String[]> -Backup <Guid> [-BackupPassword <SecureString>] [-
ProcessChildren]
```

```

[-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-
ReportUnchangedObjects]
[-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential
<PSCredential>] [-RestoreUsingChangeAuditor]
[-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-
Port <Int32>] [-IgnoreReadOnly]
[<CommonParameters>]

```

ADLds

```

Restore-RMADObject [-Attribute <String[]>] [-NoReport] [-SkipReplication]
[-KeepBackupUnpacked]
[-Id] <String[]> -Backup <Guid> [-BackupPassword <SecureString>] [-
ProcessChildren]
[-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-
ReportUnchangedObjects] [-AdLds]
-AdLdsInstance <String> [-ChangeAuditorDbName <String>] [-
ChangeAuditorDbCredential <PSCredential>]
[-RestoreUsingChangeAuditor] [-Server <String>] [-Credential
<PSCredential>] [-Partition <String>]
[-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]

```

Firewall

```

Restore-RMADObject [-Attribute <String[]>] [-NoReport] [-SkipReplication]
[-KeepBackupUnpacked]
[-Id] <String[]> -Backup <Guid> [-BackupPassword <SecureString>] [-
ProcessChildren]
[-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-
ReportUnchangedObjects] [-AdLds]
[-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential
<PSCredential>] [-ConfigureFirewall]
[-RestoreUsingChangeAuditor] [-Server <String>] [-Credential
<PSCredential>] [-Partition <String>]
[-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]

```

Agentless

```

Restore-RMADObject [-Attribute <String[]>] [-NoReport] [-SkipReplication]
[-KeepBackupUnpacked]
[-Id] <String[]> -Backup <Guid> [-BackupPassword <SecureString>] [-
UseAgentlessMethod] [-ProcessChildren]
[-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-
ReportUnchangedObjects] [-AdLds]
[-ChangeAuditorDbName <String>] [-ChangeAuditorDbCredential
<PSCredential>] [-RestoreUsingChangeAuditor]
[-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-
Port <Int32>] [-IgnoreReadOnly]
[<CommonParameters>]

```

DESCRIPTION

Restores the Active Directory objects that have specified parameters from a backup. You can only use this cmdlet when Windows PowerShell is started using MTA. To start Windows PowerShell using MTA, run this command: PowerShell -mta

EXAMPLES

Example 1

```
PS C:\> $backups = Get-RMADBackup | Sort-Object -Property date -Descending

C:\PS>$object = Get-RMADObject -Id "user1"

C:\PS>Restore-RMADObject -Id $object.ObjectInfo.Guid -Backup $backups[0] -
UseAgentlessMethod -NoReport
```

In the first line of this example, the `Get-RMADBackup` cmdlet gets all registered backups and sorts them by date in the descending order. Then, the backup objects are stored in the `$backups` variable.

Example 2

```
PS C:\> $b = Get-RMADBackup -Id 1

C:\PS>Restore-RMADObject -Id "user1" -Backup $b -Attribute
samAccountName,description -ReportUnchangedAttributes

Start-RMADReportViewer
```

In the first line of this example, the `Get-RMADBackup` cmdlet gets the registered backup whose ID is 1. Then, the backup object is stored in the `$b` variable.

PARAMETERS

-AdLds

Specifies that the AD LDS instance is used as a data storage.

```
Type: SwitchParameter
Parameter Sets: ADLds
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
Type: SwitchParameter
Parameter Sets: Firewall, Agentless
Aliases:
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-AdLdsInstance

If you restore the backed up AD LDS (ADAM) objects, you should specify the AD LDS instance whose backup you want to use.

```
Type: String
Parameter Sets: ADLds
Aliases: AdamInstance
```

```
Required: True
```

Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Attribute

Specifies the display names of the attributes to restore.
When specifying multiple display names, use a comma as a separator.

Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Backup

Specifies the backup that contains the AD objects to be restored.

Type: Guid
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupPassword

Specifies the password to access a password-protected backup. This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ChangeAuditorDbCredential

Specifies the credentials for connecting to the Change Auditor SQL database. If this parameter is omitted, the credentials of the current logged in user will be used.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ChangeAuditorDbName

Specifies the location of the Change Auditor SQL database. If this parameter is omitted, the 'ModifyBy' cell in AD reports will be empty.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ChildObjectClass

Allows you to restore only those child objects that belong to the classes you specify in this parameter.

Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ConfigureFirewall

Specifies whether Recovery Manager automatically configures Windows Firewall on domain controllers to allow compare and restore operations.

Type: SwitchParameter
Parameter Sets: Firewall
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Credential

The user name and password of the user account with which you want to connect, in the form of a PSCredential object. Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter. If this parameter is omitted, the credentials of current user account are used.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ld

Specifies the objects to restore. To specify an object, you can use object GUID, distinguished name (DN), sAMAccountName, or user principal name (UPN).

Type: String[]

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-KeepBackupUnpacked

Determines whether to save the unpacked backup after the search operation. If this parameter is not set, the unpacked backup will be deleted after the search operation is completed.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-NoReport

When present, specifies to not create any report about the restore operation.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-Partition

Specifies the AD LDS (ADAM) partition where you want to restore objects.

Type: String

Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Port

Specifies the port on which to access the AD LDS (ADAM) instance where you want to restore objects.

Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ProcessChildren

When present, specifies to process children of the objects specified in the Id attribute.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ReportUnchangedAttributes

Includes the object attributes that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ReportUnchangedObjects

Includes the objects that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False

Accept wildcard characters: False

-RestoreUsingChangeAuditor

Specifies if Change Auditor is used to restore the latest changes to the object.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-Server

Specifies the domain controller or ADAM instance host on which objects are to be restored. The domain controller can be specified by its computer name, IP address, or domain name. If you specify a domain name, deleted objects are restored to any available domain controller in the specified domain. The ADAM instance host can be specified by its computer name or IP address. If this parameter is omitted, objects are restored to any available domain controller in the current domain.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-SkipReplication

When present, specifies to skip replication during the restore operation.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-UseAgentlessMethod

Specifies to use the agentless method to access the target domain controller. If this parameter is omitted, the target domain controller is accessed via Restore Agent.

Type: SwitchParameter

Parameter Sets: Agentless

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Resume-RMADFEOperation

SYNOPSIS

Resumes paused recovery process operation.

SYNTAX

```
Resume-RMADFEOperation [[-ComputerName] <String>] [<CommonParameters>]
```

DESCRIPTION

When recovery operation is paused it can be resumed by this cmdlet

EXAMPLES

Example 1

```
PS C:\> Resume-RMADFEOperation -Name dc1.acme.com
```

This command resumes paused recovery process operation for specified computer.

Example 2

```
PS C:\> Resume-RMADFEOperation
```

This command resumes paused recovery process operations for all computers from the current RMADFE project.

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Resume-RMADFERecovery

SYNOPSIS

Resumes recovery process.

SYNTAX

Resume (Default)

```
Resume-RMADFERecovery [-ProjectPassword] <SecureString> [-IgnoreDialogueTimeout] [-GroupPasswords <Hashtable>]
```

[<CommonParameters>]

Drop

Resume-RMADFERecovery [-DropStoredSession] [<CommonParameters>]

DESCRIPTION

If some workstations have begun the restore process and failed, this cmdlet can resume the recovery process.

If you chose to reset the password for domain users in privileged groups when you started a forest recovery, you need to provide passwords again using -GroupPasswords parameter because the product does not store user passwords.

EXAMPLES

Example 1

WS1:

```
PS C:\> Open-RMADFEProject 'c:\ActiveDirectoryRestore.frproj' (ConvertTo-  
SecureString "Password" -AsPlainText -Force)  
Start-RmadFeRecovery -Force
```

WS2:

```
PS C:\> Resume-RmadFeRecovery -ProjectPassword (ConvertTo-SecureString  
"Password" -AsPlainText -Force)
```

For example, there are two RMAD workstations in your environment. Both workstations must be registered as restoring workstations. Therefore, if one of them is not responding, you can run the recovery process from another workstation.

Example 2

```
PS C:\> Resume-RmadFeRecovery -DropStoredSession
```

This command cleans up the recovery session if any.

PARAMETERS

-DropStoredSession

Lead to a session drop in the persistence DB.

Type: SwitchParameter

Parameter Sets: Drop

Aliases:

Required: True

Position: 2

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-GroupPasswords

Resets the password for domain users in the specified privileged groups.

Type: Hashtable

Parameter Sets: Resume

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreDialogueTimeout

Allows you to proceed if another console does not answer.

Type: SwitchParameter
Parameter Sets: Resume
Aliases:

Required: False
Position: 1
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ProjectPassword

The password that was configured for restore project.

Type: SecureString
Parameter Sets: Resume
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Save-RMADFEProject

SYNOPSIS

Saves the RMADFE project.

SYNTAX

```
Save-RMADFEProject [-Path] <String> [-Password] <SecureString>  
[<CommonParameters>]
```

DESCRIPTION

This cmdlet saves the RMADFE project to the specified location. You must also supply the password that is used to access the project content.

EXAMPLES

EXAMPLE 1

```
PS C:\> Save-RMADFEProject -Path C:\RMADFeProjects\SampleProject.frproj -  
Password (ConvertTo-SecureString "project password" -AsPlainText -Force)
```

This command saves SampleProject.frproj to the specified location.

PARAMETERS

-Password

Specifies the password that is used to access the RMADFE project content.

Type: SecureString

Parameter Sets: (All)

Aliases:

Required: True

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Path

Specifies the full path to the RMADFE project file.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Send- RMADFEConsoleConfigurationBackupToSecureStorage

SYNOPSIS

Copies a console configuration backup from a local storage or a network share to the secure storage server.

SYNTAX

```
Send-RMADFEConsoleConfigurationBackupToSecureStorage -BackupPath <String>  
[-BackupTargetName <String>] -StorageServer <String>  
[-AgentPort <UInt32>] [-AsJob] [<CommonParameters>]
```

DESCRIPTION

Copies a console configuration backup from a local path or network share to the secure storage server. Console configuration backup is sent by a console to secure storage server agent. Note that there must be read access to provided backup location.

EXAMPLES

Example 1

```
PS C:\> Send-RMADFEConsoleConfigurationBackupToSecureStorage -StorageServer  
'storage' -BackupPath '\\fr\backupsnew\DC1.rmad.local\2022-09-10 14-54-  
49.bkf'
```

{{ Add example description here }}

PARAMETERS

-AgentPort

Secure storage agent port

Type: UInt32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-AsJob

Runs the command as a background job.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-BackupPath

Local or network path to the backup.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-BackupTargetName

Alternative name that will be used to save backup on secure storage server.

Type: String

Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-StorageServer

Secure storage name or IP address. Assuming that the Forest Recovery agent is already installed on secure storage server.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Set-RMADCollection

SYNOPSIS

Sets properties for a computer collection.

SYNTAX

Name (Default)

```
Set-RMADCollection [-Name] <String[]> [-BackupComponents  
<BackupComponents>] [-Properties <Hashtable>]  
  [-Schedule <Schedule[]>] [-ScheduleCredential <PSCredential>] [-  
AgentCredentialEnabled <Boolean>]  
  [-AgentCredential <PSCredential>] [-StorageCredentialEnabled <Boolean>] [-  
StorageCredential <PSCredential>]  
  [-SecondaryStorageCredential <PSCredential>] [-RetentionPolicyEnabled  
<Boolean>]  
  [-RetentionPolicyCount <Int32>] [-PassThru] [-IgnoreReadOnly] [-WhatIf] [-  
Confirm] [<CommonParameters>]
```

InputObject

```
Set-RMADCollection [-InputObject] <ComputerCollection[]> [-BackupComponents  
<BackupComponents>]  
  [-Properties <Hashtable>] [-Schedule <Schedule[]>] [-ScheduleCredential  
<PSCredential>]  
  [-AgentCredentialEnabled <Boolean>] [-AgentCredential <PSCredential>] [-  
StorageCredentialEnabled <Boolean>]  
  [-StorageCredential <PSCredential>] [-SecondaryStorageCredential  
<PSCredential>]  
  [-RetentionPolicyEnabled <Boolean>] [-RetentionPolicyCount <Int32>] [-  
PassThru] [-IgnoreReadOnly] [-WhatIf]  
  [-Confirm] [<CommonParameters>]
```

Id

```
Set-RMADCollection [-Id] <Int32[]> [-BackupComponents <BackupComponents>]  
  [-Properties <Hashtable>]  
  [-Schedule <Schedule[]>] [-ScheduleCredential <PSCredential>] [-  
AgentCredentialEnabled <Boolean>]  
  [-AgentCredential <PSCredential>] [-StorageCredentialEnabled <Boolean>] [-  
StorageCredential <PSCredential>]  
  [-SecondaryStorageCredential <PSCredential>] [-RetentionPolicyEnabled  
<Boolean>]  
  [-RetentionPolicyCount <Int32>] [-PassThru] [-IgnoreReadOnly] [-WhatIf] [-  
Confirm] [<CommonParameters>]
```

DESCRIPTION

Sets properties for the Recovery Manager computer collection you specify.

EXAMPLES

Example 1

```
PS C:\> Set-RMADCollection -Name Collection1 -BackupComponents
ActiveDirectory,Registry,GroupMembership,ForestRecoveryMetadata
```

This command sets properties for the computer collection named Collection1.

Example 2

```
PS C:\> Set-RMADCollection * -RetentionPolicyEnabled $false
```

This command disables all backup retention policies for all existing computer collections.

Example 3

```
PS C:\> $c = Get-RMADCollection | Where-Object { $_.AgentCredentialEnabled
-eq $true }
```

```
C:\PS>$cred = Get-Credential
```

```
C:\PS>Set-RMADCollection -InputObject $c -AgentCredential $cred
```

The first command in this example gets objects representing the computer collections whose properties are set to access Backup Agent and backup files with a specific user account. Then the command saves the computer collection objects in the \$c variable.

Example 4

```
PS C:\> $a = Get-RMADCollection -Name "Collection1"
```

```
C:\PS>Set-RMADCollection -InputObject $a[1] -Properties
@{BackupComponents="ActiveDirectory","BootFiles";
UsePreinstalledAgent=$true}
```

In the first line of this example, the Get-RMADCollection cmdlet gets the Computer Collection whose name is Collection1 and saves it to the \$a variable. In the second line of this example, the Set-RMADCollection cmdlet sets the components to be backed up (that is, Active Directory and boot files) and specifies to use preinstalled Backup Agent for backup operations. For a complete list of items you can include in the braces, see the description of the Properties parameter.

Example 5

```
PS C:\> $schedule=(New-RMADSchedule -Daily -StartDate "9/20/2022 10:00" -
DaysInterval 1), (New-RMADSchedule -Daily -StartDate "9/20/2022 22:00" -
DaysInterval 1)
```

```
C:\PS>Set-RMADCollection -InputObject $col -Properties
@{EnableEmailLog=$true; EmailLogTo="administrator@mydomain.com";
EmailLogLevel="Everything"}
```

This example illustrates how to back up a Computer Collection by using two backup schedules. The first line of this example creates two backup creation schedules and stores them in the \$schedule variable. One schedule invokes the backup operation once in every two days at 10 a.m. Another schedule invokes the backup operation once in every two days at 10 p.m. The two backup schedules become effective starting from the 20th September 2022. The second line of this example enables e-mail notifications for the Computer Collection. The recipient address for e-mail notifications is administrator@mydomain.com. The e-mail notifications provide information about all backup events.

Example 6

```
PS C:\> $cred = Get-Credential
```

```
C:\PS>Set-RMADCollection -Name MyCollection -Properties
@{AgentSideScriptBeforeBackupEnabled = $true; AgentSideScriptBeforeBackup =
'Set-Disk -Number 5 -IsOffline $false'; AgentSideScriptAfterBackupEnabled =
$true; AgentSideScriptAfterBackup = 'Set-Disk -Number 5 -IsOffline $true';
AgentSideScriptCredential = $cred}
```

This example illustrates how to customize your environment by running PowerShell scripts on the domain controller before and after creating a backup.

PARAMETERS

-AgentCredential

Specifies the credentials for the account you want to use to access Backup Agent installed on the DCs in the computer collection and locations where backup files for the computer collection will be saved. TO enable using the account whose credentials you supply in this parameter, use the AgentCredentialEnabled parameter.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AgentCredentialEnabled

Specifies to use a particular account to access Backup Agent installed on the DCs in the computer collection and locations where backup files for the computer collection will be saved. To specify the credentials for the account, use the AgentCredential parameter.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupComponents

Use this parameter to specify the names of the System State components you want to back up.

Type: BackupComponents
Parameter Sets: (All)
Aliases:

Accepted values: None, ActiveDirectory, Adam, BootFiles, CertificateServer, ClusterQuorum, EnterpriseServices, ForestRecoveryMetadata, GroupMembership, IisMetabase, PerformanceCounters, Registry, CryptoKeys, LdapsCerts, All

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Id

Specifies the identifier of the computer collection whose properties you want to set.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

-InputObject

Renames the computer collection represented by the specified collection objects. Specify the name of the variable that contains the objects or type a command or expression that gets the objects.

Type: ComputerCollection[]

Parameter Sets: InputObject

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-Name

Specifies the name of the computer collection whose properties you want to set.

Type: String[]

Parameter Sets: Name

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-PassThru

Passes the computer collection whose properties you have set along the pipeline. If this parameter is omitted, the computer collection is not passed along the pipeline.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Properties

Allows you to modify the Computer Collection properties.

To specify the properties you want to modify, use an associative array or hash table. For more information, see the Windows PowerShell help topic on associative arrays (hash tables). To open the topic, at the PowerShell command prompt enter the following: `help about_associative_array` Below are the properties you can modify by using this parameter. The properties are grouped by the names of tabs in the "Computer Collection Properties" dialog box, because each property corresponds to an option on these tabs. To assign a new value to a property, use the following format: `PropertyName=Value`

- `UseAlternateStoragePath` - Specifies whether to store a copy of each backup in an alternate location. Can take one of these values: `$true`, `$false`.
- `AlternateStoragePath` - Specifies a storage path format for the alternate location. Surround the path with double quotes.
- `AgentCredentialEnabled` - Causes the Recovery Manager console to use a specified user account to access the Backup Agent and backup files on target computers. Can take one of these values: `$true`, `$false`.
- `AgentCredential` - Specifies the account under which the Recovery Manager console accesses the Backup Agent and backup files, in the form of a `PSCredential` object. Use the `Get-Credential` cmdlet provided by Windows PowerShell to pass a `PSCredential` object to this parameter.
- `ConfigureFirewall` - Specifies whether Recovery Manager automatically configures Windows Firewall on domain controllers to allow backup operations. Can take one of these values: `$true`, `$false`.
- `UsePreinstalledAgent` - Specifies whether Recovery Manager automatically preinstalls the Backup Agent. Can take one of these values: `$true`, `$false`.
- `DeployForestRecoveryAgent` - Specifies whether Recovery Manager verifies that the Forest Recovery Agent is installed on each domain controller in the Computer Collection. Can take one of these values: `$true`, `$false`.
- `BackupDescription` - Specifies a description for the backups to be created for the Computer Collection. The description may include expressions, such as `%COMPUTERNAME%` and `%DATETIME%`.
- `BackupPasswordEnabled` - Specifies whether to protect the backups with a password. Can take one of these values: `$true`, `$false`.
- `BackupPassword` - Specifies a password to protect the backups. The value must be a `SecureString` object.
- `ConsoleSideBackupEnabled` - Specifies to store backups on the Recovery Manager computer or on a Universal Naming Convention (UNC) share. Can take one of these values: `$true`, `$false`.
- `ConsoleSideBackupPath` - Specifies a storage path format for backup files. The path format can include expressions, such as `%COMPUTERNAME%` and `%DATETIME%`. Surround the path format with double quotes.
- `ConsoleSideRetentionPolicyEnabled` - Specifies whether to apply a retention policy to backups stored at the path provided in the `ConsoleSideBackupPath` parameter. Can take one of these values: `$true`, `$false`.
- `ConsoleSideRetentioPolicyCount` - Specifies the number of the most recent backups to retain. Other backups are automatically deleted.
- `RegisterConsoleSideAdditionalBackupPathCopies` - Specifies whether to register backup copies stored at the alternate location provided in the `AlternateStoragePath` parameter. Can take one of these values: `$true`, `$false`.
- `ConsoleSideRetentionPolicyForAdditionalBackupsEnabled` - Specifies whether to apply a retention policy to backups stored at the path provided in the `AlternateStoragePath` parameter. Can take one of these values: `$true`, `$false`.
- `ConsoleSideRetentionPolicyForAdditionalBackupsCount` - Specifies the number of the most recent backups to retain at the alternate location specified by the `AlternateStoragePath` parameter. Other backups are automatically deleted.

- AgentSideBackupEnabled - Specifies to store backups on the backed-up DC or on a Universal Naming Convention (UNC) share. Can take one of these values: \$true, \$false.
- AgentSideBackupPath - Specifies a storage path format for agent-side backup files. The path format can include expressions, such as %COMPUTERNAME% and %DATETIME%. To specify an alternate backup location, separate the primary and alternate paths with the pipe (|) character. Surround the path(s) format with double quotes.
- AgentSideRetentionPolicyEnabled - Specifies whether to apply a retention policy to backups stored at the primary path provided in the AgentSideBackupPath parameter. Can take one of these values: \$true, \$false.
- AgentSideRetentionPolicyCount - Specifies the number of the most recent backups to retain at the primary agent-side location. Other backups are automatically deleted.
- AgentSideRetentionPolicyForAdditionalBackupsEnabled - Specifies whether to apply a retention policy to backups stored at the alternate path provided in the AgentSideBackupPath parameter. Can take one of these values: \$true, \$false.
- AgentSideRetentionPolicyForAdditionalBackupsCount - Specifies the number of the most recent backups to retain at the alternate agent-side location. Other backups are automatically deleted.
- StorageCredentialEnabled - Causes the Recovery Manager console to use a specified user account to access backup files on target computers. Can take one of these values: \$true, \$false.
- StorageCredential - Specifies the account under which the Recovery Manager Backup Agent accesses the backup files, in the form of a PSCredential object. Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.
- EnableEmailLog - Specifies whether to send information about backup creation sessions by e-mail. Can take one of these values: \$true, \$false.
- EnableEmailLogOnlyOnErrors - Specifies to send information over e-mail only when an error occurs. Can take one of these values: \$true, \$false.
- EmailLogLevel - Specifies the type of information to send over e-mail. Possible values: "Everything", "ErrorsOnly".
- EmailLogTo - Specifies the recipient's e-mail address to send the information about backup creation sessions.
- EnableApplicationLog - Specifies whether to write information about backup creation sessions to the Windows application log on the Recovery Manager computer. Can take one of these values: \$true, \$false.
- EnableApplicationLogOnlyOnErrors - Specifies whether to create an Application log event only upon backup creation session errors or warnings. Can take one of these values: \$true, \$false.
- ApplicationLogLevel - Specifies the type of information to write to the Application log. Possible values: "Everything", "ErrorsOnly".
- EnableLogFile - Specifies whether to write information about backup creation sessions to the additional text file you specify. Can take one of these values: \$true, \$false.
- EnableLogFileOnlyOnErrors - Specifies whether to write information to the additional text file only upon backup creation session errors or warnings. Can take one of these values: \$true, \$false.
- LogFileLevel - Specifies the type of information to write to the additional text file. Possible values: "Everything", "ErrorsOnly".
- LogFileName - Specifies a path and name for the additional text file.
- LogFileAppend - Specifies whether to append information to the additional text file. Can take one of these values: "True", "False".
- ExtendedLogging - Specifies the logging settings for DCs in the collection. Can take one of these values: Use global (default) - use settings from the root node: Recovery Manager for Active Directory->Settings...>Logging, Yes - for all DCs in the current collection: for logs will be used the "Trace" option, No - for all DCs in the current collection: in logs will be only Warnings and Error messages.
- CompressionMethod - Specifies a method to compress the backups to be created. Can take one of these values: "None", "Fast", "Normal", "Maximum".
- ParallelBackups - Specifies the maximum number of computers serviced in parallel when creating backups. Increasing this number can speed the backup creation, however, this may result in network saturation and slow network response.
- EnableTransferRateLimit - Specifies whether to limit the total bandwidth used by the Backup Agent when transferring data over the network. Use this property to prevent the Backup Agent from generating excessive network traffic. Can take one of these values: \$true, \$false.
- TransferRateLimit - Specifies the bandwidth limit in Mbits/sec for the Backup Agent.
- EnableCpuUsageLimit - Specifies whether to limit the CPU processing time used by the Backup Agent on each computer. Can take one of these values: \$true, \$false.

- CpuUsageLimit88 - Specifies the CPU processing limit in percent.
- ScheduleEnabled - Specifies whether to enable backup creation schedule. Can take one of these values: \$true, \$false.
- Schedule - Sets up a backup creation schedule. To set up a schedule, use the New-RMADSchedule cmdlet.
- ScheduleCredential - Specify the user account under which the Task Scheduler performs backup creation tasks, in the form of a PSCredential object. Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.
- BackupComponents - Specifies the system state components to back up. Possible values: "All", "None", "ActiveDirectory", "Adam", "BootFiles", "CertificateServer", "ClusterQuorum", "EnterpriseServices", "ForestRecoveryMetadata", "GroupMembership", "IisMetabase", "PerformanceCounters", "Registry". When specifying multiple values, use a comma as a separator.
- CollectGroupMembership - Specifies whether to back up group membership data stored on Global Catalog servers. Can take one of these values: \$true, \$false.
- CollectForestRecoveryMetadata - Specifies whether to create backups that can be used to recover the Active Directory forest. Can take one of these values: \$true, \$false.
- OverrideDefaultBackupUnpackSettings - Specifies whether to override the global settings for unpacking backups for the Computer Collection. Can take one of these values: \$true, \$false.
- UnpackBackupsUponCreation - Specifies whether to unpack each backup upon its creation. Can take one of these values: \$true, \$false.
- UnpackedBackupsToKeep - Specifies the number of the most recent unpacked backups to retain. Other unpacked backups are automatically deleted.
- IsUnpackOnlySelected - Specifies whether to keep unpacked backups only for a list of selected domain controllers. Can take one of these values: \$true, \$false.
- SelectedDCsToUnpack - Specifies the names (separated by comma) of domain controllers you want to keep unpacked backups for.

Type: Hashtable
 Parameter Sets: (All)
 Aliases:

Required: False
 Position: Named
 Default value: None
 Accept pipeline input: False
 Accept wildcard characters: False

-RetentionPolicyCount

Specifies the number of latest backups you want to keep for each DC in the computer collection. To enable the deletion of obsolete backups, use the RetentionPolicyEnabled parameter.

Type: Int32
 Parameter Sets: (All)
 Aliases:

Required: False
 Position: Named
 Default value: None
 Accept pipeline input: False
 Accept wildcard characters: False

-RetentionPolicyEnabled

Specifies to delete obsolete backups for particular computer collection. To set the number of latest backups you want to keep for each DC in the computer collection, use the RetentionPolicyCount parameter.

Type: Boolean
 Parameter Sets: (All)
 Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Schedule

Causes the computer collection you specify to use the backup creation schedule you set by using the New-
RMADSchedule cmdlet.

Type: Schedule[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ScheduleCredential

Specifies the user account under which the scheduled backup creation task will be run. This account must have
sufficient permissions to back up the computer collection you specify.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SecondaryStorageCredential

Specifies the credentials for the account you want to use to Tier 1 remote storage to copy backups to the
secondary storage like Secure Storage Server or Cloud Storage.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-StorageCredential

Specifies the credentials for the account you want to use to access locations where backup files for the computer
collection will be saved. To enable using the account whose credentials you supply in this parameter, use the
StorageCredentialEnabled parameter.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named

Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-StorageCredentialEnabled

Specifies to use a particular account to access locations where backup files for the computer collection will be saved. To specify the credentials for the account, use the StorageCredential parameter.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts for a confirmation before executing the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Set-RMADFECLOUDStorage

SYNOPSIS

Updates cloud storage in the Recovery Manager.

SYNTAX

IdAzureProviderSet

```
Set-RMADFECLOUDStorage [-Id] <Int32[]> [-DisplayName <String>] [-Container  
<String>]  
-AzureConnectionString <String> [-PassThru] [-IgnoreReadOnly]  
[<CommonParameters>]
```

IdAwsProviderSet

```
Set-RMADFECLOUDStorage [-Id] <Int32[]> [-DisplayName <String>] [-Container  
<String>] [-AwsRegion <String>]  
-AwsAccessKey <String> -AwsSecretKey <String> [-PassThru] [-  
IgnoreReadOnly] [<CommonParameters>]
```

InputObjectAzureProviderSet

```
Set-RMADFECLOUDStorage [-InputObject] <CloudStorage[]> [-DisplayName  
<String>] [-Container <String>]  
-AzureConnectionString <String> [-PassThru] [-IgnoreReadOnly]  
[<CommonParameters>]
```

InputObjectAwsProviderSet

```
Set-RMADFECLOUDStorage [-InputObject] <CloudStorage[]> [-DisplayName  
<String>] [-Container <String>]  
[-AwsRegion <String>] -AwsAccessKey <String> -AwsSecretKey <String> [-  
PassThru] [-IgnoreReadOnly]
```

[<CommonParameters>]

DESCRIPTION

Updates properties for the registered cloud storage in Recovery Manager for Active Directory.

EXAMPLES

Example 1

```
PS C:\> Set-RMADFECLOUDStorage -Id 7 -DisplayName "MyStorage" -  
AzureConnectionString "... " -Container "MyContainer"
```

Updates cloud storage settings for the Azure cloud storage with the Id 7.

Example 2

```
PS C:\> Set-RMADFECLOUDStorage -Id 7 -DisplayName "MyStorage" -  
AwsAccessKey "... " -AwsSecretKey "... " -Container "MyContainer"
```

Updates cloud storage settings for the AWS cloud storage with the Id 7.

PARAMETERS

-AwsAccessKey

AWS access key ID

Type: String

Parameter Sets: IdAwsProviderSet, InputObjectAwsProviderSet

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-AwsRegion

AWS region

Type: String

Parameter Sets: IdAwsProviderSet, InputObjectAwsProviderSet

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-AwsSecretKey

AWS secret key ID

Type: String

Parameter Sets: IdAwsProviderSet, InputObjectAwsProviderSet

Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AzureConnectionString

Microsoft Azure connection string or Shared Access Signature token

Type: String
Parameter Sets: IdAzureProviderSet, InputObjectAzureProviderSet
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Container

Name of container in storage account. Backups will be copied to this location.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DisplayName

Cloud storage display name for the registered storage in Recovery Manager for Active Directory.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Id

Specifies the cloud storage Id representing the storage you want to update.

Type: Int32[]
Parameter Sets: IdAzureProviderSet, IdAwsProviderSet
Aliases: StorageId

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-InputObject

Specifies the CloudStorage object representing the storage you want to update.

Type: CloudStorage[]
Parameter Sets: InputObjectAzureProviderSet, InputObjectAwsProviderSet
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-PassThru

Passes the modified cloud storage along the pipeline. If this parameter is omitted, the modified cloud storage is not passed along the pipeline.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.Int32[]

QuestSoftware.RecoveryManager.AD.FE.PowerShell.CloudStorage[]

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Set-RMADFECLOUDStorageCollection

SYNOPSIS

Configure a computer collection to use a registered cloud storage.

SYNTAX

Id

```
Set-RMADFECLOUDStorageCollection [-Collection <ComputerCollection[]>] [-CollectionId <Int32[]>] [-Id] <Int32[]> [-IgnoreReadOnly] [<CommonParameters>]
```

InputObject

```
Set-RMADFECLOUDStorageCollection [-Collection <ComputerCollection[]>] [-CollectionId <Int32[]>] [-InputObject] <CloudStorage[]> [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Configure a computer collection to use a registered cloud storage. Backups from the specified computer collections will be copied to the cloud storage. Multiple computer collections can use a cloud storage account.

EXAMPLES

Example 1

```
PS C:\> Set-RMADFECLOUDStorageCollection -Id 2 -CollectionId @(1,2,3)
```

Specifies the computer collections with Id 1, 2 and 3 to copy backups to the cloud storage with Id 2.

PARAMETERS

-Collection

Computer collection object.

Type: ComputerCollection[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-CollectionId

Id of computer collection to copy backups from to cloud storage.

Type: Int32[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Id

Cloud storage Id that is registered in Recovery Manager for Active Directory.

Type: Int32[]

Parameter Sets: Id

Aliases: StorageId

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-InputObject

Specifies the CloudStorage object representing the storage you want to update.

Type: CloudStorage[]
Parameter Sets: InputObject
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.Int32[]

QuestSoftware.RecoveryManager.AD.FE.PowerShell.CloudStorage[]

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Set-RMADFEComputer

SYNOPSIS

Applies computer settings to the RMADFE project.

SYNTAX

```
Set-RMADFEComputer [-ComputerName] <String> [-Domain <String>] [-Backup
<Guid>] [-BmrBackup <Guid>]
  [-BackupPassword <SecureString>] [-BmrBackupPassword <SecureString>] [-
LocalCredential <PSCredential>]
  [-DcCredential <PSCredential>] [-DsrnCrediential <PSCredential>] [-
NetworkShareCredential <PSCredential>]
  [-BmrBackupNetworkShareCredential <PSCredential>] [-UseDomainSettings
<Boolean>]
  [-RecoveryMethod <RecoveryMethod>] [-RestoreSysvolFromBackup <Boolean>] [-
InstallFromMedia <Boolean>]
  [-DitPath <String>] [-LogPath <String>] [-SysvolPath <String>] [-
RestoreAdOverBmrBackup <Boolean>]
  [-WipeDisks <Boolean>] [-PerformMalwareScan <Boolean>] [-DsrnPause
<Boolean>]
  [-UseOriginalTargetNetworkSettings <Boolean>] [-TargetIpAddress <String>]
[-SubnetMask <String>]
  [-DefaultGateway <String>] [-DnsServers <String>] [-
ConfigureAsGlobalCatalog <Boolean>]
  [-InstallReadOnly <Boolean>] [-RecoveryMediaPath <String>] [-
RecoveryMediaShareCredential <PSCredential>]
  [-SaveRecoveryMediaOnBackupShare <Boolean>] [-TargetHardwareType
<TargetInfrastructureType>]
  [-TargetHardwareManagementAddress <String>] [-
TargetHardwareManagementProtocol <String>]
  [-TargetHardwareManagementPort <Int32>] [-
TargetHardwareManagementCredential <PSCredential>]
  [-VMName <String>] [-VMCPUNum <Int32>]
  [-VMMemorySize <Int64>] [-HypervisorHost <String>] [-
HypervisorHostPlacement <String>]
  [-HypervisorNetwork <String>] [-VMNetworkName <String>] [-
VMNetworkResourceGroup <String>]
  [-VMFolder <String>] [-OSImage <String>] [-OSEditionIndex <String>] [-
OSEditionName <String>]
  [-OSProductKey <String>] [-VMWareTools <String>] [-ESXiHostUserName
<String>] [-ESXiHostUserPassword <String>]
  [-VMNetworkRange <String>] [-VMSubNetworkName <String>] [-
VMSubNetworkRange <String>]
  [-UseVMNetworkGateway <Boolean>] [-VMNetworkGateway <String>] [-
VMVpnAddressPool <String>]
  [-UseStaticIPAddress <Boolean>] [-AddPublicIPAddress <Boolean>] [-
DriversPath <String>]
  [-AllowAddCustomDrivers <Boolean>] [-AllowAddCustomDriversFromBackup
<Boolean>] [-SubscriptionId <String>]
  [-TenantId <String>] [-AutoSelectVMSize <Boolean>] [-VMSize <String>] [-
VMLocation <String>]
```

```

[-VMResourceGroup <String>] [-VMSecurityGroupName <String>] [-
VMSecurityGroupResourceGroup <String>]
[-VMStorageType <String>] [-VMGeneration <String>] [-VMStorageSize
<Int32>]
[-VMStorageSizeMode <VMStorageSizeMode>] [-DeleteVMAfterVerify <Boolean>]
[-DeleteInfrastructureAfterVerify <Boolean>] [-OverwriteExistingVM
<Boolean>]
[-IsStandbyRecoveryEnabled <Boolean>] [-ResourceGroupSuffix <String>] [-
NumberOfStandbyInstances <Int32>] [-KeepInProject <Boolean>]
[-InstallDnsServer <Boolean>] [-ReplicationSourceDC <String>] [-
TempStorage <String>] [<CommonParameters>]

```

DESCRIPTION

This cmdlet applies computer settings to the current RMADFE project.

EXAMPLES

EXAMPLE 1

```

PS C:\> $dcCreds = Get-Credential
$dsrcmCreds = Get-Credential
$shareCreds = Get-Credential

```

```

Set-RMADFEComputer -Name dc1.acme.com -BackupPassword (ConvertTo-
SecureString "pwd" -AsPlainText -Force) -DcCredential $dcCreds -
DsrcmCredential $dsrcmCreds -NetworkShareCredential $shareCreds -
UseDomainSettings $false

```

This command applies the specified settings to the dc1.acme.com computer.

EXAMPLE 2

```

PS C:\> $shareCreds= Get-Credential
$dcCreds = Get-Credential
$dsrcmCreds = Get-Credential
$localCreds = Get-Credential

```

```

Set-RMADFEComputer -Name dc1.acme.com -NetworkShareCredential $shareCreds -
DcCredential $dcCreds -DsrcmCredential $dsrcmCreds -LocalCredential
$localCreds -RecoveryMethod InstallAD -InstallFromMedia $true

```

This command applies the specified settings to the dc1.acme.com computer, and installs AD using media.

EXAMPLE 3

```

Set-RMADFEComputer -ComputerName DC2.rmad.local -TempStorage
"E:\TempFolder"

```

This command sets the Temporary backup folder in a Forest Recovery project file.

PARAMETERS

-AddPublicIPAddress

Specifies if public IP address should be assigned to the virtual machine.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AllowAddCustomDrivers

Turns on the ability to set up custom drivers.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AllowAddCustomDriversFromBackup

Turns on the ability to set up custom drivers from the backup.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AutoSelectVMSize

Specifies if VM size should be selected automatically.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Backup

Specifies a System State backup that is used for recovery.

Type: Guid
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BackupPassword

Specifies the password to access a password-protected backup.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BmrBackup

Specifies a Bare Metal Recovery backup that is used in case of the Bare Metal Active Directory Recovery method.

Type: Guid
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BmrBackupNetworkShareCredential

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers to the BMR backup location. Use the Get-Credential cmdlet provided by Windows PowerShell® to get the PSCredential object representing user credentials.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-BmrBackupPassword

Specifies the password to access a password-protected BMR backup.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)
Aliases: Name

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ConfigureAsGlobalCatalog

Sets the Global Catalog role for the domain controller.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DcCredential

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers in the Normal mode. Use the Get-Credential cmdlet provided by Windows PowerShell® to get the PSCredential object representing user credentials.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DefaultGateway

Specifies the default gateway for the custom Bare Metal Recovery network settings.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DeleteInfrastructureAfterVerify

Specifies if infrastructure (security group, virtual network, virtual network gateway) must be deleted after project verification.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False

Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DeleteVMAfterVerify

Specifies if a virtual machine must be deleted after project verification.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DitPath

Specifies a path to the DIT file if the custom location is required.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DnsServers

Specifies DNS Servers for the custom Bare Metal Recovery network settings.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Domain

Specifies the Domain DNS name of the computer.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DriversPath

Specifies a path to custom drivers.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-DsrnCred

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers in Directory Services Restore Mode (DSRM). Use the Get-Credential cmdlet provided by Windows PowerShell® to get the PSCredential object representing user credentials.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-DsrnPause

Specifies if the recovery process must be paused in DSRM to perform additional actions before rebooting to normal mode.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-ESXiHostUserName

Specifies the VMWare ESXi host user name

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-ESXiHostUserPassword

Specifies the VMWare ESXi host user password

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-HypervisorHost

Specifies Hypervisor host name.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-HypervisorHostPlacement

Specifies the placement of the virtual machine.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-HypervisorNetwork

Specifies the hypervisor network of the virtual machine.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-InstallDnsServer

Specifies if DNS server will be installed when using Install Active Directory or Install Active Directory from Media recovery method.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named

Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-InstallFromMedia

This option allows you to install or reinstall AD using media.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-InstallReadOnly

Sets Read-only property for the domain controller.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-KeepInProject

Marks domain controller to be recovered later. If this domain controller is removed from the Active Directory®, it will not be removed from the project on updating with Active Directory® changes.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-LocalCredential

Specifies local credentials for the computer.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-LogPath

Specifies a path to Active Directory® log files if the custom location is required.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-NetworkShareCredential

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers to the backup location. Use the Get-Credential cmdlet provided by Windows PowerShell® to get the PSCredential object representing user credentials.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-OSEditionIndex

Specifies the index of the Operation System edition. The index list can be retrieved using the Get-WindowsImage commandlet.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-OSEditionName

Specifies the Operation System edition name. The list of available editions can be retrieved using the Get-WindowsImage commandlet.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-OSImage

Specifies the path to Operation System image file

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-OSProductKey

Specifies the Operation System product key

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-OverwriteExistingVM

Specifies if an existing machine must be deleted before creation.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IsStandbyRecoveryEnabled

Specifies if standby recovery forest should be created.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ResourceGroupSuffix

Specifies the suffix added to the standby instance resource group

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None

Accept pipeline input: False
Accept wildcard characters: False

-NumberOfStandbyInstances

Specifies the number of standby instances to be kept.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-PerformMalwareScan

Specifies if the backup must be scanned with Microsoft Defender Antivirus during project verification.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-RecoveryMediaPath

Specifies a path to ISO image which is used as a boot disk.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-RecoveryMediaShareCredential

Specifies credentials to get access to ISO image which is used as a boot disk.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-RecoveryMethod

Specifies the recovery method for this domain controller.

Type: RecoveryMethod
Parameter Sets: (All)
Aliases:
Accepted values: DoNotRecover, RestoreFromBackup, ReinstallAD, AdjustADChanges, UninstallAD, RestoreSYSVOL, InstallAD, RestoreFromWindowsBackup, RestoreOnCleanOS, Skip

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ReplicationSourceDC

Specifies the replication source DC.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-RestoreAdOverBmrBackup

This option allows you to select the RMADFE Active Directory and Registry backup to be restored over the BMR backup.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-RestoreSysvolFromBackup

{{ Fill RestoreSysvolFromBackup Description }}

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SaveRecoveryMediaOnBackupShare

Specifies a location of the ISO image which is used as a boot disk.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SubnetMask

Specifies a subnet mask for the custom Bare Metal Recovery network settings.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SubscriptionId

Specifies an Azure SubscriptionId.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SysvolPath

Specifies a path to SYSVOL if the custom location is required.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-TargetHardwareManagementAddress

Specifies the address of the target platform for the new domain controller.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-TargetHardwareManagementCredential

Specifies network credentials for communicating with the platform for the new domain controller.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-TargetHardwareManagementPort

Specifies the network port for communicating with the platform for the new domain controller.

Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-TargetHardwareManagementProtocol

Specifies the network protocol for communicating with the platform for the new domain controller.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-TargetHardwareType

Specifies the target platform for the new domain controller.

Type: TargetInfrastructureType
Parameter Sets: (All)
Aliases:
Accepted values: None, PhysicalDell, PhysicalHP, Custom, VMWare, HyperV, Azure, AWS

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-TargetIpAddress

Specifies the target IP for the computer.

Type: String
Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-TempStorage

Specifies temporary backup folder in an Forest Recovery project file.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-TenantId

Specifies an Azure TenantId.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-UseDomainSettings

This option lets you use the default domain credentials to access domain controllers.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-UseOriginalTargetNetworkSettings

This option allows you to use network settings from Bare Metal Recovery backup.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-UseStaticIPAddress

Specifies if static IP address should be assigned to the virtual machine.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-UseVMNetworkGateway

Specifies if VPN Gateway should be used to connect the virtual machine.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMCPUNum

Specifies the number of CPUs on the virtual machine.

Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMFolder

Specifies a target folder for the virtual machine.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMGeneration

Specifies an Azure VM generation.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMLocation

Specifies an Azure VM location.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMMemorySize

Specifies memory size on the virtual machine.

Type: Int64
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMName

Specifies the name of the virtual machine on the target platform.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMNetworkGateway

Specifies VPN Gateway used to connect the virtual machine.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMNetworkName

Specifies virtual network name for the virtual machine.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMNetworkRange

Specifies network range for the virtual network.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMNetworkResourceGroup

Specifies virtual network resource group name for the virtual machine.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMResourceGroup

Specifies an Azure VM resource group.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMSecurityGroupName

Specifies an Azure VM security group name.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMSecurityGroupResourceGroup

Specifies an Azure VM security group resource group name.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMSize

Specifies an Azure VM size.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMStorageSize

Specifies the virtual machine disk size in GB. Applicable with VMStorageSizeMode = SetVMStorageSize.

Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-VMStorageSizeMode

Specifies the virtual machine disk size selection mode. UseDefaultVMStorageSize - set disk size based on the Active Directory data size. SetVMStorageSize - set custom disk size. Minimal disk size values are 128 GB for OS disk and 8 GB for AD data disk.

Type: VMStorageSizeMode
Parameter Sets: (All)
Aliases:
Accepted values: UseDefaultVMStorageSize, SetVMStorageSize

Required: False
Position: Named
Default value: UseDefaultVMStorageSize
Accept pipeline input: False

Accept wildcard characters: False

-VMStorageType

Specifies the virtual machine storage type.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-VMSubNetworkName

Specifies subnetwork name for the virtual network.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-VMSubNetworkRange

Specifies subnetwork range for the virtual network.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-VMVpnAddressPool

Specifies virtual machine address pool.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-VMWareTools

Specifies the path to VMWare tools installer

Type: String

Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-WipeDisks

Specifies if a full disk cleanup on the target machine is required before starting restore from the Bare Metal Recovery backup.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Set-RMADFECOnsoleConfigurationBackupSchedule

SYNOPSIS

Sets console configuration schedule.

SYNTAX

```
Set-RMADFECOnsoleConfigurationBackupSchedule -ProjectFilesFolder <String> -Path <String> -PathAccessCredential <PSCredential> -SecureStorageServer <String> -CloudStorage <String> -BackupPassword <SecureString> -ScheduleAccount <PSCredential> -Schedule <Schedule> [<CommonParameters>]
```

DESCRIPTION

Sets console configuration schedule triggers, schedule account, target backup path and password.

EXAMPLES

Example 1

```
PS C:\> $schedule = New-RMADSchedule -Daily -StartDate ((Get-Date).AddHours(1)) -DaysInterval 1
Set-RMADFECOnsoleConfigurationBackupSchedule -Path \\BackupServer\c$\ConsoleConfig.zip -Password $password -ScheduleAccount $adminCredentials -Schedule $schedule
```

Sets new console configuration schedule to run backup daily to BackupServer share with given password.

PARAMETERS

-BackupPassword

Backup password.

Type: SecureString
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-CloudStorage

Cloud storage name to save backup on.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Path

Path to use when creating backup by schedule.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-PathAccessCredential

Credential used to access the target path.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-ProjectFilesFolder

Path to the directory containing Forest Recovery project files that are needed to be backed up.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Schedule

Schedule triggers

Type: Schedule

Parameter Sets: (All)

Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ScheduleAccount

Account that will be used to run schedule task.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SecureStorageServer

Secure storage name to save backup on.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Set-RMADFEDnsCache

SYNOPSIS

Updates cached DNS records in the Forest Recovery project.

SYNTAX

```
Set-RMADFEDnsCache [-HostName] <String> [-Address] <Object> [-Override]  
[<CommonParameters>]
```

DESCRIPTION

This cmdlet updates the cached DNS records for the specified hostname in the Forest Recovery project.

EXAMPLES

Example 1

```
PS C:\> Set-RMADFEDnsCache -HostName DC1.rmad.local -Address "192.168.0.2"
```

This command prepends "192.168.0.2" to the cached DNS records of DC1.rmad.local.

Example 2

```
PS C:\> Set-RMADFEDnsCache -HostName DC1.rmad.local -Address  
@("192.168.0.2","10.0.0.2")
```

This command prepends "192.168.0.2" and "10.0.0.2" to the cached DNS records of DC1.rmad.local.

Example 3

```
PS C:\> Set-RMADFEDnsCache -HostName DC1.rmad.local -Address "192.168.0.2"  
-Override
```

This command resets the cached DNS records of DC1.rmad.local to "192.168.0.2".

PARAMETERS

-Address

Specifies a list of IP addresses for the specified hostname.

Type: Object

Parameter Sets: (All)

Aliases:

Required: True

Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-HostName

Specifies the hostname of the domain controller.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Override

This option lets you reset the cached DNS records to the specified address.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Set-RMADFEDomain

SYNOPSIS

Sets the domain settings for the current RMADFE project.

SYNTAX

AnyParameters (Default)

```
Set-RMADFEDomain [-Domain] <String> [-Recover <Boolean>] [-
AuthoritativeSysvolRestoreComputer <String>]
[-ResetPasswords <Boolean>] [-Groups
<System.Collections.Generic.List`1[System.String]>]
[-Exclusions <System.Collections.Generic.List`1[System.String]>] [-
PerformMalwareScan <Boolean>]
[-Dsrmpause <Boolean>] [-RunDsrmscriptAction <RunScriptDsrmsAction>]
[-QuarantineSysvolFilesAction <QuarantineFilesDsrmsAction>]
[-DoNotRecoverSysvolFilesAction <DoNotRecoverFilesDsrmsAction>]
[<CommonParameters>]
```

IncludeCredentials

```
Set-RMADFEDomain [-Domain] <String> [-Recover <Boolean>] [-
AuthoritativeSysvolRestoreComputer <String>]
-DcCredential <PSCredential> -DsrmsCredential <PSCredential> -
LocalCredential <PSCredential>
[-ResetPasswords <Boolean>] [-Groups
<System.Collections.Generic.List`1[System.String]>]
[-Exclusions <System.Collections.Generic.List`1[System.String]>] [-
PerformMalwareScan <Boolean>]
[-Dsrmpause <Boolean>] [-RunDsrmscriptAction <RunScriptDsrmsAction>]
[-QuarantineSysvolFilesAction <QuarantineFilesDsrmsAction>]
[-DoNotRecoverSysvolFilesAction <DoNotRecoverFilesDsrmsAction>]
[<CommonParameters>]
```

DESCRIPTION

This cmdlet sets the domain settings for the current RMADFE project.

EXAMPLES

EXAMPLE 1

```
PS C:\> $dcCreds = Get-Credential
$dsrmCreds = Get-Credential
```

```
Set-RMADFEDomain -Domain acme.com -Recover $true -
AuthoritativeSysvolRestoreComputer dc1.acme.com -DcCredential $dcCreds -
DsrmsCredential $dsrmCreds
```

This command applies the domain settings to the acme.com domain.

EXAMPLE 2

```
Set-RMADFEDomain acme.com -ResetPasswords $true -Groups Group_A, Group_B, Group_C -Exclusions User_01, User_02
```

This command enables password resetting for domain users in the following privileged groups: Group_A, Group_B, and Group_C in the domain acme.com, except User_01 and User_02.

EXAMPLE 3

```
$action = (Get-RMADFEDomain -Domain acme.com).QuarantineSysvolFilesAction
$action.IsEnabled = $true
$action.MaliciousFiles = $false
$action.SpecifiedFiles = $true
$action.Filters = @("*.exe")
$action.Exclusions = @("*\scripts\config\setup\*")
$action.RenameFiles = $true
$action.RenameSuffix = "_INFECTED"
$action.MoveFiles = $false
Set-RMADFEDomain -Domain acme.com -QuarantineSysvolFiles $action
```

This command configures an action for domain acme.com to rename files with extension .exe in SYSVOL, except for files located in folder \scripts\config\setup.

EXAMPLE 4

```
$action = (Get-RMADFEDomain -Domain acme.com).DoNotRecoverSysvolFilesAction
$action.IsEnabled = $true
$action.MaliciousFiles = $true
$action.SpecifiedFiles = $false
Set-RMADFEDomain -Domain acme.com -DoNotRecoverSysvolFiles $action
```

This command configures an action for domain acme.com to skip restoring files in SYSVOL that were identified as malicious during an antivirus scan.

EXAMPLE 5

```
$action = (Get-RMADFEDomain -Domain acme.com).RunDsrmscriptAction
$action.IsEnabled = $true
$action.Script = Get-Content "C:\Scripts\ProcessSysvolFiles.ps1"
Set-RMADFEDomain -Domain acme.com -RunDsrmscriptAction $action
```

This command configures a PowerShell@ script for domain acme.com to run in DSRM after restoring domain controllers from a backup.

PARAMETERS

-AuthoritativeSysvolRestoreComputer

This option allows you to configure the domain controller where the authoritative restore of SYSVOL will be performed.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-DcCredential

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access domain controllers in the selected domain in the Normal mode. Use the Get-Credential cmdlet provided by Windows PowerShell® to get the PSCredential object representing user credentials.

Type: PSCredential
Parameter Sets: IncludeCredentials
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Domain

Specifies the fully qualified domain name.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DoNotRecoverSysvolFilesAction

Specifies which SYSVOL files should not be recovered when restoring data from a backup.

Type: DoNotRecoverFilesDsrmsAction
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DsrmsCredential

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access domain controllers in the selected domain in Directory Services Restore Mode (DSRM). Use the Get-Credential cmdlet provided by Windows PowerShell® to get the PSCredential object representing user credentials.

Type: PSCredential
Parameter Sets: IncludeCredentials
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Dsrmpause

Specifies if the recovery process must be paused in DSRM to perform additional actions before rebooting to normal mode.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Exclusions

This parameter specifies one or more users (separated by commas). By default, only the domain administrator configured in your project settings is excluded from password resetting. When this parameter is specified, both the administrator and the specified user(s) are excluded.

Type: System.Collections.Generic.List`1[System.String]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Groups

This parameter specifies one or more groups of users (separated by commas). When this parameter is specified, this command ONLY resets the password for the specified groups of users in the domain instead of the predefined administrative accounts.

Type: System.Collections.Generic.List`1[System.String]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-LocalCredential

Specifies local credentials for the machine.

Type: PSCredential

Parameter Sets: IncludeCredentials

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-PerformMalwareScan

Specifies if the backup must be scanned with Microsoft Defender Antivirus during project verification.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-QuarantineSysvolFilesAction

Specifies which SYSVOL files should be quarantined when restoring data from a backup.

Type: QuarantineFilesDsrmaAction
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Recover

This option lets you include the domain into or exclude the domain from the current RMADFE project.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ResetPasswords

This parameter resets the password for administrative accounts in the domain during forest recovery, including members of Enterprise Admins, Domain Admins, Administrators, Account Operators, Schema Admins, Group Policy Creator Owners, Backup Operators, Server Operators, and Print Operators.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-RunDsrmaScriptAction

Specifies a PowerShell script to run on a domain controller after restoring Active Directory data from a backup.

Type: RunScriptDsrmaAction
Parameter Sets: (All)

Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Set-RMADFEFaultTolerance

SYNOPSIS

Sets fault tolerance settings for the Forest Recovery Console.

SYNTAX

MSSQLSecurity (Default)

```
Set-RMADFEFaultTolerance [-DataSource] <String> [-Credentials]  
<PSCredential> [-CreateDatabase]  
  [<CommonParameters>]
```

DisableFaultTolerance

```
Set-RMADFEFaultTolerance [-Disable] [<CommonParameters>]
```

EnableFaultTolerance

```
Set-RMADFEFaultTolerance [-Enable] [<CommonParameters>]
```

IntegratedSecurity

```
Set-RMADFEFaultTolerance [-DataSource] <String> [-IntegratedSecurity] [-CreateDatabase] [<CommonParameters>]
```

DESCRIPTION

Configures fault tolerance, which allows you to resume a recovery on another instance of the Forest Recovery Console from the point at which it was interrupted.

EXAMPLES

Example 1

```
PS C:\> $creds = New-Object PSCredential("sa", (ConvertTo-SecureString
"Password" -AsPlainText -Force))
Set-RMADFEFaultTolerance -DataSource "SQLSERVER\SQLEXPRESS" -Credentials
$creds
Set-RMADFEFaultTolerance -Enable
Get-RMADFEFaultTolerance
```

This command enables fault tolerance by storing the forest recovery state in the specified Microsoft SQL Server instance.

Example 2

```
PS C:\> Set-RMADFEFaultTolerance -Disable
Get-RMADFEFaultTolerance
```

This command disables fault tolerance.

PARAMETERS

-CreateDatabase

Creates a fault tolerance database if it does not exist on the specified Microsoft SQL Server instance.

```
Type: SwitchParameter
Parameter Sets: MSSQLSecurity, IntegratedSecurity
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Credentials

Specifies SQL Server authentication credentials.

```
Type: PSCredential
Parameter Sets: MSSQLSecurity
Aliases:
```

```
Required: True
```

Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DataSource

Specifies the SQL Server instance.

Type: String
Parameter Sets: MSSQLSecurity, IntegratedSecurity
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Disable

Disables fault tolerance.

Type: SwitchParameter
Parameter Sets: DisableFaultTolerance
Aliases:

Required: True
Position: 0
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Enable

Enables fault tolerance.

Type: SwitchParameter
Parameter Sets: EnableFaultTolerance
Aliases:

Required: True
Position: 0
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-IntegratedSecurity

Enables Windows Authentication when connecting to the SQL Server instance.

Type: SwitchParameter
Parameter Sets: IntegratedSecurity
Aliases:

Required: True
Position: 2
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Set-RMADFEGlobalOptions

SYNOPSIS

Sets global settings for recovery projects.

SYNTAX

```
Set-RMADFEGlobalOptions [[-ToAddress] <String>] [[-SendVerifyNotification] <Boolean>]
  [[-SendRecoveryNotification] <Boolean>] [[-CustomDriversPath] <String>]
  [[-AgentOperationAbortTimeout] <UInt32>] [-CheckBackupIntegrity <Boolean>]
  [-EnableSecureBootForVMs <Boolean>]
  [-EnableOSImageCache <Boolean>] [-OSImageCachePath <String>] [-
OSImageDefaultLocale <String>]
  [-OSImageDefaultTimeZone <String>] [-AzureVMDefaultOSVersion <String>] [-
AzureVMDefaultNumberOfCores <UInt32>]
  [[-VMSizeTemplate] <String>] [-EncryptionAtHost <Boolean>]
  [-Save] [<CommonParameters>]
```

DESCRIPTION

Sets global settings that will be applied to all recovery projects by default.

EXAMPLES

Example 1

```
PS C:\> Set-RMADFEGlobalOptions -ToAddress "to@domain.com" -  
SendVerifyNotification $true -SendRecoveryNotification $true
```

This command applies the specified settings to the configuration.

Example 2

```
PS C:\> Set-RMADFEGlobalOptions -ToAddress "to@domain.com" -Save
```

This command applies the specified settings to the configuration and saves the updated settings to the file.

PARAMETERS

-AgentOperationAbortTimeout

Specifies the path of a custom driver that you want to add to the Quest Recovery Environment image.

Type: UInt32

Parameter Sets: (All)

Aliases:

Required: False

Position: 12

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-AzureVMDefaultNumberOfCores

Specifies default number of cores for created Azure VM.

Type: UInt32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-AzureVMDefaultOSVersion

Specifies a default OS version for created Azure VM.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-VMSizeTemplate

Specifies a template for automatic VM size selection.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-CheckBackupIntegrity

Enables automatic integrity check after a backup is created.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-CustomDriversPath

Specifies the path to the Quest Recovery Environment image.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 11
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-EnableOSImageCache

Specifies if generated Windows images should be stored in the local cache and on the Hypervisor.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-EncryptionAtHost

Specifies if encryption at host should be enabled for Azure VM.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-EnableSecureBootForVMs

Specifies if Hyper-V and VMWare virtual machines will be created with secure boot enabled.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-OSImageCachePath

Specifies generated Windows images local cache path.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-OSImageDefaultLocale

Specifies generated Windows images OS default locale.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-OSImageDefaultTimeZone

Specifies generated Windows images OS default timezone.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Save

Saves the global settings to the file.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-SendRecoveryNotification

Indicates whether the email notification option is enabled for the restore process.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 7
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SendVerifyNotification

Indicates whether the email notification option is enabled for the verification process.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ToAddress

Specifies the recipient of email notifications.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Set-RMADFERecoveryMode

SYNOPSIS

Sets recovery mode for the current recovery project

SYNTAX

```
Set-RMADFERecoveryMode [-RecoveryMode] <RecoveryMode> [[-ExcludingDomains]  
<String[]>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet changes the recovery mode of the recovery project.

EXAMPLES

Example 1

```
PS C:\> Set-RMADFERecoveryMode -RecoveryMode SYSVOLRecovery
```

Sets up SYSVOL recovery mode on the recovery project

Example 2

```
PS C:\> Set-RMADFERecoveryMode -RecoveryMode DomainRecovery -  
ExcludingDomains @"domain1", "domain2")
```

Sets up Domain recovery mode on the recovery project and exclude "domain1" and "domain2" from recovering.

PARAMETERS

-ExcludingDomains

Specifies domains that must not be recovered when DomainRecovery mode selected.

Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-RecoveryMode

Specifies recovery mode which can accept one of the following values:

1. ForestRecovery - complete forest recovery mode
2. DomainRecovery - recover selected domains only
3. SYSVOLRecovery - recover SYSVOL only
4. Repromotion - recover domain controllers that were not recovered in previous recovery sessions

Type: RecoveryMode
Parameter Sets: (All)
Aliases:
Accepted values: ForestRecovery, DomainRecovery, SYSVOLRecovery, Repromotion

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Set-RMADFERecoverySchedule

SYNOPSIS

Applies settings to the recovery schedule for the RMADFE project.

SYNTAX

```
Set-RMADFERecoverySchedule [[-Schedules] <Schedule[]>] [-Credential]  
<PSCredential> [[-NewCredential] <PSCredential>]  
  [[-IsEnabled] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet applies settings to the recovery schedule for the current RMADFE project.

EXAMPLES

Example 1

```
PS C:\> $schedule = New-RMADFESchedule -Once -StartDate "2/20/2022 1:00"  
$credential = Get-Credential  
Set-RMADFERecoverySchedule -Schedules $schedule -Credential $credential -  
IsEnabled $true
```

Set a one-time schedule for the current project. Schedule is enabled and will run under the specified user account.

PARAMETERS

-Credential

Specifies credentials that will be used to run the command.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IsEnabled

Specifies whether the schedule is enabled.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-NewCredential

Credential to change an account to. If a new credential is specified, the Credential parameter should contain the previous account credential for a task.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Schedules

Specifies schedules for project verification.

Type: Schedule[]
Parameter Sets: (All)
Aliases:

Required: False
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Set-RMADFESchedule

SYNOPSIS

Applies settings to the verification schedule for the RMADFE project.

SYNTAX

```
Set-RMADFESchedule [[-Schedules] <Schedule[]>] [-Credential] <PSCredential>  
[[-NewCredential] <PSCredential>]  
[[-IsEnabled] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet applies settings to the verification schedule for the current RMADFE project.

EXAMPLES

Example 1

```
PS C:\> $schedule = New-RMADFESchedule -Once -StartDate "2/20/2022 1:00"  
$credential = Get-Credential  
Set-RMADFESchedule -Schedules $schedule -Credential $credential -IsEnabled  
$true
```

Set a one-time schedule for the current project. Schedule is enabled and will run under the specified user account.

PARAMETERS

-Credential

Specifies credentials that will be used to run the command.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IsEnabled

Specifies whether the schedule is enabled.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-NewCredential

Credential to change an account to. If a new credential is specified, the Credential parameter should contain the previous account credential for a task.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Schedules

Specifies schedules for project verification.

Type: Schedule[]
Parameter Sets: (All)
Aliases:

Required: False
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Set-RMADFEVerifySchedule

SYNOPSIS

Applies settings to the verification schedule for the RMADFE project.

SYNTAX

```
Set-RMADFEVerifySchedule [[-Schedules] <Schedule[]>] [-Credential]  
<PSCredential> [[-NewCredential] <PSCredential>]  
  [[-IsEnabled] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet applies settings to the verification schedule for the current RMADFE project.

EXAMPLES

Example 1

```
PS C:\> $schedule = New-RMADFESchedule -Once -StartDate "2/20/2022 1:00"  
$credential = Get-Credential  
Set-RMADFEVerifySchedule -Schedules $schedule -Credential $credential -  
IsEnabled $true
```

Set a one-time schedule for the current project. Schedule is enabled and will run under the specified user account.

PARAMETERS

-Credential

Specifies credentials that will be used to run the command.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IsEnabled

Specifies whether the schedule is enabled.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-NewCredential

Credential to change an account to. If a new credential is specified, the Credential parameter should contain the previous account credential for a task.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Schedules

Specifies schedules for project verification.

Type: Schedule[]
Parameter Sets: (All)
Aliases:

Required: False
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Set-RMADGlobalOptions

SYNOPSIS

Sets global application settings

SYNTAX

```
Set-RMADGlobalOptions [-ExchangeOAuth2 <Boolean>] [-EmailServer <String>]
[-EmailSender <String>]
[-ExtendedLogging <Boolean>] [-Properties <Hashtable>] [-IgnoreReadOnly]
[-WhatIf] [-Confirm]
[<CommonParameters>]
```

DESCRIPTION

Sets Recovery Manager global application settings

EXAMPLES

Example 1

```
PS C:\> Set-RMADGlobalOptions -ExchangeOAuth2 $False
Set-RMADGlobalOptions -EmailServer "WS.DomainName.local"
Set-RMADGlobalOptions -EmailSender "from@WS.DomainName.local"
Set-RMADGlobalOptions -ExtendedLogging $True
```

This command sets global email settings to use SMTP Authentication in Recovery Manager for Active Directory.

Example 2

```
PS C:\> $mailOptions = @{
    "Email.ExchangeOAuth2" = $True;
    "Email.ApplicationId"   = '111-111-111';
    "Email.TenantId"       = '123-456-789';
    "Email.Thumbprint"     = 'abcdefg';
    "Email.Sender"         = 'from@WS.DomainName.local'
}
Set-RMADGlobalOptions -Properties $mailOptions
```

This command sets global email settings to use Exchange OAuth2 in Recovery Manager for Active Directory using the 'Properties' option.

Example 3

```
PS C:\> $mailOptions = @{
    "Email.ExchangeOAuth2" = $False;
    "Email.Server"         = 'WS.DomainName.local';
    "Email.UseSSL"         = $True;
    "Email.AllowInsecureConnection" = $True;
    "Email.Sender"         = 'from@WS.DomainName.local';
    "Email.AuthRequired"   = $True;
    "Email.UserName"       = 'SmtAccount';
}
```

```

        "Email.Password" = 'Password'
    }
    Set-RMADGlobalOptions -Properties $mailOptions

```

This command sets global email settings to use SMTP Authentication in Recovery Manager for Active Directory using the 'Properties' option.

Example 4

```

PS C:\> Set-RMADGlobalOptions -Properties @{"UseRestoreAgentPort" = $True;
"DefaultRestoreMethod" = 0; "AgentPort" = 3845 }

```

This command sets Recovery Manager global settings for agent.

Example 5

```

PS C:\> $mailOptions = @{
    "Email.ExchangeOAuth2" = $True;
    "Email.ApplicationId" = '111-111-111';
    "Email.TenantId" = '123-456-789';
    "Email.Thumbprint" = 'abcdefg';
    "Email.Sender" = 'from@WS.DomainName.local';
    "Email.GccHighAccount" = $True
}
Set-RMADGlobalOptions -Properties $mailOptions

```

This command sets global email settings to use Exchange OAuth2 for U.S. Gcc High Account in Recovery Manager for Active Directory using the 'Properties' option.

PARAMETERS

-EmailSender

Specifies the sender field of email notifications

```

Type: String
Parameter Sets: (All)
Aliases:

```

```

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

```

-EmailServer

Specifies the SMTP server for email notifications

```

Type: String
Parameter Sets: (All)
Aliases:

```

```

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

```

-ExchangeOAuth2

Specifies Exchange OAuth2 mode for email notifications

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ExtendedLogging

Specifies diagnostic logs

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Properties

Allows you to modify the application settings.

To specify the properties you want to modify, use an associative array or hash table.

For more information, see the Windows PowerShell help topic on associative arrays (hash tables).

To open the topic, at the PowerShell command prompt enter the following: `help about_associative_array` Below are the properties you can modify by using this parameter.

The properties are grouped by the names of tabs in the "Computer Collection Properties" dialog box, because each property corresponds to an option on these tabs. To assign a new value to a property, use the following format: `PropertyName=Value E-MAIL TAB`

- `Email.ExchangeOAuth2`. Specifies the Exchange OAuth2 mode for email notifications
- `Email.Server`. Specifies the SMTP server for email notifications
- `Email.Port`. Specifies the SMTP port for email notifications
- `Email.Sender`. Specifies the sender of email notifications
- `Email.ApplicationId`. Specifies the application (client) ID for Exchange OAuth2 email notifications
- `Email.TenantId`. Specifies the directory (tenant) ID for Exchange OAuth2 email notifications
- `Email.GccHighAccount`. Specifies the U.S. Gcc High account option for Exchange OAuth2 email notifications
- `Email.Thumbprint`. Specifies the thumbprint for Exchange OAuth2 email notifications LOGGING TAB
- `ExtendedLogging`. Specifies option "Use diagnostic logging"
- `LogsFolder`. Specify the directory for application logs.

Type: Hashtable
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts for a confirmation before executing the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Set-RMADHybridRecoveryDomainOptions

SYNOPSIS

Sets the domain systems associated with the Hybrid Connector.

SYNTAX

```
Set-RMADHybridRecoveryDomainOptions -Domain <String> -DomainController  
<String> -Credentials <PSCredential>  
[-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Sets the domain and associated systems used for the Hybrid Connector.

EXAMPLES

Example 1

```
PS C:\>$password = ConvertTo-SecureString 'mypassword' -AsPlainText -Force  
PS C:\>$credentials = New-Object System.Management.Automation.PSCredential  
( 'rmad-admin', $password )  
PS C:\>Set-RMADHybridRecoveryDomainOptions -Domain rmad.local -  
DomainController DC1.rmاد.local -Credentials $credentials
```

Returns: Nothing on success; otherwise an error

PARAMETERS

-Credentials

Credentials used for connecting to the system that is running the Azure Active Directory Connector.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Domain

Domain which the Hybrid Connector will be using.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DomainController

The domain Controller that the Azure Active Directory Connector is installed on.

Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Shows what would happen if the cmdlet runs.
The cmdlet is not run.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Set-RMADHybridRecoveryOptions

SYNOPSIS

Sets the domain systems associated with the Hybrid Connector.

SYNTAX

Relay (Default)

```
Set-RMADHybridRecoveryOptions [-Enabled <Boolean>] [-RelayUrl <String>] [-RelayKeyName <String>] [-RelayKey <SecureString>] [-UsePackedBackups <Boolean>] [-SkipReplication <Boolean>] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

AADConnect

```
Set-RMADHybridRecoveryOptions [-Enabled <Boolean>] -AADConnectHost <String> -AADConnectCredentials <PSCredential> [-UsePackedBackups <Boolean>] [-SkipReplication <Boolean>] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Sets the domain and associated systems used in the Hybrid Connector.

EXAMPLES

Example 1

```
PS C:\>$key = ConvertTo-SecureString
'YDrMzfqWP8EliwRj41BtvNIZ4pH7i4pRW24klu8ZRcU=' -AsPlainText -Force
PS C:\>Set-RMADHybridRecoveryOptions -Enabled $true -RelayUrl
'https://relayurl' -RelayKeyName 'listenKey' -RelayKey $key -
UsePackedBackups $true -SkipReplication $true
```

Returns: Nothing on success; otherwise an error

PARAMETERS

-AADConnectCredentials

Credentials to connect to the Azure Active Directory Connector.

Type: PSCredential
Parameter Sets: AADConnect
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-AADConnectHost

The host where the Azure Active Directory Connector is installed.

Type: String
Parameter Sets: AADConnect
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Enabled

Setting to confirm if the Hybrid Connector is enabled. Values can be \$true or \$false.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-RelayKey

Relay key contained in the file received from ODR. This file is down loaded from ODR when the Hybrid Connection is configured in ODR.

Type: SecureString
Parameter Sets: Relay
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-RelayKeyName

Relay name contained in the file received from ODR. This file is down loaded from ODR when the Hybrid Connection is configured in ODR.

Type: String
Parameter Sets: Relay
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-RelayUrl

The URL contained in the file received from ODR. This file is down loaded from ODR when the Hybrid Connection is configured in ODR.

Type: String
Parameter Sets: Relay
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-SkipReplication

Configures the Hybrid Connector to perform a replication via the Azure Active Directory Connector. The values can be either \$true or \$false.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-UsePackedBackups

Configures the Hybrid Connector use any unpacked backups that are available. The values can be either \$true or \$false.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Shows what would happen if the cmdlet runs.
The cmdlet is not run.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Set-RMADReplicationConsole

SYNOPSIS

Sets replication properties of consoles in the replication console list.

SYNTAX

Id

```
Set-RMADReplicationConsole [-AccessCredential <PSCredential>] [-Enabled <Boolean>] [-FallbackCredential <PSCredential>] [-FileSyncEnabled <Boolean>] [-SourceFiles <String>] [-TargetFolder <String>] [-Id] <Int32[]> [<CommonParameters>]
```

ComputerName

```
Set-RMADReplicationConsole [-AccessCredential <PSCredential>] [-Enabled <Boolean>] [-FallbackCredential <PSCredential>] [-FileSyncEnabled <Boolean>] [-SourceFiles <String>] [-TargetFolder <String>] [-ComputerName] <String[]> [<CommonParameters>]
```

InputObject

```
Set-RMADReplicationConsole [-AccessCredential <PSCredential>] [-Enabled <Boolean>] [-FallbackCredential <PSCredential>] [-FileSyncEnabled <Boolean>] [-SourceFiles <String>]
```

```
[-TargetFolder <String>] [-InputObject] <ReplicationConsole[]>  
[<CommonParameters>]
```

DESCRIPTION

Updates user credentials for connecting to a specified computer, and enables/disables the manual and scheduled replication for the console.

EXAMPLES

Example 1

```
PS C:\> C:\>$credential = Get-Credential  
C:\>Set-RMADReplicationConsole -ComputerName Hostname1 -AccessCredential  
$credential -Enabled $true
```

This command changes the credentials for accessing the console on Hostname1, and enables the replication for the console.

Example 2

```
PS C:\> C:\>Set-RMADReplicationConsole -Id 1 -AccessCredential $credential  
-Enabled $true
```

This command changes the credentials for accessing the console with specified ID, and enables the replication for the console.

Example 3

```
PS C:\> C:\>Set-RMADReplicationConsole -ComputerName Hostname1 -  
FallbackCredential $([System.Management.Automation.PSCredential]::Empty)
```

This command removes the fallback account for the console on Hostname1.

Example 4

```
PS C:\> C:\>Set-RMADReplicationConsole -Id 1 -FileSyncEnabled $true -  
SourceFiles "C:\MyProjectFiles\*.frproj" -TargetFolder "C:\MyProjectFiles"
```

This command enables replication of the forest recovery project files for the console with specified ID.

PARAMETERS

-AccessCredential

Specifies the user credentials to read data from the target computer. The user must be a local Administrator on the target computer. To obtain the user credentials, create a PSCredential object using the Get-Credential cmdlet provided by Windows PowerShell. If you need to use the credentials of the currently logged in user, specify [System.Management.Automation.PSCredential]::Empty value for this parameter.

```
Type: PSCredential  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-ComputerName

Specifies the hostname of the replication console.

Type: String[]

Parameter Sets: ComputerName

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-Enabled

Set replication item enabled.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-FallbackCredential

Supplies a fallback account for replacing the account that is used by the backup schedule task. The account must have administrator privileges on the system(s) to be backed up. If you need to reset the fallback account, specify [System.Management.Automation.PSCredential]::Empty value for this parameter. You can use this parameter only when Full mode is set for the console.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-FileSyncEnabled

Enables replication of forest recovery project files.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Id

Specifies the ID of the replication console.

Type: Int32[]

Parameter Sets: Id
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False

-InputObject

Specifies the replication console object you want to update.

Type: ReplicationConsole[]
Parameter Sets: InputObject
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

-SourceFiles

Specifies which forest recovery project files to replicate from the source console.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-TargetFolder

Specifies the folder to store the forest recovery project files replicated from the source console.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Set-RMADReplicationSchedule

SYNOPSIS

Sets replication schedules for a computer.

SYNTAX

```
Set-RMADReplicationSchedule [-Schedules <Schedule[]>] -Credential  
<PSCredential> [-WhatIf] [-Confirm]  
[<CommonParameters>]
```

DESCRIPTION

Sets replication schedules with credentials for the Recovery Manager computer you specify.

EXAMPLES

Example 1

```
PS C:\> $credential = Get-Credential  
$schedule=(New-RMADSchedule -Daily -StartDate "9/20/2022 10:00" -  
DaysInterval 1), (New-RMADSchedule -Daily -StartDate "9/20/2022 22:00" -  
DaysInterval 1)  
C:\PS>Set-RMADReplicationSchedule -Schedule $schedule
```

This example illustrates how to replicate computers by using two replication schedules. The first line of this example creates a PSCredential object. The second line of this example creates two replication schedules and stores them in the \$schedule variable. One schedule invokes the replicate operation once in every two days at 10 a.m. Another schedule invokes the replicate operation once in every two days at 10 p.m. The two replication schedules become effective starting from the 20th September 2022. The third line of this example set schedules with credentials to the computer you specify.

Example 2

```
PS C:\> $credential = Get-Credential
C:\PS>Set-RMADReplicationSchedule -Credential $credential
```

This command updates the credentials for an existing schedule.

PARAMETERS

-Credential

Specifies the user credentials for setting the replication schedule. The user must be a local Administrator on the target computer. To obtain the user credentials, create a `PSCredential` object using the `Get-Credential` cmdlet provided by Windows PowerShell.

```
Type: PSCredential
Parameter Sets: (All)
Aliases:
```

```
Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Schedules

Causes the computer you specify to use the replication schedule you set by using the `New-RMADSchedule` cmdlet.

```
Type: Schedule[]
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Confirm

Prompts for confirmation before executing the command.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-Whatif

Describes what would happen if you ran the command without actually running the command.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi
```

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Start-RMADFERecovery

SYNOPSIS

Performs the restore operation for the RMADFE project.

SYNTAX

```
Start-RMADFERecovery [-Force] [-NotifyByEmail <Boolean>] [-GroupPasswords  
<Hashtable>] [-WhatIf] [-Confirm]  
[<CommonParameters>]
```

DESCRIPTION

This cmdlet starts the restore operation on the current RMADFE project.

EXAMPLES

EXAMPLE 1

```
PS C:\> Start-RMADFERecovery
```

This command performs the restore operation on the current RMADFE project.

EXAMPLE 2

```
$pwd1 = ConvertTo-SecureString "new password 1" -AsPlainText -Force
$pwd2 = ConvertTo-SecureString "new password 2" -AsPlainText -Force
$pwd3 = ConvertTo-SecureString "new password 3" -AsPlainText -Force
$passwords = @{ "Enterprise Admins"=$pwd1; "Domain Admins"=$pwd2;
"Administrators"=$pwd3 }
Start-RMADFERecovery -GroupPasswords $passwords
```

This command performs the restore operation and resets the password for domain users in the following privileged groups: Enterprise Admins, Domain Admins, and Administrators.

PARAMETERS

-Force

Overrides restrictions that prevent the command from succeeding, apart from security settings.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-GroupPasswords

Resets a password for domain users in specified privileged groups. The new password can be only used once, users must change their password after logging in with the new password. Use the Set-RMADFEDomain cmdlet to enable the password resetting before you reset the password with this parameter. The password resetting option is available only for Forest Recovery and Domain Recovery modes.

```
Type: Hashtable
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-NotifyByEmail

Allows notification about the recovery result by email.

```
Type: Boolean
Parameter Sets: (All)
Aliases:
```

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Confirm

Prompts for confirmation before running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-Whatif

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Start-RMADFERecoveryAgentOperation

SYNOPSIS

Starts the agent operation on the remote machine where Forest Recovery agent is installed.

SYNTAX

ProjectSpecificParameters

```
Start-RMADFERecoveryAgentOperation [[-ComputerName] <String>] -Parameters  
<OperationParameters>  
  [-AgentPort <UInt32>] [<CommonParameters>]
```

ProjectlessDomain

```
Start-RMADFERecoveryAgentOperation [-ComputerName] <String> [-DcCredential  
<PSCredential>]  
  -Parameters <OperationParameters> [-AgentPort <UInt32>]  
  [<CommonParameters>]
```

ProjectlessDsrn

```
Start-RMADFERecoveryAgentOperation [-ComputerName] <String> [-  
DsrnCredential <PSCredential>]  
  -Parameters <OperationParameters> [-AgentPort <UInt32>]  
  [<CommonParameters>]
```

ProjectlessLocal

```
Start-RMADFERecoveryAgentOperation [-ComputerName] <String> [-  
LocalCredential <PSCredential>]  
  -Parameters <OperationParameters> [-AgentPort <UInt32>]  
  [<CommonParameters>]
```

ProjectlessAll

```
Start-RMADFERecoveryAgentOperation [-ComputerName] <String> [-DcCredential  
<PSCredential>]  
  [-DsrnCredential <PSCredential>] [-LocalCredential <PSCredential>] -  
Parameters <OperationParameters>  
  [-AgentPort <UInt32>] [<CommonParameters>]
```

DESCRIPTION

Starts the agent operation on the remote machine where Forest Recovery agent is installed. Operation type and parameters are defined in the Parameters parameter.

EXAMPLES

Example 1

```
PS C:\> {{ Add example code here }}  
{{ Add example description here }}
```

PARAMETERS

-AgentPort

{{ Fill AgentPort Description }}

Type: UInt32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ComputerName

Target machine name or IP address.

Type: String
Parameter Sets: ProjectSpecificParameters
Aliases:

Required: False
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
Type: String
Parameter Sets: ProjectlessDomain, ProjectlessDsrms, ProjectlessLocal,
ProjectlessAll
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-DcCredential

Credentials used to access DC when DC booted in normal mode. Not used in most cases when Schannel authentication is used between agent and console.

Type: PSCredential
Parameter Sets: ProjectlessDomain, ProjectlessAll
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False

Accept wildcard characters: False

-DsrnCredntial

Credentials used to access DC when DC booted in the DSRM. Not used in most cases when Schannel authentication is used between agent and console.

Type: PSCredential
Parameter Sets: ProjectlessDsrn, ProjectlessAll
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-LocalCredential

Credentials used to access standalone machines. Not used in most cases when Schannel authentication is used between agent and console.

Type: PSCredential
Parameter Sets: ProjectlessLocal, ProjectlessAll
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Parameters

An OperationParameters object specifies operation type and parameters.

Type: OperationParameters
Parameter Sets: (All)
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Start-RMADFESStandbyInstance

SYNOPSIS

Starts the standby instance.

SYNTAX

```
Start-RMADFESStandbyInstance [-StandbyInstance] <StandbyInstanceRecord>  
[<CommonParameters>]
```

DESCRIPTION

Starts the standby instance.

EXAMPLES

EXAMPLE 1

```
PS C:\> $instances = Get-RMADFESStandbyInstance  
$latest = $instances | Sort-Object LastUpdatedDate -Descending | Select-  
Object -First 1  
Start-RMADFESStandbyInstance -StandbyInstance $latest
```

PARAMETERS

-StandbyInstance

Standby instance to be started

Type: StandbyInstanceRecord

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

ForestRecovery.RecoveryLogic.Sessions.StandbyInstanceRecord

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Start-RMADFEVerification

SYNOPSIS

Performs verification of the RMADFE project.

SYNTAX

```
Start-RMADFEVerification [-ComputerName <String[]>] [-NotifyByEmail  
<Boolean>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet collects and saves information that is used for recovery from all domain controllers in the recovery project. Then, it checks the project recovery settings against the collected information to provide you information about any inconsistencies. Start a new project session by calling the `Start-RMADFEProjectSession` cmdlet first. Use the `Get-RMADFEProjectSummary` cmdlet to track the progress of the project session.

EXAMPLES

EXAMPLE 1

```
PS C:\> Start-RMADFEVerification
```

This command performs verification of the current RMADFE project.

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-NotifyByEmail

Allows notification about the recovery result by email.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Start-RMADHybridRecoveryDiscovery

SYNOPSIS

Start the Hybrid Recovery Discovery to update the database with a new domain discovered via the backup. This cmdlet is "for internal use only".

SYNTAX

```
Start-RMADHybridRecoveryDiscovery [-WaitForCompletion] [-IgnoreReadOnly]
[<CommonParameters>]
```

DESCRIPTION

This cmdlet populates the Hybrid Connector database with a new domain entry which was discovered via the backup. This happens automatically after 10 minutes. This cmdlet is **"for internal use only"**.

EXAMPLES

Example 1

```
PS C:\> Start-RMADHybridRecoveryDiscovery
```

Example 2

```
PS C:\> Start-RMADHybridRecoveryDiscovery -WaitForCompletion
```

Waits for the hybrid recovery discovery process to complete before returning control to the user.

PARAMETERS

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-WaitForCompletion

Wait for the hybrid recovery discovery process to complete before returning control to the user.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

None

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

schema: 2.0.0

Start-RMADReplication

SYNOPSIS

Performs replication from other computers in the replication console list.

SYNTAX

```
Start-RMADReplication [-Id <Int32[]>] [-ComputerName <String[]>] [-AsJob]
[<CommonParameters>]
```

DESCRIPTION

Performs replication from other computers in the replication console list.

EXAMPLES

Example 1

```
PS C:\> Start-RMADReplication
```

This command performs replication.

Example 2

```
PS C:\> Start-RMADReplication -AsJob
```

This command performs the replication as a background job.

Example 3

```
PS C:\> Start-RMADReplication -Id 1
```

This command performs replication from a replication console by its ID.

Example 4

```
PS C:\> Start-RMADReplication -ComputerName ws1
```

This command performs replication from a replication console by its hostname.

PARAMETERS

-AsJob

Runs the command as a background job. You can use this parameter to run commands that take a significant time to complete.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ComputerName

Specifies the hostname of the replication console.

Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False

-Id

Specifies the ID of the replication console.

Type: Int32[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Start-RMADReportViewer

SYNOPSIS

Displays a report about the results of the online comparison or restore operation.

SYNTAX

```
Start-RMADReportViewer [<CommonParameters>]
```

DESCRIPTION

Displays a report about the results of the online comparison or restore operation.

EXAMPLES

Example

```
PS C:\> Start-RMADReportViewer
```

Displays the online comparison or restoration report.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Stop-RMADFECloudStorageUploadSession

SYNOPSIS

Cancel queued or running cloud storage upload session.

SYNTAX

Id

```
Stop-RMADFECloudStorageUploadSession [-Id] <Int32[]> [-IgnoreReadOnly]  
 [<CommonParameters>]
```

InputObject

```
Stop-RMADFECloudStorageUploadSession [-InputObject] <UploadSession[]> [-  
IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Cancel a queued or running cloud storage upload session. The copy of the backup is stopped.

EXAMPLES

Example 1

```
PS C:\> Stop-RMADFECloudStorageUploadSession -Id 4
```

Cancel cloud storage upload session with Id 4.

PARAMETERS

-Id

Specifies the upload session Id representing the upload session you want to stopped.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter

Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-InputObject

Specifies the UploadSession object representing the cloud storage upload session you want to cancel.

Type: UploadSession[]
Parameter Sets: InputObject
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.Int32[]

QuestSoftware.RecoveryManager.AD.FE.PowerShell.UploadSession[]

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Stop-RMADFESubordinateInstance

SYNOPSIS

Stops the standby instance.

SYNTAX

```
Stop-RMADFESubordinateInstance [-StandbyInstance] <RecoveryStandbyInstance>  
[<CommonParameters>]
```

DESCRIPTION

Stops the standby instance.

EXAMPLES

EXAMPLE 1

```
PS C:\> $instances = Get-RMADFESubordinateInstances  
$latest = $instances | Sort-Object LastUpdatedDate -Descending | Select-  
Object -First 1  
Stop-RMADFESubordinateInstance -StandbyInstance $latest
```

PARAMETERS

-StandbyInstance

Standby instance to be stopped

Type: StandbyInstanceRecord

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

ForestRecovery.RecoveryLogic.Sessions.StandbyInstanceRecord

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

schema: 2.0.0

Stop-RMADFWorkflow

SYNOPSIS

Stops the verification or recovery workflow of the recovery project.

SYNTAX

```
Stop-RMADFWorkflow [-ComputerName <String[]>] [<CommonParameters>]
```

DESCRIPTION

This cmdlet cancels the current workflow for the specified domain controllers, or the whole session if no parameters are provided.

EXAMPLES

EXAMPLE 1

```
PS C:\> Stop-RMADFWorkflow
```

PARAMETERS

-ComputerName

Specifies the fully qualified domain name of the computer.

Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Test-RMADBackup

SYNOPSIS

Checks the integrity of backups registered with Recovery Manager.

SYNTAX

Instance

```
Test-RMADBackup [-InputObject] <BackupInfo[]> [-ShareCredential  
<PSCredential>] [-UseStorageCredential]  
 [<CommonParameters>]
```

Id

```
Test-RMADBackup [-Id] <Int32[]> [-ShareCredential <PSCredential>] [-  
UseStorageCredential] [<CommonParameters>]
```

DESCRIPTION

Checks the integrity of backups registered with Recovery Manager. This operation calculates the checksum of the backup file and compares it with the checksum stored in the backup.

EXAMPLES

Example 1

```
PS C:\> Get-RMADBackup | Test-RMADBackup
```

Checks the integrity of all backups registered with Recovery Manager.

PARAMETERS

-Id

Specifies the identifier of the backup you want to check.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-InputObject

Accepts a backup object as input to the cmdlet. Enter a variable that contains the object or type a command or expression that gets the object.

Type: BackupInfo[]

Parameter Sets: Instance

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

-ShareCredential

Specifies credential for share folder that contains the backup.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-UseStorageCredential

Uses the account configured in the collection to access the remote storage. If the backup is not associated with any collection or no account is configured for the remote storage, the account specified in the `-ShareCredential` parameter will be used instead.

Type: `SwitchParameter`

Parameter Sets: (All)

Aliases:

Required: `False`

Position: `Named`

Default value: `None`

Accept pipeline input: `False`

Accept wildcard characters: `False`

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

QuestSoftware.RecoveryManager.AD.PowerShell.BackupInfo[]

System.Int32[]

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: `QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml`

Module Name: `Quest.RecoveryManager.AD.PowerShell`

online version:

schema: 2.0.0

Test-RMADSecureStorageBackup

SYNOPSIS

Checks the integrity of a backup on the secure storage server.

SYNTAX

Name

```
Test-RMADSecureStorageBackup [-BackupPath] <String> [-Name] <String>
[<CommonParameters>]
```

Server

```
Test-RMADSecureStorageBackup [-BackupPath] <String> [-Server]
<StorageServer> [<CommonParameters>]
```

DESCRIPTION

Checks the integrity of a backup on the secure storage server. This operation calculates the checksum of the backup file and compares it with the checksum stored in the backup.

EXAMPLES

Example 1

```
Test-RMADSecureStorageBackup -Name 'storage' -BackupPath
'E:\Backups\DC1.rmad.local\2022-09-10 14-54-49.bkf'
```

PARAMETERS

-BackupPath

Path to the backup file stored on the secure storage server.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Name

Specifies the name of the secure storage server.

```
Type: String
Parameter Sets: Name
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

-Server

Specifies the target storage server. Use `Get-RMADStorageServer` to get server objects.

Type: StorageServer
Parameter Sets: Server
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

System.String

QuestSoftware.RecoveryManager.AD.PowerShell.Cmdlets.StorageServersManagement.StorageServer

OUTPUTS

System.Object

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Update-RMADBackupAgent

SYNOPSIS

Upgrades Recovery Manager Backup Agent on a specified computer or on each computer in a particular Computer Collection.

SYNTAX

DC

```
Update-RMADBackupAgent [-Computer] <String> [[-Credentials] <PSCredential>]
[[-ConfigureFirewall] <Boolean>]
[-IgnoreReadOnly] [<CommonParameters>]
```

Collection

```
Update-RMADBackupAgent [[-Credentials] <PSCredential>] [[-
ConfigureFirewall] <Boolean>]
[-CollectionName] <String> [-IgnoreReadOnly] [<CommonParameters>]
```

DESCRIPTION

Allows you to upgrade Recovery Manager Backup Agent on a specified computer or on each computer in a particular Computer Collection.

EXAMPLES

Example 1

```
PS C:\> Update-RMADBackupAgent -CollectionName "New Computer Collection"
```

This code upgrades Recovery Manager Backup Agent on each computer in a collection named "New Computer Collection".

Example 2

```
PS C:\> $credential = Get-Credential
Update-RMADBackupAgent -Computer dc1 -Credentials $credential
```

This code connects to the computer "dc1" under the user represented by the "credential" object and upgrades Recovery Manager Backup Agent there.

PARAMETERS

-CollectionName

Specifies the name of the Computer Collection that includes the computers on which Backup Agent should be upgraded.

```
Type: String
Parameter Sets: Collection
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Computer

Specifies the name of the computer on which to upgrade a Recovery Manager Backup Agent.

```
Type: String
Parameter Sets: DC
```

Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ConfigureFirewall

Specifies whether Recovery Manager automatically configures Windows Firewall on domain controllers to allow backup operations.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Credentials

Specifies the user name and the password of the user account to use for connecting to the target computer and upgrading Backup Agent. Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Notes:

- The user should be a local Administrator on the target computer.
- If you omit this parameter, Backup Agent will be upgraded under the current user account.

Type: PSCredential
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShellFE
online version:

schema: 2.0.0

Update-RMADFEPProject

SYNOPSIS

Shows the difference between the current project and live Active Directory and updates the project.

SYNTAX

```
Update-RMADFEPProject [-ForestName] <String> [-Credential] <PSCredential> [-  
WhatIf] [-Confirm]  
    [<CommonParameters>]
```

DESCRIPTION

This cmdlet shows the difference between the currently opened recovery project and live Active Directory. The confirmation will be requested before applying changes to the project.

EXAMPLES

Example 1

```
PS C:\> $credentials = New-Object PSCredential(".\Administrator",  
(ConvertTo-SecureString 'Password' -AsPlainText -Force))
```

```
Update-RMADFEPProject -ForestName "acme.test" -Credential $credentials -  
WhatIf
```

Shows the difference between the current recovery project and the forest "acme.test".

Example 2

```
PS C:\> $credentials = New-Object PSCredential(".\Administrator",  
(ConvertTo-SecureString 'Password' -AsPlainText -Force))
```

```
Update-RMADFEProject -ForestName "acme.test" -Credential $credentials -  
Confirm:$true
```

```
Save-RMADFEProject -Path "UpdatedProject.frproj" -Password (ConvertTo-  
SecureString "protection password" -AsPlainText -Force)
```

Checks and shows the difference between the current project and the forest "acme.test", and then applies the changes to the project. To keep the project updated, you have to save it.

PARAMETERS

-Credential

Credentials that are used to connect to the target Active Directory to retrieve infrastructure information.

```
Type: PSCredential  
Parameter Sets: (All)  
Aliases:
```

```
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-ForestName

Name of the target Active Directory forest.

```
Type: String  
Parameter Sets: (All)  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Confirm

Automatically confirms the update of the recovery project.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases: cf
```

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

-WhatIf

If specified, this parameter shows difference only and does not apply any changes to the recovery project.

Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml
Module Name: Quest.RecoveryManager.AD.PowerShell
online version:

schema: 2.0.0

Update-RMADLicense

SYNOPSIS

Updates license key file.

SYNTAX

```
Update-RMADLicense [-File] <String> [<CommonParameters>]
```

DESCRIPTION

Allows you to update the current license key file to a new one.

EXAMPLES

Example 1

```
PS C:\> Update-RMADLicense -File C:\license.asc
```

Updates current license using license key file C:\license.asc.

PARAMETERS

-File

Full path to a new license key file.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

Quest Software creates technology and solutions that build the foundation for enterprise AI. Focused on data management and governance, cybersecurity and platform modernization, Quest helps organizations address their most pressing challenges and make the promise of AI a reality. Around the globe, more than 45,000 companies including over 90% of the Fortune 500 count on Quest Software. For more information, visit www.quest.com or follow Quest Software on X (formerly Twitter) and LinkedIn.

Technical support resources

Technical support is available to Quest customers with a valid maintenance contract and customers who have trial versions. You can access the Quest Support Portal at <https://support.quest.com>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to-videos
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product.