



syslog-ng Store Box 7.1.0

Upgrade Guide

Copyright 2023 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC .

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.
Attn: LEGAL Dept
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our Web site (<http://www.OneIdentity.com>) for regional and international office information.

Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal/trademark-information.aspx. All other trademarks are the property of their respective owners.

Legend

-  **WARNING: A WARNING icon highlights a potential risk of bodily injury or property damage, for which industry-standard safety precautions are advised. This icon is often associated with electrical hazards related to hardware.**
-  **CAUTION: A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.**

SSBUupgrade Guide
Updated - 01 February 2023, 14:02

For the most recent documents and product information, see [Online product documentation](#).

Contents

Preface	4
Prerequisites and Notes	5
Version numbering in SSB	5
Upgrade paths to SSB	5
Guidelines and support for direct upgrade paths in SSB	6
Possible upgrade path scenarios, and their recommended upgrade paths	7
Upgrade paths to the current version of SSB	7
Upgrade checklist	8
Upgrading to SSB 7.1.0	10
Upgrading SSB	10
Upgrading an SSB cluster	11
Updating the SSB license	12
Troubleshooting	13
About us	14
Contacting us	15
Technical support resources	16

Preface

Welcome to syslog-ng Store Box (SSB) version 7.1.0 and thank you for choosing our product. This document describes the process to upgrade existing SSB installations to SSB 7.1.0. The main aim of this paper is to aid system administrators in planning the migration to the new version of SSB.

For detailed information about versioning and supported upgrade paths in SSB, see [Version numbering in SSB](#) and "[Versions and releases of SSB](#)" in the [Administration Guide](#).

 **CAUTION:**

Read the entire document thoroughly before starting the upgrade.

Prerequisites and Notes

This section and its subsections contain information about the following:

Version numbering in SSB

All releases of syslog-ng Store Box (SSB) belong in the following categories (including their respective maintenance releases):

- **LTS release version**

Format: <major.0.maintenance>, for example, 6.0.0, 6.0.1

For more information, see the **Long Term Support (LTS)** section under [the syslog-ng Store Box Product Life Cycle Table](#).

- **Feature release version**

Format: <major.minor.maintenance>, for example, 4.9.1, or 6.5.0

For more information, see the **Feature release** section under [the syslog-ng Store Box Product Life Cycle Table](#).

Upgrade paths to SSB

These sections contain information about the general guidelines for supported direct upgrade paths in syslog-ng Store Box (SSB), the possible upgrade scenarios, and their recommended upgrade paths for upgrading from LTS or Feature releases to LTS or Feature releases, and detailed information about the possible upgrade paths to the current version of SSB (currently, version 7.1.0).

For detailed information, see the following subsections:

Guidelines and support for direct upgrade paths in SSB

This section provides general guidelines for supported direct upgrade paths in syslog-ng Store Box (SSB).

For more information about possible upgrade scenarios, and their recommended upgrade paths for upgrading from LTS or Feature releases to LTS or Feature releases, see [Possible upgrade path scenarios, and their recommended upgrade paths](#).

For more information about specific upgrade paths to the current release of SSB (version 7.1.0), see [Upgrade paths to the current version of SSB](#).

General guidelines for direct upgrade paths

The following general guidelines apply for direct upgrade paths in SSB at all times:

- **Maintenance version prerequisites**

Before you upgrade from any LTS or Feature release version, always make sure that the release you are using has the latest available maintenance version installed. Otherwise, always upgrade directly to the latest available maintenance version of the release version you are using.

Examples: meeting maintenance version prerequisites before upgrading

The following examples illustrate two different upgrade scenarios when you can not upgrade directly and have to meet the maintenance requirements first.

Feature release version

If your SSB appliance is at feature version 4.9.0, we need to do a direct upgrade to 4.9.1 (that is, to the latest available 4 F9 maintenance version) before upgrading forward.

LTS version

If your SSB appliance is at 5.0.1, we need to do a direct upgrade to version 5.0.4 (that is, to the latest available 5 LTS maintenance version) before upgrading forward.

- **Supported direct upgrade scenarios**

Direct upgrade scenarios are only available to the next LTS releases (or the preceding versions).

Example: direct upgrade

For example, from version 5.0.4, you can jump directly to versions 5.1.0, 5.2.0, ..., 6.0.1.

However, it is not possible to do a single-step, direct upgrade to a version that is larger than the next LTS release (for example, from version 5.1.0 to version 6.5.0).

NOTE: While it is not possible to do a single-step upgrade (for example, directly upgrading from version 5.1.0 to version 6.5.0), you can upgrade from version 5.1.0 to version 6.5.0 in two steps, by first upgrading to the latest available maintenance version of 6 LTS, and then further upgrading to version 6.5.0.

Possible upgrade path scenarios, and their recommended upgrade paths

The following examples illustrate possible upgrade scenarios, and their recommended upgrade paths for upgrading from LTS or Feature releases to LTS or Feature releases:

Example for	From	To	Recommended (optimal) upgrade path
LTS to next LTS upgrade	5.0.0	6.0.1	5.0.0 to 5.0.4, then to 6.0.1
Complex upgrade, with several upgrade steps	4.9.0	6.5.0	4.9.0 to 4.9.1, then to 5.0.4, then to 6.0.1, then to 6.5.0
Direct, single-step upgrade	6.1.0	6.5.0	6.1.0 to 6.5.0

From older releases, upgrade to 6 LTS first. For details, see [How to upgrade to syslog-ng Store Box 5 LTS](#).

For more information about specific upgrade paths to the current release of SSB (version 7.1.0), see [Upgrade paths to the current version of SSB](#).

For more information about guidelines for supported direct upgrade paths in SSB, see [Guidelines and support for direct upgrade paths in SSB](#).

Upgrade paths to the current version of SSB

This section contains detailed information about the possible upgrade paths to the current version of syslog-ng Store Box (SSB). The most recent SSB version is 7.1.0.

For more information about the versioning system in SSB, see [Version numbering in SSB](#).

For more information about guidelines for supported direct upgrade paths in SSB, see [Guidelines and support for direct upgrade paths in SSB](#).

Upgrade paths to the current version of SSB (version 7.1.0)

Upgrading to SSB version 6.5 is tested and supported using the following upgrade path scenarios:

- The latest SSB 6 LTS maintenance version (for example, 6.0.x) to version SSB 6.5
NOTE: Always upgrade to the latest available maintenance version of SSB 6 LTS before upgrading to SSB version 6.5.
- The latest maintenance versions of the previous, not yet discontinued, feature releases to version SSB 6.5

Upgrade checklist

The following list applies to all configurations:

- The firmware of your SSB appliance is not tainted (that is, none of its files were modified locally). If the firmware is tainted, a warning is displayed on the **Basic Settings > System > Version details** page.
Upgrading is not supported if the firmware is tainted. If your firmware is tainted, [contact our Support Team](#).
- You have backed up your configuration and your data.
For more information on creating configuration and data backups, see [Data and configuration backups](#).
- For added safety, you have also exported the current configuration of SSB.
For detailed instructions, refer to [Exporting the configuration of SSB](#).
- You have a valid [support portal](#) account.
To download the required firmware file and the new license file, you need a valid [support portal](#) account. To create an account, navigate to the [support portal](#) and follow the instructions on screen (you will need to enter your product's asset number, which is the license number or serial number you have been provided previously).
- You have downloaded the new 7.1.0 license file from [support portal](#). As license files are specific to each long term release, upgrading to SSB 7.1.0 removes any earlier license.
- You have downloaded the latest SSB firmware file from the [Downloads page](#).
For a details about the firmware file, see [Firmware in SSB](#).
- You have read the Release Notes (changelog) of the firmware(s) before updating. The Release Notes might include additional instructions specific to the

firmware version.

The Release Notes are available on the [syslog-ng Store Box Documentation page](#).

If you have a high availability cluster:

- **⚠ CAUTION: Before upgrading to SSB version 7.1.0 in High Availability (HA) mode, ensure that the nodes have already been restarted since the last upgrade. Otherwise, you have to restart the nodes before upgrading SSB to version 7.1.0.**
- You have IPMI access to the slave node. You can find detailed information on using the IPMI interface in the following documents:

For syslog-ng Store Box (SSB) Appliance 3000 and 3500, see the [Latest IPMI firmware for Syslog-ng Store Box 3000/3500 and One Identity Safeguard for Privileged Sessions 3000/3500 appliances](#).

For syslog-ng Store Box (SSB) T1 and syslog-ng Store Box (SSB) T4, see the [IPMI User's Guide](#).
- You have verified on the **Basic Settings > High Availability** page that the HA status is not degraded.
- If you have a high availability cluster with geocustering enabled: Perform the firmware upload steps an hour before the actual upgrade. Geocustering can introduce delays in the synchronization between the primary and the secondary node, and the secondary node might not be able to sync the new firmware from the primary node on time.

If you are upgrading SSB in a virtual environment:

NOTE: When setting up a virtual environment, carefully consider the configuration aspects such as CPU, memory availability, I/O subsystem, and network infrastructure to ensure the virtual layer has the necessary resources available. Please consult [One Identity's Product Support Policies](#) for more information on environment virtualization.

- You have created a snapshot of the virtual machine before starting the upgrade process.
- You have configured and enabled console redirection (if the virtual environment allows it).

During the upgrade, SSB displays information about the progress of the upgrade and any possible problems to the console, which you can monitor with IPMI (ILOM) or console access.

We recommend that you test the upgrade process in a non-production (virtual) environment first.

Upgrading SSB requires a reboot. We strongly suggest that you perform the upgrade on the production appliance during maintenance hours only, to avoid any potential data loss.

Upgrading to SSB 7.1.0

For details on upgrading your syslog-ng Store Box (SSB) installation to 7.1.0, see the following procedures.

Upgrading SSB

If you want to upgrade a SSB cluster, see [Upgrading an SSB cluster](#) on page 11.

Prerequisites

Read the following warnings before starting the upgrade process.

To upgrade a standalone SSB node to version 7.1.0

1. Stop SSB from accepting the incoming log traffic. Navigate to **Basic Settings > System > Service control** and click **Disable**.
2. Update the firmware of SSB using the web interface.
 - a. Navigate to **Basic Settings > System > Upgrade**.
 - b. Upload the new .ISO file.
 - c. When the upload is finished, click **Upgrade and reboot node**.
3. Navigate to **Basic Settings > System > System Control > This node**, and choose **Reboot**.

SSB attempts to boot with the new firmware. Wait for the process to complete.
4. *Recommended step.* To help troubleshoot potential issues following the upgrade, collect and save system information (create a debug bundle) now.

Navigate to **Basic Settings > Troubleshooting > System debug** and choose **Collect and save current system state info**.
5. Navigate to **Basic Settings > System > Version details** and check the version numbers of SSB. In case you encounter problems, you can find common troubleshooting steps in [Troubleshooting](#) on page 13.

6. Upload the new license file. For details, see [Updating the SSB license](#) on page 12.
7. Enable SSB to receive the incoming log traffic. Navigate to **Basic Settings > System > Service control** and click **Enable**.

Upgrading an SSB cluster

Prerequisites

Make sure that you have physically connected the IPMI interface to the network and that it is properly configured. This is important because you can only power the secondary node on through the IPMI interface. For details on configuring the IPMI interface, see "[Out-of-band management of SSB](#)" in the [Administration Guide](#).

To upgrade an SSB cluster

1. Stop SSB from accepting the incoming log traffic. Navigate to **Basic Settings > System > Service control** and click **Disable**.
2. Update the firmware of SSB using the web interface.
 - a. Navigate to **Basic Settings > System > Upgrade**.
 - b. Upload the new .ISO file.
 - c. When the upload is finished, click **Upgrade, reboot master, and shut down slave**.

3. Log in to the SSB web interface to verify that the primary node upgrade was successful.

Navigate to **Basic Settings > System > Version details** and check the version numbers of SSB. In case you encounter problems, you can find common troubleshooting steps in [Troubleshooting](#) on page 13.

4. Upload the new license file. For details, see [Updating the SSB license](#) on page 12.
5. Use the IPMI interface to start the secondary node.

The secondary node attempts to boot with the new firmware, and reconnects to the primary node to sync data. During the sync process, certain services (including Heartbeat) are not available. Wait for the process to finish, and the secondary node to boot fully.

6. Navigate to **Basic Settings > System > High availability & Nodes** and verify that the secondary node is connected, and has the same firmware versions as the primary node.

NOTE:

When upgrading an SSB cluster, the upgrade process on the slave node will only be completed once a takeover has been performed.

7. Enable SSB to receive the incoming log traffic. Navigate to **Basic Settings > System > Service control** and click **Enable**.

Updating the SSB license

To update the syslog-ng Store Box (SSB) license

1. Download the new 7.1.0 license file from [support portal](#).
You need a new license file for every long-term-supported release. If there is no license file for SSB 7.1.0 under your account, [contact our Licensing Team](#) and **Request a license key for a new version**.
2. Navigate to **Basic Settings > System > License**.
3. Click **Browse** and select the new license file.
You can upload compressed licenses (for example, .zip archives).
4. Click **Upload**, then **Commit**.

Troubleshooting

If you experience any strange behavior of the web interface, first try to reload the page by holding the SHIFT key while clicking the Reload button of your browser to remove any cached version of the page.

In the unlikely case that SSB encounters a problem during the upgrade process and cannot revert to its original state, SSB performs the following actions:

- Initializes the network interfaces using the already configured IP addresses.
- Enables SSH access to SSB, unless SSB is running in sealed mode. That way it is possible to access the logs of the upgrade process, which helps the Support Team to diagnose and solve the problem. Note that SSH access will be enabled on every active interface, even if management access has not been enabled for the interface.

In case the web interface is not available within 30 minutes of rebooting SSB, check the information displayed on the local console and [contact our Support Team](#).

About us

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales and other inquiries, such as licensing, support, and renewals, visit <https://www.oneidentity.com/company/contact-us.aspx>.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product