

Tutorial — How to use Duo multi-factor authentication with PSM

June 19, 2018

Abstract

A detailed tutorial about how to use Duo multi-factor authentication with Balabit's Privileged Session Management (PSM)



Table of Contents

1. Introduction	3
2. How PSM and Duo MFA work together	4
3. Technical requirements	5
4. How PSM and Duo work together — in detail	5
5. Mapping PSM usernames to Duo identities	7
6. Bypassing Duo authentication	8
7. Configure your Duo account for PSM	9
8. Configure PSM to use Duo multi-factor authentication	9
9. PSM Duo plugin parameter reference	11
9.1. [duo]	12
9.2. [plugin]	13
9.3. [auth]	14
9.4. [cache]	15
9.5. [ldap]	16
9.6. [username_transform]	17
9.7. [question_1]	18
10. Store sensitive plugin data securely	19
11. Perform multi-factor authentication with the PSM Duo plugin in terminal connections	19
12. Perform multi-factor authentication with the PSM Duo plugin in Remote Desktop connections	20
13. Learn more	22
13.1. About One Identity	22

1. Introduction

This document describes how you can use the services of *Duo* to authenticate the sessions of your privileged users with Balabit's Privileged Session Management (PSM).

Balabit's Privileged Session Management:

Balabit's Privileged Session Management (PSM) controls privileged access to remote IT systems, records activities in searchable, movie-like audit trails, and prevents malicious actions. PSM is a quickly deployable enterprise device, completely independent from clients and servers — integrating seamlessly into existing networks. It captures the activity data necessary for user profiling and enables full user session drill down for forensic investigations.

PSM acts as a central authentication gateway, enforcing strong authentication before users access sensitive IT assets. PSM can integrate with remote user directories to resolve the group memberships of users who access nonpublic information. Credentials for accessing information systems can be retrieved transparently from PSM's local credential store or a third-party password management system. This method protects the confidentiality of passwords as users can never access them. When used together with Duo (or another multi-factor authentication provider), PSM directs all connections to the authentication tool, and upon successful authentication, it permits the user to access the information system.

Integrating Duo with PSM:

PSM can interact with your Duo account and can automatically request strong multi-factor authentication for your privileged users who are accessing the servers and services protected by PSM. When used together with Duo, PSM directs all connections to the Duo tool, and upon successful authentication, it permits the user to access the information system.

The integration adds an additional security layer to the gateway authentication performed on PSM. If the Duo Mobile app is installed on the user's device (smartphone, notebook, smartwatch, and so on), the user can generate a one-time password on the device. This will be used for the authentication to the One Identity platform. This way, the device turns into a two-factor authentication token for the user. The one-time password is changed after every authentication and is generated using dynamic keys.

Meet compliance requirements


ISO 27001, ISO 27018, SOC 2, and other regulations and industry standards include authentication-related requirements, for example, multi-factor authentication (MFA) for accessing production systems, and the logging of all administrative sessions. In addition to other requirements, using PSM and Duo helps you comply with the following requirements:

- PCI DSS 8.3: Secure all individual non-console administrative access and all remote access to the cardholder data environment (CDE) using multi-factor authentication.
- PART 500.12 Multi-Factor Authentication: Covered entities are required to apply multi-factor authentication for:
 - Each individual accessing the covered entity's internal systems.
 - Authorized access to database servers that allow access to nonpublic information.
 - Third parties accessing nonpublic information.

- NIST 800-53 IA-2, Identification and Authentication, network access to privileged accounts: The information system implements multi-factor authentication for network access to privileged accounts.

2. Procedure – How PSM and Duo MFA work together

Figure 1. How PSM and Duo work together



- Step 1. A user attempts to log in to a protected server.
- Step 2. **Gateway authentication on PSM.**
PSM receives the connection request and authenticates the user. PSM can authenticate the user to a number of external user directories, for example, LDAP, Microsoft Active Directory, or RADIUS. This authentication is the first factor.
- Step 3. **Outband authentication on Duo.**
If gateway authentication is successful, PSM connects the Duo server to check which authentication factors are available for the user. Then PSM requests the second authentication factor from the user.
 - For OTP-like authentication factors, PSM requests the one-time password (OTP) from the user, and sends it to the Duo server for verification.
 - For the Duo push notification factor, PSM asks the Duo server to check if the user successfully authenticated on the Duo server.
- Step 4. If multi-factor authentication is successful, the user can start working, while PSM records the user's activities. (Optionally, PSM can retrieve credentials from a local or external credential store or password vault, and perform authentication on the server with credentials that are not known to the user.)

3. Technical requirements

In order to successfully connect PSM with Duo, you need the following components.

In Duo:

- A valid Duo subscription that permits multi-factor authentication.
- Your users must be enrolled in Duo and their access must be activated.
- The users must install the Duo Mobile app.

In PSM:

- A Balabit's Privileged Session Management appliance (virtual or physical), at least version 5 F1.
- A copy of the PSM Duo plugin. This plugin is an Authentication and Authorization (AA) plugin customized to work with the Duo multi-factor authentication service.
- PSM must be able to access the Internet (at least the API services). Since Duo is a cloud-based service provider, PSM must be able to access its web services to authorize the user. The connection also requires the *ikey*, *skey*, and *host* parameters:
 1. Log on to the *Duo Admin Panel* interface and navigate to **Applications**.
 2. Click **Protect an Application** and locate **Web SDK** in the applications list.
 3. Click **Protect this Application** to get your **integration key** (*ikey*), **secret key**, (*skey*), and **API hostname** (*host*). For details, see *Getting Started with Duo Security*.
- Depending on the factor you use to authenticate your users, your users might need Internet access on their cellphones.
- PSM supports Authentication and Authorization plugins in the RDP, SSH, and Telnet protocols.
- In RDP, using an **AA plugin** together with Network Level Authentication in a Connection Policy has the same limitations as using Network Level Authentication without domain membership. For details, see *Procedure 10.3.3, Network Level Authentication without domain membership* in *The Balabit's Privileged Session Management 5 F6 Administrator Guide*.
- In RDP, using an **AA plugin** requires TLS-encrypted RDP connections. For details, see *Procedure 10.5, Enabling TLS-encryption for RDP connections* in *The Balabit's Privileged Session Management 5 F6 Administrator Guide*.

Availability and support of the plugin

The PSM Duo plugin is available as-is, free of charge to every PSM customer from the *Appstore*. In case you need any customizations or additional features, *contact professionalservices@balabit.com*.

You can use the plugin on PSM 5 F5 and later. If you need to use the plugin on PSM 5 LTS, *contact professionalservices@balabit.com*.

4. Procedure – How PSM and Duo work together — in detail

Step 1. A user attempts to log in to a protected server.

Step 2. **Gateway authentication on PSM.**

PSM receives the connection request and authenticates the user. PSM can authenticate the user to a number of external user directories, for example, LDAP, Microsoft Active Directory, or RADIUS. This authentication is the first factor.

Step 3. Check if the user is exempt from multi-factor authentication.

You can configure PSM using whitelists and blacklists to selectively require multi-factor authentication for your users, for example, to create break-glass access for specific users.

- If multi-factor authentication is not required, the user can start working, while PSM records the user's activities. The procedure ends here.
- If multi-factor authentication is required, PSM continues the procedure with the next step.

For details on creating exemption lists, see *Section whitelist (p. 15)*.

Step 4. Determining the Duo username.

If the gateway usernames are different from the Duo usernames, you must configure the PSM Duo plugin to map the gateway usernames to the Duo usernames. The mapping can be as simple as appending a domain name to the gateway username, or you can query an LDAP or Microsoft Active Directory server. For details, see *Section 5, Mapping PSM usernames to Duo identities (p. 7)*.

Step 5. Outband authentication on Duo.

If gateway authentication is successful, PSM connects the Duo server to check which authentication factors are available for the user. Then PSM requests the second authentication factor from the user.

- For OTP-like authentication factors, PSM requests the OTP from the user, and sends it to the Duo server for verification.
- For the Duo push notification factor, PSM asks the Duo server to check if the user successfully authenticated on the Duo server.

Step 6. If multi-factor authentication is successful, the user can start working, while PSM records the user's activities. (Optionally, PSM can retrieve credentials from a local or external credential store or password vault, and perform authentication on the server with credentials that are not known to the user.)

Step 7. If the user opens a new session within a short period, they can do so without having to perform multi-factor authentication again. After this configurable grace period expires, the user must perform multi-factor authentication to open the next session. For details, see *Section 9.4, [cache] (p. 15)*.

5. Mapping PSM usernames to Duo identities

By default, PSM assumes that the Duo username of the user is the same as the gateway username (that is, the username the user used to authenticate on PSM during the gateway authentication). To identify the users, PSM uses the username (login) field in Duo, which is an email address.

If the gateway usernames are different from the Duo usernames, you must configure the PSM Duo plugin to map the gateway usernames to the Duo usernames. You can use the following methods:

- To simply append a string to the gateway username, configure the *append_domain_parameter*. In this case, PSM automatically appends the @ character and the value of this option to the username from the session, and uses the resulting username on the Duo server to authenticate the user. For example, if the domain is set as `append_domain: example.com` and the username is `Example.User`, the PSM plugin will look for the user `Example.User@example.com` on the Duo server.
- To look up the Duo username of the user from an LDAP/Active Directory database, configure the *[ldap]* section of the PSM Duo plugin. Typically, the PSM plugin queries the email address corresponding to the username from your LDAP or Active Directory database. For details on LDAP parameters, see *Section 9.5, [ldap] (p. 16)*.
- If you configure both the *append_domain_parameter* and the *[ldap]* section of the PSM Duo plugin, PSM appends the @ character and the value of the *append_domain* parameter to the value retrieved from the LDAP database.
- If you have configured neither the *Domain* parameter nor the *[ldap]* section, PSM assumes that the Duo username of the user is the same as the gateway username.

6. Bypassing Duo authentication

Having to perform multi-factor authentication to a remote server every time the user opens a session can be tedious and inconvenient for the users, and can impact their productivity. PSM offers the following methods to solve this problem:

- In PSM, the Connection policy determines the type of authentication required to access a server. If you do not need multi-factor authentication for accessing specific servers, configure your Connection policies accordingly.
- If the user opens a new session within a short period, they can do so without having to perform multi-factor authentication. After this configurable grace period expires, the user must perform multi-factor authentication to open the next session. For details, see *Section 9.4, [cache] (p. 15)*.
- You can configure PSM using whitelists and blacklists to selectively require multi-factor authentication for your users, for example, to create break-glass access for specific users. For details on creating exemption lists, see *Section whitelist (p. 15)*.

7. Procedure – Configure your Duo account for PSM

Prerequisites:

- Administrator access to your Duo account.
- Make sure that you have all the required components listed in *Section 3, Technical requirements (p. 5)*.

Step 1. Add people to your Duo account.

The users you want to authenticate with PSM must have an activated account in Duo. For details on adding or importing your users, see *Enrolling Users* in the Duo documentation.

Step 2. Enable Multi-factor Authentication (MFA) for your organization.

Optionally, you can create a Policy in Duo to enable MFA only for the group of users who you want to authenticate with PSM.

For details, see *Protecting Applications* in the Duo documentation.

Step 3. Create an API token.

Navigate to **Admin > API > Tokens**, click **Create Token**, and save it.

8. Procedure – Configure PSM to use Duo multi-factor authentication

Prerequisites:

- Your Duo API token.



Warning

According to the current Duo policies, your API token expires if it is not used for 30 days. Make sure that you use it regularly, because PSM will reject your sessions if the API token is expired.

- Administrator access to PSM.
- Make sure that you have all the required components listed in *Section 3, Technical requirements (p. 5)*.

Steps:

Step 1. Download the PSM Duo plugin.

PSM customers can download the plugin from *Appstore*.

Step 2. Upload the plugin to PSM.

Upload the plugin to PSM. For details, see *Procedure 18.5.2, Authorizing connections to the target hosts with a PSM plugin* in *The Balabit's Privileged Session Management 5 F6 Administrator Guide*.

Step 3. Configure the plugin on PSM.

The plugin includes a default configuration file, which is an ini-style configuration file with sections and name=value pairs. You can edit it on the **Policies > AA Plugin Configurations** page of the PSM web interface.

Step a. Configure the usermapping settings if needed. PSM must find out which Duo user belongs to the username of the authenticated connection. For that, it can query your LDAP/Microsoft Active Directory server. For details, see *Section 5, Mapping PSM usernames to Duo identities (p. 7)*.

Step b. Configure other parameters of your plugin as needed for your environment. For details, see *Section 9, PSM Duo plugin parameter reference (p. 11)*.

Step 4. **Configure a Connection policy and test it.**

Configure a Connection policy on PSM. In the **AA plugin** field of the Connection policy, select the PSM Duo plugin you configured in the previous step, then start a session to test it. For details on how a user can perform multi-factor authentication, see *Procedure 11, Perform multi-factor authentication with the PSM Duo plugin in terminal connections (p. 19)* and *Procedure 12, Perform multi-factor authentication with the PSM Duo plugin in Remote Desktop connections (p. 20)*.



Warning

According to the current Duo policies, your API token expires if it is not used for 30 days. Make sure that you use it regularly, because PSM will reject your sessions if the API token is expired.

9. PSM Duo plugin parameter reference

This section describes the available options of the PSM Duo plugin.

The plugin uses an ini-style configuration file with sections and name=value pairs. This format consists of sections, led by a [section] header and followed by name=value entries. Note that the leading whitespace is removed from values. The values can contain format strings, which refer to other values in the same section. For example, the following section would resolve the %(dir)s value to the value of the dir entry (/var in this case).

```
[section name]
dirname=%(dir)s/mydirectory
dir=/var
```

All reference expansions are done on demand. Lines beginning with # or ; are ignored and may be used to provide comments.

You can edit the configuration file from the PSM web interface. The following code snippet is a sample configuration file.

```
[duo]
# Do NOT use ikey and skey in production
; ikey=<API-integration-key>
; skey=<API-security-key>
host=<API-hostname>
timeout=60
ignore_conn_err=no

[plugin]
config_version=1
log_level=info
cred_store=<name-of-credstore-storing-sensitive-data>

[auth]
prompt=Hit Enter to send Duo push notification or provide the OTP:
whitelist=name-of-a-userlist

[username_transform]
append_domain=""

[ldap]
ldap_server_config=<PSM-LDAP-server-policy-name>
filter=(&(samAccountName={})(objectClass=user))
user_attribute=mail

[cache]
soft_timeout=15
hard_timeout=90
conn_limit=5

[question_1]
key=<name-of-name-value-pair>
prompt=<the-question-itself-in-text>
```

[duo]

```
disable_echo=No  
[question_2]...
```

9.1. [duo]

This section contains the options related to your Duo account.

```
[duo]  
# Do NOT use ikey and skey in production  
; ikey=<API-integration-key>  
; skey=<API-security-key>  
host=<API-hostname>  
timeout=60  
ignore_conn_err=no
```

ikey

Type:	string
Required:	yes
Default:	N/A



Warning

This parameter contains sensitive data. Make sure to store this data in your local credential store. Never use it in production.

For details, see "Store sensitive plugin data securely".

Only use this parameter in the configuration for testing purposes in a secure, non-production environment.

Description: The API integration key.

skey

Type:	string
Required:	yes
Default:	N/A



Warning

This parameter contains sensitive data. Make sure to store this data in your local credential store. Never use it in production.

For details, see "Store sensitive plugin data securely".

Only use this parameter in the configuration for testing purposes in a secure, non-production environment.

Description: The API security key.

[plugin]

host

Type:	string
Required:	yes
Default:	N/A

Description: The API host name.

timeout

Type:	integer [seconds]
Required:	no
Default:	60

Description: How long an HTTP request can take during the communication with the Duo server.

ignore_conn_err

Type:	yes no
Required:	no
Default:	no

Description: Determines how to handle the sessions if the Duo service is not available. If set to yes, the plugin assumes that the user successfully authenticated even if the plugin cannot access Duo to verify this.



Warning

Enabling this option allows the users to bypass multi-factor authentication if PSM cannot access the Duo service for any reason, for example, a network configuration error in your environment.

9.2. [plugin]

This section contains general plugin-related settings.

```
[plugin]
config_version=1
log_level=20
cred_store=<name-of-credstore-hosting-sensitive-data>
```

config_version

Type:	integer
Required:	yes
Default:	1

Description: The version number of the configuration format. This is used to enable potentially incompatible changes in the future. If provided, the configuration will not be upgraded automatically. If not provided, the configuration will be upgraded automatically.

[auth]

cred_store

Type: string
Required: no
Default: N/A

Description: The name of a local credential store policy configured on PSM. You can use this credential store to store sensitive information of the plugin in a secure way, for example, the *ikey/skey* values in the *[duo]* section. For details, see *Procedure 10, Store sensitive plugin data securely (p. 19)*.

log_level

Type: integer or string
Required: no
Default: info

Description: The logging verbosity of the plugin. The plugin sends the generated log messages to the PSM syslog system. You can check the log messages in the **Basic settings > Troubleshooting > View log files** section of the PSM web interface. Filter on the `plugin: string` to show only the messages generated by the plugins.

The possible values are:

- debug or 10
- info or 20
- warning or 30
- error or 40
- critical or 50

For details, see Python logging API's log levels: [Logging Levels](#).

9.3. [auth]

This section contains the options related to authentication.

```
[auth]
prompt=Hit Enter to send Duo push notification or provide the OTP:
whitelist=name-of-a-userlist
```

prompt

Type: string
Required: no
Default: Hit Enter to send push notification or provide the OTP:

Description: PSM displays this text to the user in a terminal connection to request an OTP interactively. The text is displayed only if the user uses an OTP-like factor, and does not send the OTP in the connection request.

[cache]

```
prompt=Hit Enter to send Duo push notification or provide the OTP:
```

whitelist

Type:	string
Required:	no
Default:	N/A

Description: The name of a user list configured on PSM (**Policies > User Lists**). You can use this option to selectively require multi-factor authentication for your users, for example, to create break-glass access for specific users.

- If you set the **Default Policy** of the user list to `Reject`, then the list is a whitelist, so the plugin will not request Duo authentication from the users on the list.
- If you set the **Default Policy** of the user list to `Accept`, then the list is a blacklist, so the plugin will request Duo authentication only from the users on the list.


For details on creating user lists, see *Procedure 7.8, Creating and editing user lists* in *The Balabit's Privileged Session Management 5 F6 Administrator Guide*.

9.4. [cache]

This section contains the settings that determine how soon after performing a Duo authentication must the user repeat the authentication when opening a new session.

After the first Duo authentication of the user, PSM will not request a new Duo authentication from the user as long as the new authentications would happen within `soft_timeout` seconds from each other. After the `hard_timeout` expires (measured from the first Duo login of the user), PSM will request a new Duo authentication.

In other words, after opening the first session and authenticating on Duo, the user can keep opening other sessions without having to authenticate again on Duo as long as the time between opening any two sessions is less than `soft_timeout`, but must authenticate on Duo if `hard_timeout` expires.



```
[cache]
soft_timeout=15
hard_timeout=90
conn_limit=5
```

soft_timeout

Type: integer [seconds]
Required: yes, if you want caching
Default: N/A

Description: The time in seconds after which the PSM plugin requires a new Duo authentication for the next new session of the user, unless the user successfully authenticates another session within this period.

hard_timeout

Type: integer [seconds]
Required: yes, if you want caching
Default: N/A

Description: The time in seconds after which the PSM plugin requires a new Duo authentication for the next new session of the user. The time is measured from the last Duo authentication of the user.

conn_limit

Type: integer [number of]

Description: The cache can be used *conn_limit* times without multi-factor authentication. If the number of logins exceeds this number, the plugin will request multi-factor authentication again. If this parameter is not set, the number of logins from cache are unlimited.

9.5. [ldap]

This section contains the settings you configure when you need to use an LDAP query to map the usernames from your audited sessions to the usernames in Duo.

To look up the Duo username of the user from an LDAP/Active Directory database, configure the *[ldap]* section of the PSM Duo plugin. Typically, the PSM plugin queries the email address corresponding to the username from your LDAP or Active Directory database. For details on LDAP parameters, see *Section 9.5, [ldap]* (p. 16).

If you configure both the *append_domain_parameter* and the *[ldap]_section* of the PSM Duo plugin, PSM appends the @ character and the value of the *append_domain* parameter to the value retrieved from the LDAP database.

For other methods of mapping gateway usernames to Duo usernames, see *Section 5, Mapping PSM usernames to Duo identities* (p. 7).

```
[ldap]
ldap_server_config=<PSM-LDAP-server-policy-name>
filter=(&(cn={})(objectClass=inetOrgPerson))
user_attribute=CN
```

[username_transform]

ldap_server_config

Type: string
Required: no
Default: N/A

Description: The name of a configured LDAP server policy in PSM. For details on configuring LDAP policies, see *Procedure 7.9, Authenticating users to an LDAP server* in *The Balabit's Privileged Session Management 5 F6 Administrator Guide*.

filter

Type: string
Required: no
Default: (&(cn={})(objectClass=inetOrgPerson))

Description: The LDAP filter query that locates the user based on the gateway username. The plugin automatically replaces the {} characters with the gateway username from the session.

```
filter=(&(cn={})(objectClass=inetOrgPerson))
```

user_attribute

Type: string
Required: no
Default: cn

Description: The name of the LDAP attribute that contains the Duo username.

9.6. [username_transform]

This section contains username transformation-related settings.

```
[username_transform]  
append_domain=""
```

append_domain

Type: string (nonrequired, no default)
Required: no
Default: N/A

Description: If the gateway usernames are different from the Duo usernames, you must configure the PSM Duo plugin to map the gateway usernames to the Duo usernames.

To simply append a string to the gateway username, configure the *append_domain_parameter*. In this case, PSM automatically appends the @ character and the value of this option to the username from the session, and uses the resulting username on the Duo server to authenticate the user. For example, if the domain is set as

[question_1]

`append_domain`: `example.com` and the username is `Example.User`, the PSM plugin will look for the user `Example.User@example.com` on the Duo server.

If you configure both the `append_domain_parameter` and the `[ldap]_section` of the PSM Duo plugin, PSM appends the `@` character and the value of the `append_domain` parameter to the value retrieved from the LDAP database.

For other methods of mapping gateway usernames to Duo usernames, see *Section 5, Mapping PSM usernames to Duo identities (p. 7)*.

9.7. [question_1]

Type:	integer [seconds]
-------	-------------------

Description: Used for communication between plugins. This is an interactive request/response right after authentication in order to supply data to credential store plugins. The question is transferred to the session cookie and all hooks of all plugins receive it.

For example, if you have an external authenticator app, you do not have to wait for the question to be prompted but can authenticate with a one-time password:

```
ssh otp=123456@root@scb
```

Name subsequent questions with the appropriate number, for example, `[question_1]`, `[question_2]`, and so on.

For details, see *Procedure 18.5.3, Performing authentication with AA plugin in terminal connections in The Balabit's Privileged Session Management 5 F6 Administrator Guide* and *Procedure 18.5.4, Performing authentication with AA plugin in Remote Desktop connections in The Balabit's Privileged Session Management 5 F6 Administrator Guide*.

key

Type:	string
Required:	yes
Default:	N/A

Description: The name of the name-value pair.

prompt

Type:	string
Required:	yes
Default:	N/A

Description: The question itself in text format.

disable_echo

Type: boolean yes|no
Required: no
Default: no

Description: Whether the answer to the question is visible (yes), or replaced with asterisks (no).

10. Procedure – Store sensitive plugin data securely

Purpose:

By default, the configuration of the plugin is stored on PSM in the configuration of PSM. Make sure that you store the sensitive parameters (for example, *ikey* and *skey*) of the plugin in an encrypted way. To do this, complete the following procedure.

Steps:

- Step 1. Log in to PSM and create a local Credential Store. For details, see *Procedure 18.4.1, Configuring local Credential Stores* in *The Balabit's Privileged Session Management 5 F6 Administrator Guide*. Instead of usernames and passwords, you will store the configuration parameters of the plugin in this Credential Store.
- Step 2. Add the plugin parameters you want to store in an encrypted way to the Credential Store. You can store any configuration parameter of the plugin in the Credential Store, but note that if an option appears in the Credential Store, the plugin will use it. If the same parameter appears in the configuration of the plugin, it will be ignored.
 - Enter the name of the configuration section without the brackets in the **HOST** field (for example, duo).
 - Enter the name of the plugin parameter in the **USERNAME** field (for example, ikey).
 - Enter the value of the plugin parameter in the **PASSWORD** field.
- Step 3. Commit your changes, and navigate to the configuration of the plugin on the **Policies > AA Plugin Configurations** page.
- Step 4. In the plugin configuration file, enter the name of the local Credential Store under the *[plugin]* section, in the *cred_store* parameter.

11. Procedure – Perform multi-factor authentication with the PSM Duo plugin in terminal connections

Purpose:

To establish a terminal connection (SSH, TELNET, or TN3270) to a server, complete the following steps.

Steps:

- Step 1. Connect to the server.
 - If you can authenticate using an OTP or token, encode the OTP as part of the username. You can use the @ as a field separator. For example:

```
ssh otp=YOUR-ONE-TIME-PASSWORD@user@server
```

Replace *YOUR-ONE-TIME-PASSWORD* with your actual OTP. If needed, you can specify the type of OTP as a prefix to the OTP. For example, to specify the OTP of a YubiKey token:

```
ssh otp=y_YOUR-ONE-TIME-PASSWORD@user@server
```

- Google Authenticator: g
- inWebo Authenticator: o
- Symantec token: s
- YubiKey: y
- RSA token: r

- If you need to authenticate using the Duo Verify push notification, approve the connection in your mobile app.

Step 2. If PSM prompts you for further information, enter the requested information. If you need to authenticate with an OTP, but you have not supplied the OTP in your username, you will be prompted to enter the OTP.

Step 3. Authenticate on the server.

Step 4. If authentication is successful, you can access the server.

12. Procedure – Perform multi-factor authentication with the PSM Duo plugin in Remote Desktop connections

Purpose:

To establish a Remote Desktop (RDP) connection to a server when the **AA plugin** is configured, complete the following steps.

Steps:

Step 1. Open your Remote Desktop client application.

Step 2. If you have to provide additional information to authenticate on the server, you must enter this information in your Remote Desktop client application in the **User name** field, before the regular content (for example, your username) of the field.

If you can authenticate using an OTP or token, encode the OTP as part of the username. To encode additional data, you can use the following special characters:

- % as a field separator
- ~ as the equal sign
- ^ as a colon (for example, to specify the port number or an IPv6 IP address)

For example, use the following format:

```
domain\otp~YOUR-ONE-TIME-PASSWORD%Administrator
```

Replace *YOUR-ONE-TIME-PASSWORD* with your actual OTP. If needed, you can specify the type of OTP as a prefix to the OTP. For example, to specify the OTP of a YubiKey token:
domain\otp~y_YOUR-ONE-TIME-PASSWORD%Administrator

- Google Authenticator: g
- inWebo Authenticator: o
- Symantec token: s
- YubiKey: y
- RSA token: r

Step 3. Connect to the server.

If you need to authenticate using the Duo Authenticator push notification, approve the connection in your mobile app.

Step 4. Authenticate on the server.

Step 5. If authentication is successful, you can access the server.

13. Learn more

To find out more about PSM, visit the [One Identity page](#).

If you need help in connecting your Duo account with Balabit's Privileged Session Management, [contact our Sales Team](#) or contact_professionalservices@balabit.com.

13.1. About One Identity

One Identity LLC, is a leading provider of Privileged Access Management (PAM) and Log Management solutions. Founded in 2000, One Identity has a proven track record of helping businesses reduce the risk of data breaches associated with privileged accounts. With offices in the United States and Europe, and a global client list that includes 25 Fortune 100 companies, One Identity and its network of reseller partners serves more than 1,000,000 corporate users worldwide.

For more information, visit www.balabit.com, read the One Identity blog, or follow us on Twitter via @balabit, LinkedIn or Facebook.

To learn more about commercial and open source One Identity products, request an evaluation version, or find a reseller, visit the following links:

- [Privileged Session Management homepage](#)
- [One Identity Documentation page](#)
- To request an evaluation version, [contact our Sales Team](#)

About One Identity

One Identity helps organizations optimize identity and access management (IAM). Our combination of offerings, including a portfolio of identity governance, access management, privileged management and identity as a service solutions, enables organizations to achieve their full potential — unimpeded by security, yet safeguarded against threats. For more information, visit oneidentity.com.