



One Identity Manager 8.1.2

API Designer User and Development Guide

Copyright 2020 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC .

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.
Attn: LEGAL Dept
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our Web site (<http://www.OneIdentity.com>) for regional and international office information.

Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal. All other trademarks are the property of their respective owners.

Legend

 **WARNING:** A WARNING icon highlights a potential risk of bodily injury or property damage, for which industry-standard safety precautions are advised. This icon is often associated with electrical hazards related to hardware.

 **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.

One Identity Manager API Designer User and Development Guide
Updated - March 2020
Version - 8.1.2

Contents

API Designer	7
Basic principles of API development	8
Examples and help – Software Development Kit	9
Quick start – Creating an API	10
Working with the API Designer	11
Starting the API Designer	11
Project types	12
Changing the project type	12
Solution projects	13
Importing solution project changes into a database	14
User interface	15
Menu bar	16
Toolbar	19
Status bar	20
Navigation	21
Opening the navigation	22
Start page	23
Opening the start page	23
Global settings	23
Changing global settings	26
Switching languages	26
Database objects	27
Object properties	27
Displaying object properties	28
Managing objects in a project (solution)	29
Opening the solution	30
Editing database objects (definition tree view)	30
Opening the definition tree view	31
Context menu in the definition tree window	32
Extensions	34

Viewing and saving generated code belonging to a node	34
Node editor view	35
Labeling changes	37
Using change labels	38
Creating a change label	38
Change management	39
Deleting change labels	40
Find and replace	40
Running a search	43
Multilingual captions	44
Creating multilingual captions	45
Searching for a multilingual caption	45
Editing a multilingual caption	46
Deleting a multilingual caption	47
Managing database queries	48
Displaying database queries	49
Creating a database query	50
Editing a database query	50
Testing a database query	51
Deleting a database query	52
Managing tabs	52
Managing layouts	53
Displaying the change history (command list)	54
Opening the command list	54
Bookmarks	55
Editing bookmarks	55
Setting bookmarks	56
Deleting bookmarks	57
Compiling an API	57
Testing a compilation	58
Starting a compilation	59
Managing compilation errors and warnings (task window)	60
Opening the task window	61
Resolving errors and warnings	61
Opening the compiling log	61

Managing versions (compilation branches)	62
Selecting and using compilation branches	62
Creating compilation branches	63
Editing compilation branches	63
Deleting compilation branches	64
Testing an API	64
Linking C# projects to the API Designer	65
API projects	68
Creating API projects	68
Editing API projects	69
Deleting API projects	70
Configuring authentication	71
Configuring the compilation	74
Assigning API files to an API project	74
Importing API projects	75
API files	76
Creating API files	77
Editing API files	77
Deleting API files	78
Assigning API files to an API project	78
Importing API files	79
API Server	81
ImxClient command line program	82
Starting the ImxClient command line program	82
ImxClient command overview	82
help	83
compile-app	83
repl	84
branch	84
connect	85
compile-api	85
fetch-files	87
push-files	87
get-apistate	88

get-filestate	88
setup-web	89
run-apiserver	90
check-translations	91
About us	92
Contacting us	92
Technical support resources	92
Index	93

API Designer

The API Designer allows you to create, record, compile, and publish a REST API (Representational State Transfer Application Programming Interface) in the quickest way possible. This API is based on the OpenAPI Specification and the One Identity Manager database model.

The main benefits of API Designer include:

- Offers easy and fast operation.
- The finished API "understands" the One Identity Manager database model.
- Modifications to the API are transparent.
- Supports the principles of good API design.
- OpenAPI support: APIs that you create using the API Designer are based on the OpenAPI specification standard. This allows you to make use of other tools, including:
 - Swagger: Use Swagger to create code, documentation, and test cases.
 - Postman: Use Postman to test the various methods of your API.

Basic principles of API development

The main components of an API created using the API Designer are files and projects.

Basic information on [API files](#):

- You can use API files to send data to the application or request data from the application.
- An API file can belong to more than one project.

The basics of [API projects](#):

- API projects combine multiple API files into logical sections. The API project includes the configuration.

Related topics

- [Quick start – Creating an API](#) on page 10

Examples and help – Software Development Kit

To make it easier for you to start developing your API with the API Designer, One Identity provides a Software Development Kit (SDK) with lots of commented code example.

The SDK can be found on the installation medium in the directory `QBM\dvd\AddOn\ApiSamples`.

Quick start – Creating an API

The following provides a rough list of the steps you must take to create an API in the API Designer:

1. [Start](#) the API Designer.
2. [Create](#) API files (in which you can define an API method, for example).
3. [Create](#) an API project.
4. [Configure](#) the authentication for the API project (Single Sign-On, for example).
5. [Assign](#) the created API files to the API project.
6. [Test](#) the API.
7. [Compile](#) the API.
8. [Save](#) the changes to the database.

Related topics

- [Starting the API Designer](#) on page 11
- [Creating API files](#) on page 77
- [Creating API projects](#) on page 68
- [Configuring authentication](#) on page 71
- [Assigning API files to an API project](#) on page 78
- [Testing an API](#) on page 64
- [Compiling an API](#) on page 57
- [Importing solution project changes into a database](#) on page 14

Working with the API Designer

This section provides you with general information on working with the API Designer.

For example, you will learn:

- How the API Designer [interface](#) is structured
- How to edit your [projects](#) - locally or within the database itself
- How to [edit database objects](#)
- To [compile an API](#)

and much more.

Starting the API Designer

Before you start developing your API, you must start the API Designer.

To start the API Designer

1. Go to the installation path for API Designer.
2. Run the `ApiDesigner.Editor.exe` application.
The API Designer opens.
3. Perform one of the following tasks:
 - To use an existing connection to the One Identity Manager database, select it in the **Select a database connection** menu.
 - To create a new connection to the One Identity Manager database, click **Add new connection** and enter a new connection.
4. Select the authentication method and enter the login data for the database under **Authentication method**.
5. Click **Connect**.
6. In the **Select project save type** dialog, perform one of the following tasks:

- Click **Database project** to save the project in the database.
 - Click **Solution project** to save the project within a solution.
| **TIP:** For more information, see [Project types](#) on page 12.
7. (Optional) To save the selected storage type for future projects, select the **Use selected project as default** option.
 8. Click **OK**.
The API Designer opens and displays the [start page](#).

Related topics

- [Start page](#) on page 23
- [Project types](#) on page 12

Project types

The API Designer distinguishes between two different project types for saving your changes.

- Database project: The project will be stored in the database. Your saved changes are visible to others.
- Solution project: API Designer allows file-based editing of custom objects **locally** on your own computer. For more information, see [Solution projects](#) on page 13.

Related topics

- [Changing the project type](#) on page 12
- [Solution projects](#) on page 13
- [Importing solution project changes into a database](#) on page 14
- [Menu bar](#) on page 16

Changing the project type

You can save your project as a [database project](#) or as a [solution project](#). For more information, see [Project types](#) on page 12.

To save the project as a database project

1. On the menu bar, click **Edit | Set project type**.
2. In the **Select the project type** dialog, click **Database project**.
3. (Optional) To save the selection and use it the next time you start the API Designer,

enable the option **Use selected project as default**.

TIP: To undo this setting:

1. Click **Connection | Settings** on the menu bar.
2. Expand the **Editor** pane in the **Global settings** dialog.
3. In the **Editor** pane, select the **Ask for project type at each start** option.
The next time the program is started, the **Select the project type** dialog is displayed.

4. Click **OK**.

To save the project as a solution project

1. On the menu bar, click **Edit | Set project type**.
2. In the **Select the project type** dialog, click **Solution project**.
3. Perform one of the following actions:
 - Click **Create solution** and use the wizard to create a new solution.
 - Click **Load solution** and enter the path to an existing solution.
 - Click the solution most recently used.
4. (Optional) To save the selection and use it the next time you start the API Designer, enable the option **Use selected project as default**.

TIP: To undo this setting:

1. Click **Connection | Settings** on the menu bar.
2. Expand the **Editor** pane in the **Global settings** dialog.
3. In the **Editor** pane, select the **Ask for project type at each start** option.
The next time the program is started, the **Select the project type** dialog is displayed.

5. Click **OK**.

Related topics

- [Project types](#) on page 12
- [Menu bar](#) on page 16

Solution projects

API Designer allows for custom objects to be edited **locally** in a file-based format on your own computer. To do this you will need to export any custom objects stored within the database to the API Designer. In other words, you must use the "solution project" project type (see [Changing the project type](#) on page 12).

To import the changes made to the solution project back into the database, follow the instructions in [Importing solution project changes into a database](#) on page 14.

After exporting these objects from the database, you can edit and remove them on your computer, or supplement them with additional objects. Local object editing is no different than editing within the database project.

During export, any objects contained in the selected module are copied to the hard drive:

- API projects
- API files

Related topics

- [Changing the project type](#) on page 12
- [Importing solution project changes into a database](#) on page 14
- [Menu bar](#) on page 16

Importing solution project changes into a database

Changes that have been executed within a [solution project](#) must be transferred into the One Identity Manager database.

To import object into the One Identity Manager database

1. Click **Edit | Import objects into database** on the menu bar.
2. In the **Import objects into database** dialog, enable the option **Remove deleted objects from database**. Objects that you have deleted from your solution project are now also deleted from the database.
3. Go to **Solution objects** to select the objects that you want to change and export into the database.

TIP: To select or deselect listed objects quickly, enable the **Select all/deselect all** option.

4. Click **Continue**.
5. Click **Finished**.

Related topics

- [Solution projects](#) on page 13
- [Project types](#) on page 12

User interface

This section will give you a rough overview of the graphical user interface of the API Designer.

Use the mouse and keyboard to interact with the API Designer's graphical user interface. Use a screen resolution of at least 1280 x 1024 pixels and a minimum color depth of 16 bits for optimum display.

TIP: The API Designer view can be customized at any time to suit your needs by moving, closing, or hiding items.

Main user interface components

- **Top – Title bar**

The title bar shows the program icon, program name, and connected database (including the current user).

- **Top – Menu bar**

You can use the menus on the menu bar to access submenus and to access and execute many functions in API Designer quickly. For more information, see [Menu bar](#) on page 16.

- **Top – Toolbar**

The toolbar contains different icons that you can click to access other functions. For more information, see [Toolbar](#) on page 19.

- **Left – Navigation**

Use the navigation to manage (create, open, delete) API configurations, API files, and API projects. You can also access the most recently edited file here. For more information, see [Navigation](#) on page 21.

- **Center – Work pane**

The center pane is where other work panes for editing are shown, such as the [Definition tree view](#). When you open objects, they are shown in the work pane in separate [Tabs](#).

- **Bottom – Status bar**

The status bar shows information such as database activity, project information, the connected database, and the current user. For more information, see [Status bar](#) on page 20.

Start page

The start page is displayed when the API Designer starts up.

On the start page, you can:

- Use [compilation branches](#) to store different versions of your API in the database.
- [Test](#) your API locally

- [Compile the API](#) and then write it to the database
- Use the API Designer to [connect and edit](#) C# projects

For more information, see [Start page](#) on page 23.

Detailed information about this topic

- [Menu bar](#) on page 16
- [Toolbar](#) on page 19
- [Status bar](#) on page 20
- [Navigation](#) on page 21
- [Start page](#) on page 23

Menu bar

You can use the menus on the menu bar to access submenus and to access and execute many functions in API Designer quickly. The following table provides you with information about each menu.

Table 1: Menus and menu items on the menu bar.

Menu	Menu item	Description
Connection		
	Settings	Opens the Global settings dialog. You can configure the basic settings for API Designer here. For more information, see Global settings on page 23.
	Exit	Closes the program.
Edit		
	Set project type	Opens the Select the project type dialog. Select whether the project should be saved as a database or solution project here. For more information, see Project types on page 12 and Changing the project type on page 12.
	Import objects into database	Opens the Import objects into database dialog. From here you can import new and modified objects from your solution project into your One Identity Manager database. For more information, see Importing solution project changes into a database on page 14.
	Change standard	From here you can change the solution project that is to be used here.

Menu	Menu item	Description
	project file	
	Find and replace	<p>Opens the Find and replace dialog. You can search through documents using certain terms or strings and replace where necessary here.</p> <p>For more information, see Find and replace on page 40.</p>
	Find next	<p>Performs the search with the search parameters specified in the Find and replace dialog.</p> <p>The search continues without reopening the dialog.</p>
	Captions	<p>Opens the Multilingual captions dialog. You can create and edit multilingual captions here.</p> <p>For more information, see Multilingual captions on page 44.</p>
	Import object	<p>You can use this menu item to import API projects and API files into the API Designer.</p> <p>For more information, see Importing API projects on page 75 and Importing API files on page 79.</p>
	Edit database queries	<p>Opens the Edit database queries dialog. You can add, change, or delete database queries here.</p> <p>For more information, see Managing database queries on page 48.</p>
View		
	Tabs	<p>Opens the Tabs dialog. You can manage open tabs here. For more information, see Managing tabs on page 52.</p>
	Restore standard layout	<p>Restores the default layout. For more information, see Managing layouts on page 53.</p>
	Restore standard layout (including size)	<p>Restores the default layout and the default window size. For more information, see Managing layouts on page 53.</p>
	Restore saved layout	<p>Restores the layout that you saved earlier (see Save layout on the menu). For more information, see Managing layouts on page 53.</p>
	Save layout	<p>After you have customized the layout of the API Designer to suit your needs, you can save it and restore it at any time. For more information, see Managing layouts on page 53.</p>
	Start page	<p>Opens the start page.</p>

Menu	Menu item	Description
		For more information, see Start page on page 23.
	Solution	<p>Opens the Solution window. The solution can be used to display and manage any objects in the API Designer that can be opened from the navigation menu.</p> <p>For more information, see Managing objects in a project (solution) on page 29.</p>
	Node editor	<p>Opens the Node editor view. You can edit a node's properties here.</p> <p>For more information, see Node editor view on page 35.</p>
	Tasks	<p>Opens the Tasks view. Compilation errors and warnings can be viewed here.</p> <p>For more information, see Managing compilation errors and warnings (task window) on page 60.</p>
	Command List	<p>Opens the Command list window. You can view the change history of the selected database object here and undo any changes where necessary.</p> <p>For more information, see Displaying the change history (command list) on page 54.</p>
	Compilation	<p>Opens the Compiling window. You can view the compilation log here.</p> <p>For more information, see Opening the compiling log on page 61.</p>
	Bookmarks	<p>Opens the Bookmarks window. Bookmarks can be managed here.</p> <p>For more information, see Bookmarks on page 55.</p>
	Navigation	<p>Opens the navigation view. This can be used to manage (create, open, delete) API files, and API projects. You can also access the most recently edited file here.</p> <p>For more information, see Navigation on page 21.</p>
Help		
	Community	Opens the One Identity forum.
	Support portal	Opens the support portal website.
	Training	Opens the training website.
	Online documentation	Opens One Identity's documentation website.
	Info	Opens a dialog. Detailed information on the API Designer is

Menu	Menu item	Description
		available here (system information, version number, information about the software producer, installed modules etc.).


Related topics







- [User interface](#) on page 15
- [Global settings](#) on page 23
- [Changing the project type](#) on page 12
- [Find and replace](#)
- [Multilingual captions](#)
- [Importing API projects](#)
- [Managing database queries](#) on page 48
- [Managing tabs](#) on page 52
- [Managing layouts](#) on page 53
- [Start page](#) on page 23
- [Managing objects in a project \(solution\)](#) on page 29
- [Node editor view](#) on page 35
- [Managing compilation errors and warnings \(task window\)](#) on page 60
- [Displaying the change history \(command list\)](#) on page 54
- [Bookmarks](#) on page 55
- [Navigation](#) on page 21
- [Opening the compiling log](#) on page 61

Toolbar

The toolbar contains different icons that you can click to access other functions.

Table 2: Toolbar functions

Icon	Description
Change Label:	In the list, select the label under which changes made to the One Identity Manager database are to be saved. Use the label to make it easier to identify and assign changes to the database. For more information, see Labeling changes on page 37.
 Managing change labels	Opens the Change label dialog. You can select, add, change, or delete change labels here. For more information, see Labeling changes on page

Icon	Description
	37.
 Use the current change label as default	Specify that the current change label (see Change label) is to be used as the default change label. This change label will automatically be selected upon API Designer startup. This setting is bound to the client and does not affect other users of the One Identity Manager database. For more information, see Using change labels on page 38 .
 Captions	Opens the Multilingual captions dialog. Here you can create and edit multilingual captions. For more information, see Multilingual captions on page 44 .
 Testing a compilation	Tests the compilation for either the Debug or Release version. For more information, see Testing a compilation on page 58 .
 Save	Saves changes to the object currently being edited. If you want to save changes to other database objects, select the corresponding tab in the definition tree view and click the button.
 Save all	Saves changes to all objects currently being edited.
 Previous/next node	<p>Navigates backwards and forwards within the history of the selected objects. This displays the selected database object in the definition tree view.</p> <p>If an object or node has been deleted, the next object is shown. If an object that no longer exists is selected in the history, the previous object is shown.</p> <p>TIP: On the menu bar under Connection Settings, you can specify the number of database objects shown in the history. The history can be deleted in the context menu using Clear history.</p>

Related topics

- [User interface](#) on page [15](#)
- [Labeling changes](#) on page [37](#)
- [Multilingual captions](#) on page [44](#)
- [Testing a compilation](#) on page [58](#)







Status bar

The status bar displays different status data. Some status data is shown by way of icons. Which icons are displayed is partially dependent on the program settings selected. The status bar comes in different colors.

Table 3: Meaning of the colors

Color	Meaning
none	Development environment database is connected.
Red	Simulation mode is enabled.
Green	Test environment database is connected.
Yellow	Productive environment database is connected.

Table 4: Status bar icons

Icon	Meaning
	Shows the current user.
	Shows information about the project.
	The database is connected.
	Shows database access.
	The database must be compiled.
	The program is in simulation mode.

On the status bar, the database is also shown in the following format:

<Server>/<Database (description)>

TIP: To copy the database path into the clipboard, double-click the database name in the status bar.

To see more information about the current user, double-click the user name in the status bar.

Related topics

- [User interface](#) on page 15

Navigation





Open the navigation using **View | Navigation** (see [Opening the navigation](#) on page 22).

Use the navigation to manage (create, open, delete) API files and API projects. You can also access the most recently edited file here.

At the bottom of the navigation view, you can select whether you would like to manage API files or API projects.

The following table provides an overview of the various features available within the navigation.

Table 5: Navigation features

Control	Description
 Add	Adds a new database object. The type of database object changes according to the pane you are in (API files or API projects). For detailed information, see the following sections: <ul style="list-style-type: none">• Creating API projects on page 68• Creating API files on page 77
 Delete	Deletes a database object. For detailed information, see the following sections: <ul style="list-style-type: none">• Deleting API projects on page 70• Deleting API files on page 78
 Reload data	Refreshes the view/reloads the data.
 Properties	Opens the Object properties dialog. Allows you to view the properties for the selected database object. For more information, see Object properties on page 27.
Searching	Uses the search feature to find specific database objects. Enter the required search term and then press Enter.

Related topics

- [User interface](#) on page 15
- [Creating API projects](#) on page 68
- [Creating API files](#) on page 77
- [Deleting API projects](#) on page 70
- [Deleting API files](#) on page 78
- [Object properties](#) on page 27

Opening the navigation

By default, the navigation remains open (on the left side of the window) until you close it. You can open the navigation again at any time.

To open the navigation

- On the menu bar, click **View | Navigation**.

Related topics

- [Navigation](#) on page 21
- [User interface](#) on page 15

Start page

Open the start page from **View | Start page** (see [Opening the start page](#) on page 23).

The start page is displayed when the API Designer starts up.

On the start page, you can:

- Use [compilation branches](#) to store different versions of your API in the database.
- [Test](#) your API locally
- [Compile the API](#) and then write it to the database
- Use the API Designer to [connect and edit](#) C# projects

Related topics

- [Managing versions \(compilation branches\)](#) on page 62
- [Testing an API](#) on page 64
- [Compiling an API](#) on page 57
- [Linking C# projects to the API Designer](#) on page 65
- [Opening the start page](#) on page 23
- [User interface](#) on page 15

Opening the start page

You can open the start page again at any time.

To open the start page

- Click **View | Start page** on the menu bar.
The start page opens in the work pane.

Global settings

Open the global settings from **Connection | Settings** (see [Changing global settings](#) on page 26).

Use the **Global settings** dialog to configure basic settings for API Designer. The following table gives an overview of the various features within the **Global settings** dialog.

Table 6: Global settings

Pane	Setting	Description
Common		
	Language	
	Current	Displays the language currently in use for formatting data such as date, time, or numbers.
	After next restart	Specify which language the API Designer will use for formatting data such as date, time, or numbers. The next time the API Designer starts up, the API Designer will use this language. For more information, see Switching languages on page 26.
	Use another language for the UI	Specify whether you want to use a different language for the API Designer's user interface than the one configured for formatting values. Use the After next restart option to specify the language for the user interface. For example, you can continue using English for formatting data but have German as the display language.
	UI language	
	Current	Shows the language currently in use.
	After next restart	Specifies the language for the API Designer. The next time the API Designer starts up, the API Designer will use this language. For more information, see Switching languages on page 26.
	Resolution	Specifies the resolution.
	Maximum history length	Specifies how many changes can be undone.
Editor		
	Shorten long property values	If you would like to shorten long property values, enable this option.
	Show an error message if syntax errors are found after editing	Enable this option if you want to receive a notification when syntax errors have been found after editing.
	Save and load API Designer size within	If you would like to save the size settings for the API Designer view and reload them upon restarting, enable this option.

Pane	Setting	Description
	layout	
	Ask for project type at each start	Enable this option if you would like to select how you would like to save your project each time you start API Designer (see Changing the project type on page 12).
	Compilation branch identifier	<p>Use compilation branches to store different API versions in the database.</p> <p>Manage your compilation branches. You can select the compilation branch that you want to use, display the existing compilation branches, create compilation branches, edit compilation branches, and delete compilation branches.</p> <p>For more information, see Managing versions (compilation branches) on page 62.</p>

Compiler

	Show following warnings as errors	<p>Specify which warnings are displayed as errors during compilation. Enter the codes for the warnings, separated by commas. The error codes refer to the Microsoft C# compiler. For more information about compilation, see Compiling an API on page 57.</p> <p>TIP: For information about error codes that occur during compilation, you can refer, for example, to the Error code table in the Tasks view (see Managing compilation errors and warnings (task window) on page 60).</p>
	Ignore following warnings	<p>Specify which errors should be ignored during compilation. Enter the codes for the warnings, separated by commas. The error codes refer to the Microsoft C#Sharp compiler. For more information about compilation, see Compiling an API on page 57.</p> <p>TIP: For information about error codes that occur during compilation, you can refer, for example, to the Error code table in the Tasks view (see Managing compilation errors and warnings (task window) on page 60).</p>

Save and backup

	Ask for change label if none is selected	Enable this option if you would like to be asked for a change label when saving.
	Keep backup of unsaved objects on the local machine	If you would like to back up unsaved changes on your local hard drive, enable this option. This ensures that your changes are not lost if the program crashes.

Keyboard layout

Pane	Setting	Description
	Show next bookmark	Specify the shortcut to be used for the next bookmark. TIP: To specify a Ctrl or Shift shortcut, enable the Alt and/or Ctrl options. Finally, select a button from the list.
	Set/delete bookmarks	Specify the shortcut you want to use to set or remove a bookmark. TIP: To specify a Ctrl or Shift shortcut, enable the Alt and/or Ctrl options. Finally, select a button from the list.

Related topics

- [Changing global settings](#) on page 26
- [Menu bar](#) on page 16

Changing global settings

You can change the global settings, general settings, or both for the API Designer at any time.

To adjust API Designer settings

1. On the menu bar, click **Connection | Settings**.
2. In the **Global settings** dialog, click a pane to collapse or expand it.
3. Configure the required settings (see [Global settings](#) on page 23).
4. Click **Apply**.

Related topics

- [Global settings](#) on page 23

Switching languages

The API Designer is available in German and English. You can switch between these languages at any time. Changing the language requires the API Designer to be restarted.

To change the API Designer language

1. On the menu bar, select **Connection | Settings**.
2. In the **Global settings** dialog, in the **Common | Common culture** section, select the desired language (for formatting and user interface) in the **After next restart**

menu.

3. (Optional) If you want to use another language for formatting values in the user interface, set the **Use another language for the UI** option and select the desired language in the **After next restart** menu.

For example, if you want dates to be displayed in the German format (TT.MM.JJJJ) and the rest of the user interface in English, select **German (Germany)** in step 2 and **English (United States)** in step 3.

4. Click **Apply**.
5. Confirm the prompt by selecting **Yes** in the **Restart API Designer dialog**. The API Designer will restart in the selected language.

Related topics

- [Global settings](#) on page 23

Database objects

API projects, and API files are defined as database objects in API Designer. Here you can learn how to work with these database objects in API Designer.

Related topics

- [Editing database objects \(definition tree view\)](#) on page 30
- [Managing objects in a project \(solution\)](#) on page 29
- [Object properties](#) on page 27

Object properties

Right-click on an object to open the **Object properties** dialog (see [Displaying object properties](#) on page 28)

The **Object properties** dialog displays the properties of objects in the API Designer. The dialog is divided into five tabs, which are explained below.

General

Under the **General** tab, the general properties of the object such as ID, status, or primary key are displayed.

Properties

Under the **Properties** tab, all columns in the database object are displayed in a table alongside their values. You can choose between a simple column view or the advanced view with additional data for column definitions.

Permissions

On the **Permissions** tab, the database object permissions are displayed. The first entry shows the basic permissions for the table. Under that, the permissions are listed for the specific database object. The other entries show the column permissions.

TIP: Double-click the table entry, the object entry, or a column entry to display the permissions group from which the permissions were determined.

Table 7: Icon used for permissions

Icon	Meaning
✓	Permissions exist.
•	Permissions have been removed by the object layer.
☑	Permissions limited by conditions.

Label

Under the **Change labels** tab, all the [change labels](#) assigned to the database object are displayed. You can also assign a change label to the object.

Export

Under the **Export** tab, you can export the database object:

- To the clipboard
- As a file
- Using drag-and-drop
- As a SQL INSERT statement or SQL UPDATE statement


Related topics

- [Displaying object properties](#) on page 28

Displaying object properties

You can display the properties of a database object at any time.

To display the properties of a database object

1. On the menu bar, click **View | Navigation**.
2. In the navigation, click the database object whose properties you would like to display.
3. Click **Properties** .

The **Object properties** dialog opens. This dialog contains several tabs displaying the properties of the selected database object. For more information, see [Object properties](#) on page 27.

Related topics

- [Object properties](#) on page 27

Managing objects in a project (solution)

Open the **Solution** view using **View | Solution** (see [Opening the solution](#) on page 30).

The solution can be used to display all the objects in the API Designer that can be opened from the navigation menu.

The solution view depends on your choice of project. If you select a [solution](#) project when starting the API Designer, the listed entries will be grouped according to their respective database modules and you will be able to disable the compilation of individual database modules. Database modules whose status has not changed, are shown as collapsed nodes. If you mark a subnode, you can run additional tasks.

You can also identify the objects whose status has changed in API Designer. Differences between changes in the API Designer and changes to resources in the database or on the hard disk are marked.

To open an object, double-click it in the solution.

The following table provides an overview of the various features available in the **Solution** window.

Table 8: Controls







Control	Description
 Update list	Refreshes the list of database objects.
 Reload selected objects	Reloads the selected objects.
 Mark all modified objects to be reloaded	Any objects that you have modified will be reloaded after you click  Reload selected objects .
 Disable module compilation	Disables compilation of the selected module.
 Only display modified objects	Only modified objects will be displayed in the list.

Table 9: Solution columns

Column	Description
Object identifier	Name of the object
DB status	Up to date is displayed when the database has been refreshed. Otherwise, the user who made the change is displayed.
Status drive	Up to date is displayed when the file has been updated. Otherwise, a time when the changes will be made is shown.
Status API Designer	Displays object modifications. The status is shown as Changed if the object has been changed.
Reload	A check box is displayed for new objects. You can reload selected objects.
Path	Shows storage location of the file on the hard drive.

Related topics

- [Opening the solution](#) on page 30
- [Menu bar](#) on page 16

Opening the solution

You can open the solution at any time.

To open the solution

- Click **View** | **Solution** on the menu bar.

Related topics

- [Managing objects in a project \(solution\)](#) on page 29

Editing database objects (definition tree view)

Open the definition tree view over **View** | **Navigation** | **Click the required database object** (see [Opening the definition tree view](#) on page 31).

Use the definition tree view to display and edit different database objects in API Designer. A separate tab containing a unique definition tree view will be opened for each database object that you edit. A definition tree view opens when adding or editing database objects, for example.




A database object contains what are known as nodes, which you can display in a tree structure within the definition tree view and edit in the node editor view (see [Node editor view](#) on page 35). If you add a new database object to your project (for example, an API project), this database object is created with a predefined number of nodes and is shown in the object definition. The object definition is a type of view found within the definition tree view.

The predefined nodes contained in a database object form the basic structure of the database object. You cannot delete these nodes.

In addition to the predefined nodes, you can add extra nodes by right-clicking on the context menu. You can delete these nodes.

The following table gives an overview of the various features contained on the toolbar within the definition tree view.

Table 10: Definition tree view toolbar

Icon	Description
 Object definition	An overview of nodes contained in a database object can be found here.
 Generated code	You can view the code generated for a selected node here. For more information, see Viewing and saving generated code belonging to a node on page 34.
 Find and replace	You can search for terms here and replace them where necessary. For more information, see Find and replace on page 40.

Related topics

- [Opening the definition tree view](#) on page 31
- [Viewing and saving generated code belonging to a node](#) on page 34
- [Find and replace](#) on page 40

Opening the definition tree view

You can open the definition tree view at any time.

To open the definition tree view of a database object

1. On the menu bar, click **View | Navigation**.
2. In the navigation, double-click on the database object which holds the definitions you would like to display.

The definition tree view for the selected object opens in a separate tab.

Related topics

- [Editing database objects \(definition tree view\)](#) on page 30
- [Navigation](#) on page 21

Context menu in the definition tree window





To access the context menu, right-click a node in the [definition tree window](#). The options available in the menu depend on the type of node selected (context-sensitive).











Structure

The top section of the context menu lists the node types that can be added to the selected node.

Some node types do not allow additional node types to be pasted into them. In such cases, the **Object in extension** function is at the top of the context menu. All other functions are either available or grayed out, depending on the type of node and its position in the definition tree window.

Table 11: Functions in the context menu

Function	Description
Object in extension	Allows you to create sub-elements of the selected node in an extension instead of an object.
Move to extension	Moves the selected node into a new or existing extension.
 Cut	Cuts the highlighted node and copies it to the clipboard. Any child nodes for the selected node are also cut. NOTE: You cannot cut any nodes that have been automatically added to the definition tree.
 Copy	Copies the highlighted and child nodes to the clipboard.
 Paste	Pastes the node contained in the clipboard. NOTE: You can only paste nodes contained in the clipboard if they are also permitted at the selected point. Example: You cannot paste a Plugin node below the Compilation settings node.
 Delete	Deletes the highlighted node and all child nodes. NOTE: You cannot delete any nodes that have been automatically added to the definition tree. TIP: You can select multiple nodes by holding down the Ctrl key to apply the function once to all selected nodes.

Function	Description
Delete node as an extension	Deletes the highlighted node as an extension.
 Set/remove bookmark	Sets or removes a bookmark on the highlighted node. For more information, see Bookmarks on page 55.
Expand all	Expands all nodes.
Collapse all	Collapses all nodes.
 Export	Saves the selected node and their child nodes in XML format to your hard drive.
 Import	Pastes previously exported child nodes at the selected point. NOTE: You can only paste nodes if they are also permitted at the selected point. Example: You cannot paste a Plugin node below the Compilation settings node.
 Move up	Moves the selected node upwards. NOTE: You cannot move any nodes that have been automatically added to the definition tree.
 Move down	Moves the selected node downwards. NOTE: You cannot move any nodes that have been automatically added to the definition tree.
 Undo	Undoes the previous action.
 Redo	Redoes the last action that has been undone.
 Search object references	Searches for all references that refer to the selected node. NOTE: If searching for a reference within a collection, the results are grouped by related columns.
 Search	Opens the Find and replace dialog. For more information, see Find and replace on page 40.
 Search next	This function continues the search using the current search parameters and highlights the next matching node. The search is executed even if the Search dialog is not open.

Related topics

- [Editing database objects \(definition tree view\)](#) on page 30
- [Bookmarks](#) on page 55
- [Find and replace](#) on page 40


Extensions

Use extension to indirectly edit base objects (standard database objects that are contained in your project). You can add as many extensions as you wish to the base objects in the API Designer.

Extensions are edited when you configure the base objects. This means you add an extension to the object and change the property value. The base object is subsequently compiled and the modification resulting from the extension is highlighted in the API Designer.

Base objects to which you want to add an extension can be identified as colored nodes in the **Object definitions** view in the [Definition tree view](#).

Figure 1: Workflow in the API Designer



Viewing and saving generated code belonging to a node

In the [Definition tree view](#), you can view a node's generated code (within a database object) and copy or save where necessary.

This function is particularly useful if you are looking at code in detail and want to reuse parts of the code, or you want to examine an error in more detail.

NOTE: You cannot edit the code.

NOTE: If you want to search for a specific point in the code, you can use the shortcut **Ctrl + F**.

To view a node's generated code

1. On the menu bar, click **View | Navigation**.
2. In the navigation, double-click the database object that contains the node you require.
3. Click the node in the definition tree view whose code you want to see.

4. Click  .

The code will be displayed in a code view.

To save the generated code as a file

1. Execute the [steps previously described](#).
2. In the code view, select the code that you want to save.
3. Right-click the highlighted code.
4. Click **Copy**.
5. Click **Save as** in the context menu.
6. Select a name and location for the file in the save dialog and click **Save**.

Related topics

- [Editing database objects \(definition tree view\)](#) on page 30
- [Resolving errors and warnings](#) on page 61

Node editor view





Open the node editor view using **View | Node editor** (see [Opening the node editor view](#) on page 36).








The **Node editor** view allows you to edit the properties of a node that you have selected in the [Definition tree view](#) (see [Editing nodes](#) on page 37).

| **NOTE:** The settings shown depend on the type of node selected.

The following table provides an overview of the various features available within the **Node editor** window.

Table 12: Controls

Control	Description
 and name / icon of the base object	Displays if a file-based database object (Solution project) has been selected. Click  Open corresponding folder to open the folder on your drive where the database object is located. For more information, see Solution projects on page 13.
Node name/node type icon	Shows the node identifier and the node type icon that marks it in the definition tree view.
 Database	Displays if a database object is selected.
 Delete	Deletes the filter entered into the next field.

Control	Description
filter	
Filter field	<p>Displays only fields that match the text that has been entered.</p> <p>Example: If you enter Pe, only the Permission field will be displayed.</p> <p>NOTE: The API Designer only filters the settings fields and not the values contained within them.</p>
 Sort ascending alphabetically	<p>Sorts the settings alphabetically in ascending order within each category.</p> <p>If you enable sorting, the button will be highlighted with a colored frame.</p>
 Sort descending alphabetically	<p>Sorts the settings alphabetically in descending order within each category.</p> <p>If you enable sorting, the button will be highlighted with a colored frame.</p>
 View grouping	<p>Enables/disables the display of the various settings in categories.</p> <p>If you enable this option, the button will be highlighted with a colored frame.</p>
 Expand all	Expands all categories.
 Collapse all	Collapses all categories.
Show extension values	<p>Highlights settings that have had an extension added to them. Use  to switch to the extension. A node that has had an extension added to it, is indicated in the definition tree view with the  icon.</p> <p>If you enable this option, the button will be highlighted with a colored frame.</p>

Related topics

- [Opening the node editor view](#) on page 36
- [Editing nodes](#) on page 37
- [Menu bar](#) on page 16
- [Editing database objects \(definition tree view\)](#) on page 30

Opening the node editor view

You can open the node editor view at any time.

To open the node editor view

- Click **View | Node editor** on the menu bar.


Related topics

- [Editing nodes](#) on page 37
- [Node editor view](#) on page 35

Editing nodes

Node properties can be edited for any node in the node editor view.

To edit a node

1. On the menu bar, click **View | Navigation**.
2. In the navigation, double-click the object that you would like to edit.
3. Click **View | Node editor** on the menu bar.
The [Node editor view](#) opens.
4. In the [Definition tree view](#), click the node that you would like to edit.
The fields and options shown in the node editor view will change depending on the selected node.
5. Make the changes in the **Node editor** view.
6. On the toolbar, click  **Save**.

Related topics

- [Opening the node editor view](#) on page 36
- [Node editor view](#) on page 35
- [Editing database objects \(definition tree view\)](#) on page 30
- [Menu bar](#) on page 16
- [Navigation](#) on page 21

Labeling changes

Use **Change label** to make it easier to view and assign changes in the database. Any database objects that yield a project are entered on a change label. Database Transporter is used for moving the web project. You can create and edit change labels in different One Identity Manager tools.

Related topics

- [Using change labels](#) on page 38
- [Creating a change label](#) on page 38

- [Change management](#) on page 39
- [Deleting change labels](#) on page 40

Using change labels

In order to also be able to assign a change label to changes, you need to select a change label for further use.

To use a change label

- On the toolbar, select the required change label in the **Change label** list.
Any changes stored in the project during this session will be assigned to the selected change label.

TIP: If you always use the same change label and do not want to select it every time you start the API Designer, click  **Use the current change label as default** in the toolbar.



Related topics


- [Labeling changes](#) on page 37
- [Creating a change label](#) on page 38
- [Change management](#) on page 39
- [Deleting change labels](#) on page 40

Creating a change label

You can create as many change labels as you wish and use them to track your changes.

To edit a change label

1. In the toolbar, click  **Manage change label**.
2. Click **Create a new change label**  in the **Change label** dialog.
3. Specify the properties of the change label in the right-hand column in the list:
 - **Change label:** Enter a name for the change label.
 - **Description:** (Optional) Enter a description for the change label.
 - **Locked:** (Optional) Select whether you would like to block the change label from further use. If a change label is locked, no further changes can be booked to this label.
 - **Comment:** (Optional) Enter a comment to monitor changes to the change label.

- **Status:** (Optional) Select a status from the list.
 - **Status comments:** (Optional) Enter a comment in relation to the status.
 - **Parent change label:** (Optional) Select a change label from the list to be the parent.
4. Click  **Save change label** above the list.
 5. Click **OK**.




Related topics

- [Labeling changes](#) on page 37
- [Using change labels](#) on page 38
- [Change management](#) on page 39
- [Deleting change labels](#) on page 40

Change management

You can edit existing change labels at any time.

To edit a change label

1. In the toolbar, click  **Manage change label**.
2. In the **Change label** dialog, click the label to be edited.
3. Click  **Show / hide edit** view.
4. Change the properties of the change label in the right-hand column in the list:
 - **Change label:** Enter a name for the change label.
 - **Description:** (Optional) Enter a description for the change label.
 - **Locked:** (Optional) Select whether you would like to block the change label from further use. If a change label is locked, no further changes can be booked to this label.
 - **Comment:** (Optional) Enter a comment to monitor changes to the change label.
 - **Status:** (Optional) Select a status from the list.
 - **Status comments:** (Optional) Enter a comment in relation to the status.
 - **Parent change label:** (Optional) Select a change label from the list to be the parent.
5. Click  **Save change label** above the list.
6. Click **OK**.



Related topics

- [Labeling changes](#) on page 37
- [Using change labels](#) on page 38
- [Creating a change label](#) on page 38
- [Deleting change labels](#) on page 40

Deleting change labels

You can delete existing change labels at any time.

To edit a change label

1. In the toolbar, click  **Manage change label**.
2. In the **Change label** dialog, click the change label you would like to delete.
3. Click  **Delete the selected change label**.
4. Confirm the prompt by selecting **Yes** in the dialog.
5. Click **Cancel**.

Related topics


- [Labeling changes](#) on page 37
- [Using change labels](#) on page 38
- [Creating a change label](#) on page 38
- [Change management](#) on page 39

Find and replace

Open the search function over **Edit | Find and replace** (see [Running a search](#) on page 43).

Use the **Find and replace** dialog to search for (and replace) certain captions or items within your project. The following table gives an overview of the various features within the **Find and replace** dialog.

Table 13: Controls for find and replace

Control	Description
Find	Enter the term to be found.  TIP: To reuse terms from previous searches, click the arrow to the

Control	Description
	right of the field and select the required term.
Find as	Select whether you would like to search using simple text or by wildcards or regular expressions .
Replace by	(Optional) Enter the text that will replace the text found.
Find scope	<p>If you would like to further narrow the search, you can select which objects you would like to search for here:</p> <ul style="list-style-type: none"> • Current document: Only the current document is included in the search. • Current document and its extensions: Only the current document and all of its extensions are included in the search. • Current document and its parent documents: Only the current document and all of its parent items are included in the search. • Below the selected object: Only the objects below the current object are included in the search. • All API Designer objects: All objects are included in the search.
Find options	<p>Configure other search settings:</p> <ul style="list-style-type: none"> • Case sensitive: API Designer finds only occurrences of the text that match the case that you have entered into the Find field. • Whole word: Only the whole word is included in the search. Example: If you enter Person, the search will only find "person" and not "persons." • Match entire value: API Designer finds only objects containing the exact values that match the text you have entered into the Find field. • Filter by type: Select the objects to which your search will be limited.
Find	Finds and opens the next occurrence of the term.
Find all	Triggers a search that lists all occurrences of the text in the Find results pane.
Find results	Lists all occurrences of the term.
Replace	Replaces the occurrence of the term that you have highlighted in Find results with the text that you have entered in the Replace by field.
Replace all	Replaces all occurrences of the term that you have selected in the Replace column under Find results with the text that you have entered in the Replace by field.

Wildcards

Use wildcards to replace a single character, or a string of characters, using a single character when searching for strings. The most common wildcards are the question mark (?), to symbolize an individual character, and the asterisk (*), to symbolize any combination of characters.

To use wildcards in the **Find and replace** dialog, enter the search term into the **Find** field and select the **Wildcards** option from the **Find as** list.

Examples

The following table gives some examples of wildcard searches:

Sample term	Result
P*n	Finds "person," "position," "plugin," and so on.
Per*	Finds "person," "personal," "perfection," and so on.
AP?.json	Finds "API.json" but not "APIProject.json."

Regular expressions

Regular expressions (also known as "regex" or "regexp") are similar to [wildcards](#) in that they also allow you to find strings. Regular expressions are more effective than wildcards, however.

To use regular expressions in the **Find and replace** dialog, enter the search term into the **Find** field and select the **Regular expressions** option from the **Find as** list.

Examples

The following table gives some examples of regular expressions:

Regular expression	Description
[a-z]	Any lowercase Latin letter
[A-Z]	Any uppercase Latin letter
\d	A digit
\D	A character that is not a digit
\w	A letter, a digit, or an underscore

Regular expression	Description
\W	A character that is neither a letter, a number, nor an underscore
\s	Blank space
\S	A character that is not a blank space
{n}	The preceding term must occur exactly "n" number of times. Example: C{3} finds "CCC"
 	Alternatives Example: Regex Regexp finds "Regex" or "Regexp"
?	The preceding term is optional, it can occur once, but does not need to, that is, the term either occurs once or not at all.



Related topics

- [Running a search](#) on page 43
- [Menu bar](#) on page 16

Running a search

You can perform a search of the whole project, or parts of it, at any time.

To run a search

1. Click **Edit | Find and replace** on the menu bar.
2. In the **Find and replace** dialog, enter a search term in the **Find** field.
3. In the **Find as** list, select whether you would like to search using simple text or by [wildcards](#) or [regular expressions](#).
4. (Optional) In the **Replace by** field, enter the text to replace the text in the search.
5. In the **Find scope** list, select which objects you would like to include in the search.
6. (Optional) In the **Find options** pane, click  **Expand** to configure further search settings.
7. Click **Find** or **Find all**.
The search results are displayed in the **Find results** pane
8. In the **Find options** pane, click  **Expand** to configure further search settings.
9. (Optional) Double-click a result in the results list.

This marks and displays the corresponding nodes in the definition tree view.

10. (Optional) To replace a result, highlight it in the **Find results** pane and click **Replace**.
11. (Optional) To replace several results, enable the checkbox next to the relevant results and click **Replace all**.

Related topics

- [Find and replace](#) on page 40

Multilingual captions




Open the **Multilingual captions** dialog using  **Captions**.

Use the **Multilingual captions** dialog to add, edit, or delete captions in multiple languages. You can use this text later in your API or web application.

Before adding or editing multilingual captions, define objects in your project that output captions in your API. You create keys for these objects. You assign a text to the keys for each language. This means that the keys are translated into the different languages you wish to use.

You can create and edit keys and translations on the **Captions** tab in the **Multilingual captions** dialog. The following table gives an overview of the various features within the **Multilingual captions** dialog.

Table 14: Controls

Control	Description
 Add	Creates a new caption. For more information, see Creating multilingual captions on page 45.
 Delete	Deletes the caption selected in the results list. For more information, see Deleting a multilingual caption on page 47.
 Save	Saves the changes. For more information, see Editing a multilingual caption on page 46.
Search mask	In this pane, you can search for existing captions and edit them. For more information, see Searching for a multilingual caption on page 45.
Result list	Lists the results generated by the search. For more information, see Searching for a multilingual caption on page 45.
Handling	You can edit captions in this pane. For more information, see Creating multilingual captions and Editing a multilingual caption on page 46.




Related topics

- [Creating multilingual captions on page 45](#)
- [Searching for a multilingual caption on page 45](#)
- [Editing a multilingual caption on page 46](#)
- [Deleting a multilingual caption on page 47](#)
- [Menu bar on page 16](#)

Creating multilingual captions

You can create multilingual captions at any time.

To create a multilingual caption

1. Click  **Captions** on the menu bar.
2. Click  **Add** on the toolbar in the **Multilingual captions** dialog.
3. In the **Edit** pane, enter a unique value in the **Key** field to be used to reference the text.
NOTE: If you have not added a translation for a language, the API will use the caption that has been saved under **Key**.
4. Select the caption's language in the **Language** list.
5. Enter the caption to be shown for the selected language in the **Text** field.
6. Repeat the previous two steps for all the required languages.
7. Click  **Save** on the toolbar in the **Multilingual captions** dialog.
8. Click **Apply**.



Related topics

- [Multilingual captions on page 44](#)
- [Searching for a multilingual caption on page 45](#)
- [Editing a multilingual caption on page 46](#)
- [Deleting a multilingual caption on page 47](#)

Searching for a multilingual caption

You can search for multilingual captions at any time.

To search for a multilingual caption

1. Click  **Captions** on the menu bar.
2. In the **Multilingual captions** dialog, enter a term into the **Search form** (such as the name of a key or parts of the caption).
3. Use the options below the search bar to limit your search:
 - **Search key and value:** Searches for the term in the key and captions.
 - **Search for key only:** Only searches for the term in the key.
 - **Search for value only:** Only searches for the term in the captions.
 - **Search in all available languages:** Enable this option if you would like to search for the term across all languages. If you disable this option, the search will only be performed in the language that is current shown in the **Language** field in the **Edit** pane.
4. Click  **Search**.

The search results are displayed in the **Result list** pane

TIP: If one of the **Search key and value** or **Search for key only** options is set, the keys shown in the result list are labeled with an asterisk (*).


Related topics

- [Multilingual captions](#) on page 44
- [Creating multilingual captions](#) on page 45
- [Editing a multilingual caption](#) on page 46
- [Deleting a multilingual caption](#) on page 47



Editing a multilingual caption

You can edit existing multilingual captions at any time.

To edit a multilingual caption

1. Click  **Captions** on the menu bar.
2. In the **Multilingual captions** dialog, enter the search term in the **Search form** section.
3. Use the options below the search bar to limit your search:
 - **Search key and value:** Searches for the term in the key and captions.
 - **Search for key only:** Only searches for the term in the key.
 - **Search for value only:** Only searches for the term in the captions.
 - **Search in all available languages:** Enable this option if you would like to

search for the term across all languages. If you disable this option, the search will only be performed in the language that is current shown in the **Language** field in the **Edit** section.

4. Click  **Search**.
5. In the **Result list** section, click the caption to be edited.
TIP: If one of the **Search key and value** or **Search for key only** options is set, the keys shown in the result list are labeled with an asterisk (*).
6. In the **Edit** section, change the unique value in the **Key** field that is used to reference the text.
NOTE: If you have not added a translation for a language, the API will use the caption that has been saved under **Key**.
7. Select the caption's language in the **Language** list.
8. Enter the caption to be shown for the selected language in the **Text** field.
9. Repeat the last two steps for any languages that you would like to change or add.
10. Click  **Save** on the toolbar in the **Multilingual captions** dialog.
11. Click **Apply**.

Related topics


- [Multilingual captions](#) on page 44
- [Creating multilingual captions](#) on page 45
- [Searching for a multilingual caption](#) on page 45
- [Deleting a multilingual caption](#) on page 47


Deleting a multilingual caption


You can delete existing multilingual captions at any time.

NOTE: You cannot delete multilingual captions that have been predefined by API Designer.

To delete a multilingual caption

1. Click  **Captions** on the menu bar.
2. In the **Multilingual captions** dialog, enter a term into the **Search parameters** (such as the name of a key or parts of the caption).
3. Use the options below the search bar to limit your search:
 - **Search key and value:** Searches for the term in the key and captions.
 - **Search for key only:** Only searches for the term in the key.
 - **Search for value only:** Only searches for the term in the captions.

- **Search in all available languages:** Enable this option if you would like to search for the term across all languages. If you disable this option, the search will only be performed in the language that is current shown in the **Language** field in the **Edit** section.
4. Click .
 5. In the **Result list** section, click the caption to be deleted.

TIP: If one of the **Search key and value** or **Search for key only** options is set, the keys shown in the result list are labeled with an asterisk (*).
 6. Click  **Delete** on the toolbar in the **Multilingual captions** dialog.
 7. Confirm the prompt by selecting **Yes** in the dialog.
 8. Click **Apply**.

Related topics

- [Multilingual captions](#) on page 44
- [Creating multilingual captions](#) on page 45
- [Editing a multilingual caption](#) on page 46
- [Searching for a multilingual caption](#) on page 45

Managing database queries



Open the **Edit database queries** dialog over **Edit | Edit database queries** (see [Displaying database queries](#) on page 49).






In the **Edit database queries** dialog, you can [display](#), [create](#), [edit](#), [delete](#), and [test](#) database queries.

Database queries enable secure communication between your web application and your One Identity Manager database. The actual SQL code is saved in SQL snippets, to which only certain parameters can be added later. The database queries are referenced later in the code only based on their name.

The following table gives an overview of the various features within the **Edit database queries** dialog.

Table 15: Controls

Control	Description
 Add	Creates a new database query. For more information, see Creating a database query on page 50.
 Delete	Deletes the selected database query. For more information, see Deleting a database query on page 52.

Control	Description
 Save	Saves changes to the selected database query. For more information, see Editing a database query on page 50.
 Save all	Saves all changes. For more information, see Editing a database query on page 50.
 Discard object changes	Undoes all changes to the selected database query.
Identifier	Is a unique database query ID.
Description	Gives a description of the database query that explains the query and its function.
SQL expression	Is the actual query in SQL code.
Dialog groups	Are dialog groups that are permitted to use this database query (labeled ) or forbidden from using it (labeled )
Test statement	Opens the Test statement dialog. You can test the database query here. For more information, see Testing a database query on page 51.

Related topics

- [Displaying database queries](#) on page 49
- [Creating a database query](#) on page 50
- [Editing a database query](#) on page 50
- [Testing a database query](#) on page 51
- [Deleting a database query](#) on page 52

Displaying database queries

You can edit all existing database queries at any time.

To show all database queries

- Click **Edit | Edit database queries** on the menu bar.

Related topics



- [Managing database queries](#) on page 48
- [Editing a database query](#) on page 50

- [Testing a database query](#) on page 51
- [Deleting a database query](#) on page 52

Creating a database query

You can create new database queries at any time.

To create a database query

1. Click **Edit | Edit database queries** on the menu bar.
2. Click  **Add** in the **Edit database queries** dialog.
3. Enter a unique name for the database query in the **Identifier** field.
4. (Optional) In the **Description** field, enter a description for the database query that describes the database query and its function.
5. Enter the query as a SQL code in the **SQL expression** field.
6. Double-click the dialog groups that may use the database query in the **Dialog groups** pane.
TIP: Click **Select all** or **Deselect all** to quickly select or deselect all dialog groups.
7. (Optional) Click **Test statement** to test the SQL statement with different values. For more information, see [Testing a database query](#) on page 51.
8. Click  **Save**.
9. Click **Close**.

Related topics


- [Managing database queries](#) on page 48
- [Displaying database queries](#) on page 49
- [Editing a database query](#) on page 50
- [Testing a database query](#) on page 51
- [Deleting a database query](#) on page 52

Editing a database query

NOTE: You cannot edit any database queries that have been predefined by the API Designer.

You can edit existing database queries at any time.

To edit a database query

1. Click **Edit | Edit database queries** on the menu bar.
2. Click the database query you would like to edit in the **Edit database queries** dialog.
3. Enter a unique name for the database query in the **Identifier** field.
4. (Optional) In the **Description** field, enter a description for the database query that describes the database query and its function.
5. Enter the query as a SQL code in the **SQL expression** field.
6. In the **Dialog groups** section, double-click the dialog groups for which access permissions are to be changed.
TIP: Click **Select all** or **Deselect all** to quickly select or deselect all dialog groups.
7. (Optional) Click **Test statement** to test the SQL statement with different values. For more information, see [Testing a database query](#) on page 51.
8. Click  **Save**.
9. Click **Close**.

Related topics

- [Managing database queries](#) on page 48
- [Displaying database queries](#) on page 49
- [Creating a database query](#) on page 50
- [Testing a database query](#) on page 51
- [Deleting a database query](#) on page 52

Testing a database query

You can test database queries at any time.

To test a database query

1. Click **Edit | Edit database queries** on the menu bar.
2. In the **Edit database queries** dialog, click the database query you would like to test.
3. Click **Test statement**.
4. In the **Test statement** dialog, enable the check box next to the SQL statement parameters that you would like to include in the test.
5. Enter the values for each parameter in the **Value** column.
6. Click **Test statement**.

7. Click **Close**.
8. Click **Close** in the **Edit database queries** dialog.

Related topics


- [Managing database queries](#) on page 48
- [Displaying database queries](#) on page 49
- [Creating a database query](#) on page 50
- [Editing a database query](#) on page 50
- [Deleting a database query](#) on page 52

Deleting a database query

NOTE: You cannot delete any database queries that have been predefined by the API Designer. The **Delete** button is disabled for such database queries.

You can delete existing database queries at any time.

To delete a query

1. Click **Edit | Edit database queries** on the menu bar.
2. Click the database query you would like to delete in the **Edit database queries** dialog.
3. Click  **Delete**.
4. Confirm the prompt by selecting **Yes** in the dialog.
5. Click **Close** in the **Edit database queries** dialog.

Related topics

- [Managing database queries](#) on page 48
- [Displaying database queries](#) on page 49
- [Creating a database query](#) on page 50
- [Editing a database query](#) on page 50
- [Testing a database query](#) on page 51

Managing tabs

Use the **Tabs** dialog to enable opened tabs, close tabs, or save changes that you have made in tabs.

To manage tabs

1. Click **View | Tabs** on the menu bar.
2. Click one or more tabs (while holding down the Ctrl key) in the **Tabs** dialog.
3. Perform one of the following tasks:
 - Click **Enable** to enable the tab.
 - Click **Save** to save tab changes.
 - Click **Close tabs** to close the tab.
4. Click **Close**.

Related topics

- [Menu bar](#) on page 16

Managing layouts

You can adjust, save, and, where necessary, restore the layout (assign and show different menus and panes) at any time.

To save your own layout

1. Customize the layout of the API Designer to suit your needs.
2. Click **View | Save layout** on the menu bar.

To restore a saved layout

- Click **View | Restore saved layout** on the menu bar.

To restore the default layout

- Click **View | Restore standard layout** on the menu bar.

To restore the default layout including the window size

- Click **View | Restore standard layout (including size)** on the menu bar.


Related topics

- [Menu bar](#) on page 16

Displaying the change history (command list)

Open the command list using **View | Command list** (see [Opening the command list](#) on page 54).



Use the **Command list** window to display any changes made to an object and to either undo or redo them.

Executed commands are indicated with the  icon. This icon is not shown for commands that were undone.

The use of wizards allows numerous commands to be automatically implemented, which in the command list are displayed as composite commands and the individual commands are shown at a second level. You can only undo the composite commands.

The following table gives an overview of the various features available in the **Command list** window.

Table 16: Controls

Control	Description
 Undo	Undoes the last implemented command in the list.
 Redo	Redoes the last command in the list that was undone.

Related topics

- [Opening the command list](#) on page 54

Opening the command list

You can view a list of actions that have been taken at any time.

To open the command list

- Click on **View | Command list** on the menu bar.

Related topics

- [Displaying the change history \(command list\)](#) on page 54






Bookmarks

Open the **Bookmarks** window using **View | Bookmarks** (see [Editing bookmarks](#) on page 55).

To make navigating around the API Designer easier and to find objects quickly, you can set bookmarks to any node in the [Definition tree view](#). View, manage, and use these bookmarks in the **Bookmarks** window.

The following table provides an overview of the various features available within the **Bookmarks** window.

Table 17: Controls

Control	Description
 Delete all bookmarks	Deletes all bookmarks (see Deleting bookmarks on page 57).
 Edit bookmark description	Opens a dialog that allows you to change the description of the selected bookmark (see Editing bookmarks on page 55).
 Remove module/-component bookmark	Deletes all bookmarks for the module (or component) selected in the list (see Deleting bookmarks on page 57). NOTE: This feature is only available if you selected to group the bookmarks by module/component earlier (see Group by modules/components) button.
 Delete current bookmark	Deletes the bookmark that you have selected in the list (see Deleting bookmarks on page 57).
 Group by modules/-components	Groups the bookmarks by the API projects to which they are assigned.

Related topics

- [Editing bookmarks](#) on page 55
- [Setting bookmarks](#) on page 56
- [Deleting bookmarks](#) on page 57

Editing bookmarks

You can [show](#) all bookmarks, [delete](#) all bookmarks, or [change](#) the description of bookmarks at any time.


To open the bookmark window

- Click **View | Bookmarks** on the menu bar.

To open a bookmark

1. Click **View | Bookmarks** on the menu bar.
2. Double-click a bookmark in the **Bookmarks** window.

To edit the bookmark description

1. Click **View | Bookmarks** on the menu bar.
2. Click a bookmark in the **Bookmarks** window.
3. Click  **Edit bookmark description**.
4. Insert a description for the bookmark in the **Bookmark description** dialog.
5. Click **OK**.


Related topics

- [Bookmarks](#) on page 55
- [Setting bookmarks](#) on page 56
- [Deleting bookmarks](#) on page 57

Setting bookmarks

You can set a bookmark for database objects at any time. This allows you to do things such as quickly access frequently used nodes.

To set a bookmark

1. On the menu bar, click **View | Navigation**.
2. In the navigation, double-click the database object that contains the node you require.
3. In the definition tree view, right-click the node for which you would like to set a bookmark.
4. Click  **Set bookmark** in the context menu.
5. Insert a description for the bookmark in the **Bookmark description** dialog.
6. Click **OK**.

Related topics


- [Bookmarks](#) on page 55
- [Editing bookmarks](#) on page 55

- [Deleting bookmarks](#) on page 57



Deleting bookmarks

You can delete [single bookmarks](#), [all bookmarks within a module](#), or [all bookmarks within a project](#) at any time.


To delete a single bookmark

1. Click **View | Bookmarks** on the menu bar.
2. Click the bookmark that you would like to delete in the **Bookmarks** window.
3. Click  **Delete current bookmark**.
4. Confirm the prompt by selecting **Yes** in the dialog.

To delete all the bookmarks in a module/component

1. Click **View | Bookmarks** on the menu bar.
2. Click  **Group by modules/components** in the **Bookmarks** window.
3. Click the module whose bookmarks you would like to delete.
4. Click  **Remove bookmarks from module/component**.
5. Confirm the prompt by selecting **Yes** in the dialog.

To remove all bookmarks

1. Click **View | Bookmarks** on the menu bar.
2. Click **Delete all bookmarks** in the  **Bookmarks** window.
3. Confirm the prompt by selecting **Yes** in the dialog.

Related topics

- [Bookmarks](#) on page 55
- [Editing bookmarks](#) on page 55
- [Setting bookmarks](#) on page 56

Compiling an API

TIP: See additional configuration options for compilation directly on the API project (see [Configuring the compilation](#) on page 74 and in the [global settings](#)).

Before you can use an API that has been created with the API Designer, the API must be compiled using the API Designer compiler.

The API Designer compiler can be opened from the API Designer, as well as from the Database Compiler. For more detailed information about the Database Compiler, see the *One Identity Manager Operational Guide*.

A web project must be compiled in the following cases:

- After changing a definition (API file or API project) in the API Designer
- After changing certain system settings that require Database Compiler to be run

The API Designer compiler creates a set of DLL files from the project's XML definition and saves them in the database.

Methods of compiling

There are two ways to compile a web project:

- Run a **Release compilation** to release a specific version of the project for use.
NOTE: Changes within the API Designer do not affect the API as long as there is no release compilation.
- Use a **Debug compilation** during the development phase for testing and debugging purposes. Debug compilation creates additional code to support the API Designer debugger. This means the DLL files are somewhat larger.

An API loads the latest compiled DLL files on startup. If these DLL files are updated, the web project reloads the new DLL files; however, only new sessions run with the code from the newly loaded DLLs.

Related topics

- [Testing a compilation](#) on page 58
- [Starting a compilation](#) on page 59
- [Managing versions \(compilation branches\)](#) on page 62
- [Managing compilation errors and warnings \(task window\)](#) on page 60
- [Resolving errors and warnings](#) on page 61
- [Opening the compiling log](#) on page 61
- [Configuring the compilation](#) on page 74
- [Global settings](#) on page 23

Testing a compilation

The two types of compilation ([Debug](#) and [Release](#) compilation) can be tested in advance.

To test the compilation

1. On the menu bar, click **View | Start page**.
2. On the start page, expand the **Compilation** pane.
3. In the **Compilation** pane, perform one of the following actions:
 - To test a debug compilation, enable the **DEBUG** option.
 - To test a release compilation, enable the **RELEASE** option.
4. Click **Test compilation**.

The [Compilation log](#) opens and shows compilation status and progress.

The **Tasks** window opens. Use this to view and rectify any errors and warnings that arise during compilation. For more information, see [Managing compilation errors and warnings \(task window\)](#) on page 60.

Related topics

- [Compiling an API](#) on page 57
- [Managing compilation errors and warnings \(task window\)](#) on page 60
- [Menu bar](#) on page 16

Starting a compilation

You can start two types of compilation ([Debug](#) and [Release](#)). If compilation completes without any errors, then the compiled API is written to the database.

To start compilation

1. On the menu bar, click **View | Start page**.
2. On the start page, expand the **Compilation** pane.
3. In the **Compilation** pane, perform one of the following actions:
 - To start a debug compilation, enable the **DEBUG** option.
 - To start a release compilation, enable the **RELEASE** option.
4. Click **Compile**.

The [Compilation log](#) opens and shows compilation status and progress.

The **Tasks** window opens if errors arise. Use this to view and rectify any errors and warnings that arise during compilation. For more information, see [Managing compilation errors and warnings \(task window\)](#) on page 60.

Related topics

- [Compiling an API](#) on page 57
- [Managing compilation errors and warnings \(task window\)](#) on page 60

- [Testing a compilation](#) on page 58
- [Menu bar](#) on page 16

Managing compilation errors and warnings (task window)

Open the task window with **View | Tasks** (see [Opening the task window](#) on page 61).

Use the **Tasks** window to view compilation errors and warnings and to rectify them where necessary (debug).




- **Compilation errors** prevent the web project from compiling properly and must therefore be eliminated. Development states cannot be released if they cannot be compiled.
- **Compilation warnings** relate to missing extensions, or to messages concerning accessibility. The compilation warnings of the relevant compiler are also taken into account. If compiler warnings are the only type of message that is generated, the development state will be successfully compiled nonetheless.

TIP: In the global settings, you can define which warnings are displayed as errors during compilation and which errors are ignored. For more information, see [Global settings](#) on page 23.

If individual messages are displayed (⊕ icon) together, it means that the errors indicated occur at various locations throughout the web project. This can happen, for example, if an extension that is referenced by a number of nodes is missing.

The following table gives an overview of the various features in the **Tasks** window.

Table 18: Controls

Control	Description
 Errors	Hides or displays compilation errors.
 Warnings	Hides or displays compilation warnings.
 Error details	Displays the error message. This button is only active if you have highlighted a listed error message. Click this button to view a detailed description of the error. Click Send as mail to transfer the error message to an email and send.

Related topics

- [Opening the task window](#) on page 61
- [Resolving errors and warnings](#) on page 61

Opening the task window

You can open the task window at any time.

To open the task window

- Click **View** | **Tasks** on the menu bar.

Related topics

- [Resolving errors and warnings](#) on page 61
- [Managing compilation errors and warnings \(task window\)](#) on page 60

Resolving errors and warnings

If errors occur when compiling your API, the task view can be used to see and resolve them.

TIP: In the global settings, you can define which warnings are displayed as errors during compilation and which errors are ignored. For more information, see [Global settings](#) on page 23.

To open and edit objects with errors in the task window

1. Click **View** | **Tasks** on the menu bar.
2. Click either **Errors** or **Warnings** in the task window.
3. Perform one of the following tasks:
 - Double-click the listed error/warning and then resolve the error/warning within the **Node editor** window itself.

NOTE: The node editor window opens if the node contains the error. If the error occurs when the resulting code is compiled, you can double-click it to display **Generated code (read-only)** in the definition tree view.

- OR -

- Click the error/warning in the list and then click  **Correct errors**.

Related topics

- [Opening the task window](#) on page 61
- [Managing compilation errors and warnings \(task window\)](#) on page 60

Opening the compiling log

The compiling log displays compiling status and progress.

To open the compiling log

- Click **View | Compilation** on the menu bar.

Related topics

- [Compiling an API](#) on page 57
- [Menu bar](#) on page 16

Managing versions (compilation branches)


To manage different versions of your compiled API and save them in the database, you use compilation branches. Compilation branches are managed in a separate pane on the start page. Here you can [select](#) the compilation branch that you want to use, display the existing compilation branches, [create](#) compilation branches, [edit](#) compilation branches, and [delete](#) compilation branches.

Related topics

- [Compiling an API](#) on page 57
- [Selecting and using compilation branches](#) on page 62
- [Creating compilation branches](#) on page 63
- [Editing compilation branches](#) on page 63
- [Deleting compilation branches](#) on page 64

Selecting and using compilation branches

To select and use compilation branches

1. On the menu bar, click **View | Start page**.
2. On the start page, expand the **Compilation branches** pane.
3. In the **Compilation branches** pane, in the **Compilation branch identifier** list, click the compilation branch that you want to use.
| **TIP:** If you do not want to use a compilation branch, click  **Use master status**.




Related topics

- [Managing versions \(compilation branches\)](#) on page 62
- [Creating compilation branches](#) on page 63

- [Editing compilation branches](#) on page 63
- [Deleting compilation branches](#) on page 64

Creating compilation branches

To use a compilation branch


1. On the menu bar, click **View | Start page**.
2. On the start page, expand the **Compilation branches** view.
3. In the **Compilation branches** view, click  **Manage name of branches**.
4. In the **Manage compilation branches** window, click  **Add**.
A new entry **Unknown** is added at the end of the list.
5. In the list, click **Unknown**.
6. In the **Identifier** field, enter a unique name for the compilation branch.
7. (Optional) In the **Description** field, enter a description for the compilation branch. This description may explain, for example, the intended purpose of the compilation branch.
8. Click  **Save**.

Related topics

- [Managing versions \(compilation branches\)](#) on page 62
- [Selecting and using compilation branches](#) on page 62
- [Editing compilation branches](#) on page 63
- [Deleting compilation branches](#) on page 64

Editing compilation branches

To edit existing compilation branches

1. On the menu bar, click **View | Start page**.
2. On the start page, expand the **Compilation branches** pane.
3. In the **Compilation branches** pane, click  **Manage compilation branches**.
4. In the **Manage compilation branches** dialog, click the compilation branch that you want to edit in the list.
5. In the **Identifier** field, enter a unique name for the compilation branch.
6. (Optional) In the **Description** field, enter a description for the compilation branch. This description may explain, for example, the intended purpose of the compilation

branch.



7. Click  **Save**.

Related topics

- [Managing versions \(compilation branches\)](#) on page 62
- [Selecting and using compilation branches](#) on page 62
- [Creating compilation branches](#) on page 63
- [Deleting compilation branches](#) on page 64

Deleting compilation branches

To delete compilation branches

1. On the menu bar, click **View | Start page**.
2. On the start page, expand the **Compilation branches** pane.
3. In the **Compilation branches** pane, click  **Manage compilation branches**.
4. In the **Manage compilation branches** dialog window, click the compilation branch that you want to delete from the list.
5. Click **Delete** .
6. Confirm the **Delete?** prompt by selecting **Yes**.

Related topics

- [Managing versions \(compilation branches\)](#) on page 62
- [Selecting and using compilation branches](#) on page 62
- [Creating compilation branches](#) on page 63
- [Editing compilation branches](#) on page 63

Testing an API

You can test the functionality of your API locally on your PC at any time.

To test your API locally

1. On the menu bar, click **View | Start page**.
2. Expand the **Self-hosted API Server** pane on the start page.
3. In the **Startup options** field, enter the options for starting the API.
| **TIP:** Alternatively, you can also select previous commands from the list.

4. Click **Start**.

The API is compiled and will then be available locally. The corresponding web address is displayed next to the **Status**. Click the address to open this directly in the browser.

Related topics



- [Opening the start page](#) on page 23

Linking C# projects to the API Designer

To edit an API as a C# project with external programs (for example, Visual Studio), you must perform three steps:


1. [Link](#) your API Designer project with a new or existing C# project.
2. [Edit](#) the C# project in an external program.
3. [Open](#) the C# project again in API Designer and save it in the API project.

To link the API Designer project with a C# project

1. On the menu bar, click **View | Start page**.
2. On the start page, expand the **C# development** pane.
3. In the **C# development** pane, perform one of the following actions:
 - To export and link the API Designer project as a new C# project, click  **Export C# project**. Navigate to the folder where you want to export the content of your API Designer project as a C# project and click **OK**.
 - To link the API Designer project with an existing project, click  **Load C# project**.

The API Designer is linked with the C# project.

To edit the C# project in an external program

1. On the menu bar, click **View | Start page**.
2. On the start page, expand the **C# development** pane.
3. In the **C# development** pane, click **Project file: <path to C# project>**.
The project opens in the program that the project file is linked with.
TIP: To open the project folder directly, click  **Open corresponding folder**.
4. Edit the project in the external program. For example, you can create, change, or delete API files.

To save changes back to the API Designer project

1. Open the API Designer.
2. On the menu bar, click **View | Start page**.
3. On the start page, expand the **C# development** pane.
4. In the **C# development** pane, click **↔ Synchronize C# project with base**.
You now see the objects that you have changed outside the API Designer.
5. In the list on the right, next to the changed objects, select the actions that you want to perform for the API Designer project.

Status message	Description	Actions
New C# file	A new API file was created in the C# project.	Add API file: Adds the C# file that you created in the external program to your API Designer project as an API file. Delete file: Deletes the C# class in the C# project.
New API file	A new API file was created in the API Designer Sharp project.	Add C# file: Adds the API file that you created in the API Designer to your C# project as a C# file. Delete API file: Deletes the API file in the API Designer project.
API file is newer	An API file was modified in the API Designer project.	Update: Transfers the changes to the API file from the API Designer project into the C# project. Revert changes: Reverses the changes that you made in your API Designer project in the API file.
C# file is newer	An API file was modified in the C# project.	Update: Transfers the changes to the API file from the C# project into the API Designer project.

Status message	Description	Actions
		<p>Revert changes: Reverses the changes that you made in your C# project in the API file.</p>

6. Select the check box next to the objects for which the selected actions should be performed.

TIP: To quickly select or deselect all objects, select the **Select all/deselect all** check box above the list.

7. Click  **Apply selected actions.**

API projects

An API project represents the actual API application itself.

You can combine API files that you have created in one API project for a logical application. The API project includes the configuration. The API project includes the [authentication](#) on the database.



Related topics

- [Creating API projects](#) on page 68
- [Editing API projects](#) on page 69
- [Deleting API projects](#) on page 70
- [Configuring authentication](#) on page 71
- [Configuring the compilation](#) on page 74
- [Assigning API files to an API project](#) on page 78
- [Importing API projects](#) on page 75


Creating API projects

You can create new API projects at any time.

To create an API project

1. On the menu bar, click **View | Navigation**.
2. Click  **API projects** in the navigation.
3. Click  **Add | Add API project**.
4. In the [definition tree view](#), click the topmost node.
5. Click **View | Node editor** on the menu bar.
6. In the [node editor view](#), configure the following settings.

Setting	Description
General settings	
Identifier	Enter a unique name for the node.
Technical abbreviation	Enter a short name for the API project. This name is used later for the assignment of the project.
Control-ID	Enter a unique ID for the node.
Model version	Shows the model version being used.
Workflow control	
Allow extensions to this document	Enable this option to permit the creation of enhancements to this node.
Advanced settings	
Required database modules	(Optional) Enter the database modules required for this API project.

7. Configure further API project settings (see [Configuring authentication](#) on page 71 and [Configuring the compilation](#) on page 74).
8. On the toolbar, click  **Save**.

Related topics

- [Editing API projects](#) on page 69
- [Configuring authentication](#) on page 71
- [Configuring the compilation](#) on page 74
- [Deleting API projects](#) on page 70
- [API projects](#) on page 68
- [Navigation](#) on page 21

Editing API projects

You can edit any API projects you have created at any time.

| NOTE: You cannot edit any API projects that have been predefined by the API Designer.

To edit an API project

1. On the menu bar, click **View | Navigation**.
2. Click



API projects in the navigation.

3. In the tree structure, double-click the API project to be edited.
4. Click **View | Node editor** on the menu bar.
5. Use the [Definition tree view](#) and the [Node editor view](#) to configure further API project settings (see [Configuring authentication](#) on page 71 and [Configuring the compilation](#) on page 74).
6. On the toolbar, click **Save**.

Related topics

- [Creating API projects](#) on page 68
- [Configuring authentication](#) on page 71
- [Configuring the compilation](#) on page 74
- [Deleting API projects](#) on page 70
- [API projects](#) on page 68
- [Navigation](#) on page 21

Deleting API projects

You can delete any API projects you have created at any time.

NOTE: You cannot delete any API projects that have been predefined by the API Designer.

To delete an API project

1. On the menu bar, click **View | Navigation**.
2. Click **API projects** in the navigation.
3. In the tree structure, click on the API project to be deleted.
4. Click **Delete**.
5. Confirm the prompt by selecting **Yes** in the dialog.
6. Click **Reload data** in the tree structure.

Related topics

- [Creating API projects](#) on page 68
- [Editing API projects](#) on page 69
- [API projects](#) on page 68
- [Navigation](#) on page 21





Configuring authentication

The **Authentication** node in the definition tree view is used to determine how clients will log in to the API.


There are three authentication options that you can configure:

- **Standard**: Only the authentication methods you list here are permitted. For this method you can also [enable single sign-on](#).
- **Allow all manual modules**: All manual authentication modules are permitted, if these are activated for the selected product. For this method you can also [enable single sign-on](#).
- **Fixed credentials**: This settings enables the user to log in to the API using fixed login data. To use this option, the login data must be stored in the `web.config` files on each API server.




To set the permitted manual authentication options

1. On the menu bar, click **View | Navigation**.
2. Click  **API projects** in the navigation.
3. In the tree structure, double-click the API project to be edited.
4. In the [definition tree view](#), click the  **Authentication** node.
5. Click **View | Node editor** on the menu bar.
6. In the [node editor view](#), perform the following actions:
 - a. In the **Authentication type** menu, select **Standard**.
 - b. Enter a unique ID for the node in the **Control ID** field.
 - c. (Optional) In the **Authentication properties** field, enter the properties for the authentication. For more information about the authentication modules, see the *One Identity Manager Configuration Guide*.
 - d. (Optional) If authorizations for users are controlled by a product, enable the **Product** option and select the required product in the selection list.
7. In the definition tree view, open the  **Authentication** node.
8. Right-click the  **Manual authentication modules** node.
9. Click **Authentication module** in the context menu.




The **Authentication module** node is placed as a child to the node.
10. Click the **Authentication module** node.
11. In the node editing view, select the required authentication module from the **Name** selection list. For more information about the authentication modules, see the *One Identity Manager Configuration Guide*.
12. Enter a unique ID for the node in the **Control ID** field.


13. Repeat steps 8 to 12 until to add each authentication method you wish to use.
14. Click  **Save** on the menu bar.

To permit all manual authentication options

1. On the menu bar, click **View | Navigation**.
2. Click  **API projects** in the navigation.
3. In the tree structure, double-click the API project to be edited.
4. In the [definition tree view](#), click the  **Authentication** node.
5. Click **View | Node editor** on the menu bar.
6. In the [node editor view](#), perform the following actions:
 - a. In the **Authentication type** selection list, select **Allow all manual modules**.
 - b. Enter a unique ID for the node in the **Control ID** field.
 - c. (Optional) In the **Authentication properties** field, enter the authentication properties.
 - d. (Optional) Enable the **Product** option and select the product from the list.
7. Click  **Save** on the menu bar.

To allow single sign-on

1. On the menu bar, click **View | Navigation**.
2. Click  **API projects** in the navigation.
3. In the tree structure, double-click the API project to be edited.
4. In the [definition tree view](#), open the  **Authentication** node.
5. Right-click the  **Authentication modules for single sign-on** node.

NOTE: This node is only available if you have [manually set the authentication options yourself](#) or if [you have enabled all manual authentication options](#).
6. Click **Authentication module** in the context menu.
The **Authentication module** node is placed as a child to the node.
7. Click the **Authentication module** node.
8. Click **View | Node editor** on the menu bar.
9. In the [node editing view](#), select the required authentication module from the **Name** selection list. For more information about the authentication modules, see the *One Identity Manager Configuration Guide*.
10. Click  **Save** on the menu bar.

Log in with stored login data

To approve a login with stored login data, perform the following two steps:

1. **Store** the login data for the users for whom you want to allow access in the `web.config` file of each API server.
2. **Configure** the authentication in the API Designer for the API project.




To store login data in the API Server

1. Connect to your API Server.
2. Open the `web.config` file in a text editor.
| **NOTE:** If the file is encrypted, you must decrypt it before editing.
3. In the `<connectionStrings>` section, add the following entry:

```
<add name="sub:<NAME>" connectionString="Module=DialogUser;User=<USER>;(Password)Password=<PASSWORD>" />
```

- `<NAME>` stands for the name/ID of the API project.
 - `<USER>` stands for the login name of the user.
 - `<PASSWORD>` stands for the user's password.
4. Save your changes to the file.
 5. (Optional) encrypt the file.

To configure the login with the saved login data on the API project

1. Start the API Designer.
2. On the menu bar, click **View | Navigation**.
3. Click  **API projects** in the navigation.
4. In the tree structure, double-click the API project to be edited.
5. In the **definition tree view**, click the  **Authentication** node.
6. Click **View | Node editor** on the menu bar.
7. In the **node editor view**, perform the following actions:
 - a. In the **Authentication type** selection list, select **Fixed credentials**.
 - b. Enter a unique ID for the node in the **Control ID** field.
 - c. (Optional) In the **Authentication properties** field, enter the authentication properties.
 - d. (Optional) Enable the **Product** option and select the product from the list.
8. Click  **Save** on the menu bar.

Related topics



- [Creating API projects](#) on page 68
- [Editing API projects](#) on page 69
- [API projects](#) on page 68

Configuring the compilation

Use the **Compilation settings** node in the definition tree view to configure the settings for compiling the API.

If you want to use code from other DLLs in your API code (for example, API files from other projects), you need to create an assembly reference so that the compiler recognizes these DLLs.

To create an assembly reference

1. On the menu bar, click **View | Navigation**.
2. Click  **API projects** in the navigation.
3. In the tree structure, double-click the API project to be edited.
4. In the [definition tree view](#), right-click the **Compilation settings** node.
5. In the context menu, click **Assembly reference**.
The **Assembly reference** node is added under this node.
6. In the definition tree view, click **Assembly reference**.
7. Click **View | Node editor** on the menu bar.
8. In the [node editor view](#), enter the name of the assembly you wish to reference into the **Referenced assembly** field.
9. Click  **Save** on the toolbar.

Related topics

- [Compiling an API](#) on page 57
- [Creating API projects](#) on page 68
- [Editing API projects](#) on page 69
- [API projects](#) on page 68
- [Configuring authentication](#) on page 71

Assigning API files to an API project

In order for the API files you have created to be used practically, they must be assigned to an [API project](#).

To assign API files to an API project

1. On the menu bar, click **View | Navigation**.
2. In the navigation view, click



API projects.

3. In the tree structure, double-click the API project to be edited.
4. In the [definition tree view](#), right-click the topmost node.
5. In the context menu, click **API file reference**.
The new **API file reference** node is added.
6. In the definition tree view, click **API file reference**.
7. Click **View | Node editor** on the menu bar.
8. In the [node editor view](#), enter a unique ID for the node into the **Control ID** field.
9. Select the required file in the **Name** list.
TIP: To skip directly to the file definition, click **Show definition object**.
10. On the toolbar, click **Save**.

Related topics

- [Creating API files](#) on page 77
- [Editing API files](#) on page 77
- [Importing API files](#) on page 79
- [Deleting API files](#) on page 78
- [Creating API projects](#) on page 68
- [Editing API projects](#) on page 69
- [Deleting API projects](#) on page 70
- [API projects](#) on page 68

Importing API projects

You can import API projects into the API Designer. The API Designer independently detects whether the projects are API projects, and imports them as such.

To import an API project

1. Click **Edit | Import object** on the menu bar.
2. In the file browser, select the required API project and click **Open**.
The API project is imported.

Related topics

- [API projects](#) on page 68
- [Menu bar](#) on page 16

API files

You can use an API file to create a call for exchanging data with the server (or database) relating to a specific application scenario. An API file can belong to more than one project. In an API file, you can define an API method, for example.

NOTE: If you create a new API file to provide a new API method, you must name the API file the same as the class. Ensure you use the correct case.

You can use the API Designer to create the following API files.

Entity files

Entity files work with small parts of the object model in order to read data from the database or write data to the database. When you create an entity file, you only need to enter the table and column name and, if required, a filter condition (WHERE clause). Internal processing is handled by the API Server. The data schema for the input and output also has a specific format.

For examples for the definition of entity files, see the [SDK](#) under `Sdk01_Basics\01-BasicQueryMethod.cs`.

C# files

C# files are files for which you fully define the processing, input, and output data in code. This type therefore offers the greatest flexibility.

For examples for the definition C# files, see the [SDK](#) under `Sdk01_Basics\03-CustomMethod.cs`.

SQL files

SQL files are files that provide data from a predefined SQL query through the API. Create the parameters of a query as SQL parameters.

For examples for the definition of SQL files, see the [SDK](#) under `Sdk01_Basics\02-BasicSqlMethod.cs`.

Related topics




- [Creating API files](#) on page 77
- [Editing API files](#) on page 77
- [Deleting API files](#) on page 78
- [Assigning API files to an API project](#) on page 78
- [Importing API files](#) on page 79

Creating API files

You can create new API files at any time.

NOTE: If you create a new API file to provide a new API method, you must name the API file the same as the class. Ensure you use the correct case.

To create an API file

1. On the menu bar, click **View | Navigation**.
2. In the navigation, click  **API files**.
3. Click  **Add | Add API file**.
4. In the new window, create the file definition.
5. On the toolbar, click  **Save**.

Related topics


- [API files](#) on page 76
- [Editing API files](#) on page 77
- [Deleting API files](#) on page 78
- [Navigation](#) on page 21


Editing API files

You can edit the API files you have created at any time.

NOTE: You cannot edit API files that have been predefined by the API Designer.

To edit an API file

1. On the menu bar, click **View | Navigation**.
2. In the navigation, click  **API files**.

3. In the tree structure, click the API file that you want to edit.
4. In the new window, create the file definition.
5. On the toolbar, click  **Save**.

Related topics




- [API files](#) on page 76
- [Creating API files](#) on page 77
- [Deleting API files](#) on page 78
- [Navigation](#) on page 21

Deleting API files

You can delete the API files you have created at any time.

| **NOTE:** You cannot delete API files that have been predefined by API Designer.

To delete an API file

1. On the menu bar, click **View | Navigation**.
2. In the navigation, click  **API files**.
3. In the tree structure, click the API file that you want to delete.
4. Click  **Delete**.
5. Confirm the prompt by selecting **Yes** in the dialog.
6. Click  **Reload data** in the tree structure.




Related topics

- [API files](#) on page 76
- [Creating API files](#) on page 77
- [Editing API files](#) on page 77
- [Navigation](#) on page 21

Assigning API files to an API project

In order for the API files you have created to be used practically, they must be assigned to an [API project](#).

To assign API files to an API project

1. On the menu bar, click **View | Navigation**.
2. In the navigation view, click  **API projects**.
3. In the tree structure, double-click the API project to be edited.
4. In the [definition tree view](#), right-click the topmost node.
5. In the context menu, click **API file reference**.
The new **API file reference** node is added.
6. In the definition tree view, click **API file reference**.
7. Click **View | Node editor** on the menu bar.
8. In the [node editor view](#), enter a unique ID for the node into the **Control ID** field.
9. Select the required file in the **Name** list.
TIP: To skip directly to the file definition, click  **Show definition object**.
10. On the toolbar, click  **Save**.

Related topics

- [Creating API files](#) on page 77
- [Editing API files](#) on page 77
- [Importing API files](#) on page 79
- [Deleting API files](#) on page 78
- [Creating API projects](#) on page 68
- [Editing API projects](#) on page 69
- [Deleting API projects](#) on page 70
- [API projects](#) on page 68

Importing API files

You can import API files into the API Designer. The API Designer automatically detects that the files are API files and imports them as such.

To import an API file

1. Click **Edit | Import object** on the menu bar.
2. In the file browser, select the API file and click **Open**.
The API file is imported.

Related topics

- [API files](#) on page 76
- [Menu bar](#) on page 16

API Server

The API that you created in the API Designer is available in the API Server.

To call the API Server web interface

- In a web browser, open the web address (URL) of your API Server.

From here, you can:

- Configure the API Server.
- Call the swagger documentation for your API.
- Open the Operations Support Web Portal.
- Call all installed HTML5 applications.

ImxClient command line program

The ImxClient command line tool can be used to execute all API Designer API functions from a command line without a graphical interface.

Related topics

- [Starting the ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

Starting the ImxClient command line program

You can start the ImxClient command line tool at any time using any command line interface.

To start the ImxClient command line program

1. Open a command line interface (for example, Windows Powershell).
2. In the command line program, go to the installation path for the API Designer.
3. Run the ImxClient.exe application.

Related topics

- [ImxClient command line program](#) on page 82

ImxClient command overview

The following chapters contain a list of all ImxClient commands that you can execute.

Related topics

- [help](#) on page 83
- [compile-app](#) on page 83
- [repl](#) on page 84
- [branch](#) on page 84
- [connect](#) on page 85
- [compile-api](#) on page 85
- [fetch-files](#) on page 87
- [push-files](#) on page 87
- [get-apistate](#) on page 88
- [get-filestate](#) on page 88
- [setup-web](#) on page 89
- [run-apiserver](#) on page 90
- [check-translations](#) on page 91

help

Displays a list of available commands.

Parameters

To view help for a specific command, add the command as a parameter.

Example: `help fetch-files`

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

compile-app

Executes HTML5 package compilation.

This command performs the following steps:

1. Executes the **npm install** command in the application folder.
2. Executes the **npm run build** command in the package folder.
3. Creates the output in subdirectory `dist`
.The output is stored as a zip file in the database.

Parameters

- `/conn <name of the database connection>`: Specify the database to which you want to connect.
- `/dialog <name of the dialog authentication>`: Enter the dialog authentication.
- `/path <path to main folder>`: Enter the path to the main folder. This folder contains the application to be compiled. This folder normally contains the `package.json` file of the application.
- `-N`: (Optional) Prevents saving to the database.
- `-D`: Executes [debug compilation](#).
- `/branch <ID of the compilation branch>`: (Optional) Saves the compiled result under the specified compilation branch. You must also specify the parameter `-D`.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

repl

Starts the ImxClient command line tool in REPL mode.

In this mode, the following actions are performed in an infinite loop:

- Read commands from **stdin**.
- Forward commands to the relevant plug-in.
- Output the results of processing to **stdout**.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

branch

Manages [compilation branches](#) in the database.

Parameters

- **Run without parameters**: If the command is called without specifying any parameters, this command outputs the total number of compilation branches and

their IDs from the database.

- `/id <ID of the compilation branch>`: (Optional) Queries the field name and corresponding values of a compilation branch.
- `-d /id <ID of the compilation branch>`: (Optional) Deletes a compilation branch.
- `branch -c /id <ID of the compilation branch>`: (Optional) Creates a new compilation branch.

To also specify a description of the compilation branch, use `/description <description>`.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

connect

Establishes a database connection.

If a connection to a database has already been established, this is closed and a new connection is then established.

Parameters

- `/conn <name of the database connection>`: Specify the database to which you want to connect.
- `/dialog <name of the dialog authentication>`: Enter the dialog authentication.
- `/factory <target system>`: (Optional) Enter the target system for the connection. Enter this parameter if you want to establish a connection to the application server.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

compile-api

Compiles the API and saves the result to the database.

Parameters

- `/conn <name of the database connection>`: Specify the database to which you want to connect.
- `/dialog <name of the dialog authentication>`: Enter the dialog authentication.
- `/factory <name of target system>`: (Optional) Enter the target system for the connection. Enter this parameter if you want to establish a connection to the application server. Example: `QBM.AppServer.Client`.
- `/solution <path to solution project>`: (Optional) Enter the path to the solution project file that you want to use. If you do not enter these parameters, a database project is used.
- `/mode <compile mode>`: (optional) Enter the mode for the compilation:
 - `normal`: Complete compilation (default mode).
 - `nostore`: Assemblies are not saved in the database.
 - `nocompile`: Creates only C# code. The compilation is not executed.
 - `nocodegen`: Executes only the compilation. No C# code is generated.
- `-E`: (Optional) Activates extended checks.
- `-D`: (Optional) The compilation is executed as debug compilation.
- `/csharpout <path to target folder for C# files>`: (Optional) Enter the path to the folder in which you want to save the C# files.
- `/copyapi <path to folder>`: (Optional) Enter the path to the folder to which you want to copy the `imx-api.tgz` file.
- `/apidll <path to an API-DLL>`: (Optional) Enter the path for an API-DLL file that you want to use. The `/solution` and `/branch` parameters are ignored if you use this parameter.
- `/branch <ID of the compilation branch>`: (Optional) Enter the compilation branch under which you want to save the project. You must also specify the parameter `-D`.
- `/nowarn <error1,error2,...>`: (Optional) Specify which errors are to be ignored during compilation. Enter the codes for the warnings, separated by commas.
- `/warnaserror <error1,error2,...>`: (Optional) Specify which warnings are displayed as errors during compilation. Enter the codes for the warnings, separated by commas.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

fetch-files

Loads all files of the HTML Development machine role from the database and saves them in a local file.

Parameters

- `/conn <name of the database connection>`: Specify the database to which you want to connect.
- `/dialog <name of the dialog authentication>`: Enter the dialog authentication.
- `/factory <target system>`: (Optional) Enter the target system for the connection. Enter this parameter if you want to establish a connection to the application server.
- `/path <path to target folder>`: (Optional) Enter the path to the folder in which you want to save the files.
- `/targets <target1;target2;...>`: (Optional) Specify which machine roles you want to use. If you do not use this parameter, the HTML Development machine role is used.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

push-files

Saves files that you have changed locally back to the database.

Parameters

- `/conn <name of the database connection>`: Specify the database to which you want to connect.
- `/dialog <name of the dialog authentication>`: Enter the dialog authentication.
- `/targets <target1;target2;...>`: Specify which machine roles you want to use. If you do not use this parameter, the HTML Development machine role is used.
- `/factory <target system>`: (Optional) Enter the target system for the connection. Enter this parameter if you want to establish a connection to the application server.
- `/path <path to folder>`: (optional) Enter the path to the folder containing the files that you have changed and you now want to save to the database.
- `/tag <uid>`: (Optional) Specifies the UID of a change tag.
- `/add <file1;file2;...>`: (Optional) Specify the paths to all new files to be added to the database. Use relative paths.

- `/del <file1;file2;...>`: (Optional) Enter the paths to all files that you want to delete from the database. Use relative paths.
- `-C`: (Optional) Prevents the saving of changed files and saves only new files, and deletes files from the database.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

get-apistate

Queries the compilation status of the API in the database.

Parameters

- `/conn <name of the database connection>`: Specify the database to which you want to connect.
- `/dialog <name of the dialog authentication>`: Enter the dialog authentication.
- `/factory <target system>`: (Optional) Enter the target system for the connection. Enter this parameter if you want to establish a connection to the application server.
- `/branch <ID of the compilation branch>`: (Optional) Queries the date of the compilation status of the API under which this compilation branch was saved.
- `/htmlapp <name of the HTML package>`: (Optional) Supplies data for the specified HTML package.
- `-D`: (Optional) Supplies data for debug assemblies.
- `-R`: (Optional) Supplies data for release assemblies.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

get-filestate

Compares the local file structure with the file structure in the database.

Using the **QBM | ImxClient | get-filestate | NewFilesExcludePatterns** configuration parameter, you can define which files are excluded from the synchronization. This prevents excessive load during synchronization. The `node_modules` and `imx-modules` folders are excluded from the synchronization by default.

You can adjust this parameter in the Designer. Use the following formats when defining the rules:

<https://docs.microsoft.com/en-us/dotnet/api/microsoft.extensions.filesystemglobbing.matcher>

Use the | character to separate multiple entries.

NOTE: This configuration parameter is generally only used to exclude new files from the synchronization. Files that already exist in the database are not taken into account.

Parameters

- /conn <name of the database connection>: Specify the database to which you want to connect.
- /dialog <name of the dialog authentication>: Enter the dialog authentication.
- /factory <target system>: (Optional) Enter the target system for the connection. Enter this parameter if you want to establish a connection to the application server.
- /targets <target1;target2;...>: (Optional) Specify which machine roles you want to use. If you do not use this parameter, the HTML Development machine role is used.
- /path <path to folder>: (Optional) Enter the path to the folder containing the files that you want to synchronize.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

setup-web

Installs necessary files for the development of TypeScript clients.

Parameters

- /root: Enter the path to the main folder.
- /conn <name of the database connection>: Specify the database to which you want to connect.
- /dialog <name of the dialog authentication>: Enter the dialog authentication.
- /factory <target system>: (Optional) Enter the target system for the connection. Enter this parameter if you want to establish a connection to the application server.
- /path <path to the API project>: (Optional) Specify the path to the folder for the API project.
- /branch <ID of the compilation branch>: (Optional) Enter the ID of a compilation branch for which you want to install files.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

run-apiserver

Starts or stops a self-hosted API Server.

This command requires a database connection.

Parameters

- `/conn <name of the database connection>`: Specify the database to which you want to connect.
- `/dialog <name of the dialog authentication>`: Enter the dialog authentication.
- `/factory <target system>`: (Optional) Enter the target system for the connection. Enter this parameter if you want to establish a connection to the application server.
- `-S`: (Optional) Stops the API Server.
- `/baseaddress <URL with port>`: (Optional) Specify the base URL and the port of the HTML application.
- `/baseurl <base URL>`: (Optional) Enter the base URL of the HTML application.
- `/branch <ID of the compilation branch>`: (Optional) Specify the ID of a compilation branch for whose API you want to start the API Server.
- `-D`: (Optional) Loads the debugging assemblies.
- `-C`: (Optional) Compiles the API using source data from the database.
- `-T`: (Optional) Retrieves the status of the currently running API Server.
- `-B`: (Optional) Locks the console.
- `/compile {path to solution file}`: Compiles the API using source data from a (local) solution project.
- `/excludedMiddlewares {Middleware-Name1,Middleware-Name2,...}`: (Optional) Specify which middleware services you do not want to offer. Enter multiple values separated by a comma.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

check-translations

Search for captions ([multilingual captions](#)) with missing translations in a particular folder and its subfolders.

Parameters

- `/conn <name of the database connection>`: Specify the database to which you want to connect.
- `/dialog <name of the dialog authentication>`: Enter the dialog authentication.
- `/path <Path to folder>`: Enter the path to the folder that you want to check.
- `/factory <target system>`: (Optional) Enter the target system for the connection. Enter this parameter if you want to establish a connection to the application server.

Related topics

- [ImxClient command line program](#) on page 82
- [ImxClient command overview](#) on page 82

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales and other inquiries, such as licensing, support, and renewals, visit <https://www.oneidentity.com/company/contact-us.aspx>.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product

A

add

- API files 77
- API projects 68
- change label 38
- compiler branch 63
- database query 49-50
- multilingual captions 45

API

- test 64

API Designer 7

- start 11

API development

- basics 8

API files 76

- add 77
- assign to a project 74, 78
- change 77
- create 77
- delete 78
- edit 77
- import 79
- remove 78

API projects 68

- add 68
- change 69
- create 68
- delete 70
- edit 69
- import 75
- remove 70

API Server 81

assembly reference 74

authentication

- configure 71

B

basics 8

benefits 7

bookmarks 55

- delete 57
- display 55
- open 55
- place 56
- remove 57

branches 62

C

C Sharp methods 76

C# project 65

captions 44

- change 46
- create 45
- delete 47
- edit 46
- find 45
- new 45
- remove 47
- search 45

change

- API methods 77

- API projects 69
- captions 46
- change label 39
- compiler branch 63
- database query 50
- global settings 26
- multilingual captions 46
- nodes 37
- settings 26
- change label 37
 - add 38
 - apply 38
 - change 39
 - create 38
 - delete 40
 - edit 39
 - new 38
 - remove 40
- CLI 82
- close
 - tab 52
- code
 - display 34
- colors 20
- command line 82
- command list 54
 - display 54
 - open 54
- commandos 82
- commands 54
- compile 57, 59
- compiler branch 62
 - add 63
 - apply 62
 - change 63
 - create 63
 - delete 64
 - edit 63
 - new 63
 - remove 64
 - select 62
- compiling 57
 - configure 74
 - display 61
 - execute 59
 - open 61
 - start 59
 - test 58
- configurations
 - authentication 71
 - compiling 74
- context menu 32
- create
 - API files 77
 - API projects 68
 - captions 45
 - change label 38
 - compiler branch 63
 - database query 49-50
 - multilingual captions 45
- custom layout 53

D

- database project 12
- database query 48
 - add 49-50
 - change 50
 - create 49-50
 - delete 52
 - edit 50

- manage 48
- new 49-50
- remove 52
- test 51
- deactivate compilation 29
- debug 57
- default layout 53
 - restore 53
- definition tree
 - open 31
- definition tree view 27, 30-31
 - open 31
- delete
 - API methods 78
 - API projects 70
 - bookmarks 57
 - captions 47
 - change label 40
 - compiler branch 64
 - database query 52
 - multilingual captions 47
- display
 - bookmarks 55
 - code 34
 - command list 54
 - compiling 61
 - definition tree 31
 - definition tree view 31
 - definitions 31
 - generated code 34
 - navigation 22
 - object properties 28
 - task window 61

E

- edit
 - API files 77
 - API projects 69
 - captions 46
 - change label 39
 - compiler branch 63
 - database query 50
 - multilingual captions 46
 - nodes 37
- editing nodes 35
- entity methods 76
- examples 9
- execute
 - compiling 59
- export 12, 14
- export solution 14
- extensions 34

F

- file based 13
- file path 29
- find
 - captions 45
 - multilingual captions 45
- find and replace 40, 43
- fix error 61
- fix warnings 61

G

- generated code 34
- global settings 23
 - change 26

- open 26
- graphical user interface 15
- GUI 15

H

- help 9

I

- icons 19
- import
 - API files 79
 - API projects 75
- import namespace 74
- import object to database 14
- ImxClient 82
 - commandos 82
 - branch 84
 - check-translations 91
 - compile api 85
 - compile app 83
 - connect 85
 - fetch-files 87
 - get-apistate 88
 - get-filestate 88
 - help 83
 - push-files 87
 - repl 84
 - run-apiserver 90
 - setup-web 89
- ImxClient command line program
 - start 82
- interface 15

L

- language 44-47
- languages 44-47
- layout 53
 - restore 53
 - save 53

M

- managing database queries 48
- menu 16
- menu bar 16
- multilingual captions 44-47
 - add 45
 - change 46
 - create 45
 - delete 47
 - edit 46
 - find 45
 - new 45
 - remove 47
 - search 45

N

- namespace 74
- navigate 21
- navigation 21
 - display 22
 - open 22
- new
 - API files 77
 - API projects 68
 - captions 45
 - change label 38

- compiler branch 63
- database query 49-50
- multilingual captions 45
- new API file 77
- new API project 68
- node editor 35
 - open 36
- node editor view 35
- nodes
 - change 37
 - edit 37

O

- object properties 27
 - display 28
 - open 28
- open
 - bookmarks 55
 - command list 54
 - compiling 61
 - definition tree 31
 - definition tree view 31
 - generated code 34
 - global settings 26
 - home page 23
 - navigation 22
 - node editor 36
 - object properties 28
 - settings 26
 - solution 30
 - tab 52
 - task window 61
- option 23

P

- postman 81
- project types 12

Q

- quick start 10

R

- redo 23, 54
- release 57
- reload object 29
- remove
 - API files 78
 - bookmarks 57
 - captions 47
 - change label 40
 - compiler branch 64
 - database query 52
 - multilingual captions 47
- repeat 23
- replace 40, 43
- resolution 23
- right click 32
- run
 - command line program 82
 - compiling 59

S

- save
 - tab 52
- save changes 14
- save locally 12

- save to disk 12
- save type
 - specify 12
- SDK 9
- search 40, 43
 - captions 45
 - multilingual captions 45
- searching 40, 43
- settings 23
 - change 26
 - open 26
- single sign-on 71
- software development kit 9
- solution 29
 - open 30
- solution project 12-13
- specify
 - save type 12
- SQL expression
 - test 51
- SQL files 76
- SSO 71
- start 11
- start page 23
 - open 23
- status bar 20
 - meaning of the colors 20
- Swagger 81

T

- tab 52
 - close 52
 - manage 52
 - open 52
 - save 52

- task window 60
 - display 61
 - open 61
- tasks 60
- test
 - API 64
 - compiling 58
 - database query 51
 - SQL expression 51
- text 44-47
- toolbar 19
- type member 74

U

- UI 15
- undo 23, 54
- usage
 - change label 38
- user interface 15

V

- version control 62
- Visual Studio 65