



One Identity Manager 8.1

Authorization and Authentication Guide

Copyright 2019 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC.

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.
Attn: LEGAL Dept
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our Web site (<http://www.OneIdentity.com>) for regional and international office information.

Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal. All other trademarks are the property of their respective owners.

Legend

-  **WARNING:** A WARNING icon indicates a potential for property damage, personal injury, or death.
-  **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.
-  **IMPORTANT, NOTE, TIP, MOBILE, or VIDEO:** An information icon indicates supporting information.

Contents

About this guide	7
One Identity Manager Application roles	8
Application roles overview	9
Application roles for basic functions	10
Compliance & Security Officer	11
Auditors	12
Application roles for identity audit	12
Application roles for company policies	14
Application roles for attestation	15
Application roles for subscribable reports	16
Management level	17
Application roles for business roles	17
Application roles for organizations	18
Application roles for employees	19
Application roles for the IT Shop	20
Application roles for target systems	21
Application roles for Universal Cloud Interface	23
Application roles for custom tasks	24
Implementing the application roles	25
Creating and editing application roles	25
Master data of application roles	26
Assigning employees to application roles	28
Customized extension of application role edit permissions	28
Additional tasks for managing application roles	29
Creating dynamic roles for application roles	29
Specifying mutually exclusive application roles	30
Assigning subscribable reports to application roles	31
Assigning extended properties to application roles	32
Generating assignment resources for application roles	32
Reports about application roles	32
Granting One Identity Manager schema permissions	34

Predefined permissions groups and system users	35
Rules for determining the valid permissions for tables and columns	38
Processing permissions groups	40
Permissions groups properties	41
Permissions group dependencies	42
Editing the dependencies of permissions groups	43
Copying permissions groups	44
Creating permissions groups	45
Editing system users	45
Creating system users	46
System users' passwords	47
System user properties	48
Adding system users to permission groups	49
Which employees use the system user?	50
Deleting dynamic system users	50
Editing table permissions and column permissions	51
Displaying the permissions of a permissions group	51
Displaying permissions for tables	52
Editing table properties	53
Editing column permissions	54
Copying table permissions and column permissions	56
Simulating permissions for system users	57
Displaying permissions for objects	58
Displaying permissions for the current user	59
Assigning permissions groups to applications	60
Managing permissions to program features	61
Program functions for starting the One Identity Manager tools	61
Display program functions available to a user	63
Assigning program function to permissions groups	64
Permissions for executing scripts	64
Permissions for executing methods	65
Permissions for triggering processes	66
Modifying permissions for executing actions in the Launchpad	67
One Identity Manager Authentication modules	68

System users	68
Generic single sign-on (role-based)	69
Employee	71
Employee (role-based)	71
Employee (dynamic)	72
User account	73
User account (role-based)	74
Account-based system user	75
Active Directory user account	76
Active Directory user account (role-based)	77
Active Directory user account (manual input)	78
Active Directory user account (manual input/role-based)	79
Active Directory user account (dynamic)	80
LDAP user account (role-based)	81
LDAP user account (dynamic)	83
HTTP Header	85
HTTP Header (role-based)	86
OAuth 2.0 / OpenID Connect	87
OAuth 2.0 / OpenID Connect (role-based)	88
Synchronization authentication module	89
Web agent authentication module	90
Component authentication module	90
Crawler	91
Password reset	91
Password reset (role-based)	92
Editing authentication modules	93
Enabling authentication modules	94
Assigning authentication modules to applications	94
Disabling or enabling authentication modules for applications	94
Authentication module properties	95
Initial data for authentication modules	96
Configuration data for system user dynamic authentication	100
Example of a simple system user assignment	101
Example of a system user assignment using a selection criterion	102
Example of a function group assignment	103

Enabling the validity of a login	104
OAuth 2.0/OpenID Connect configuration	105
Expiry of the OAuth 2.0/OpenID Connect authentication	105
Creating the OAuth 2.0/OpenID Connect configuration	107
Assigning OAuth 2.0/OpenID Connect configuration to web applications	111
Displaying the configuration of the identity provider and the OAuth 2.0/OpenID Connect applications	112
Defining enabling and disabling columns for the determination of user accounts	113
Multi-factor authentication in One Identity Manager	114
Editing table properties	116
Preparing the Starling 2FA token request	116
Requesting a security code	117
About us	119
Contacting us	119
Technical support resources	119
Index	120

About this guide

You can use the One Identity Manager roles and permissions model to control the edit permissions for users of the One Identity Manager. Permissions for accessing tables and columns of the One Identity Manager schema are defined by permissions groups. Permissions groups can be linked to application roles. The users are assigned to application roles and therefore receive the permissions they require. The valid permissions for a user are determined when the user logs into One Identity Manager. One Identity Manager provides different authentication modules for the login.

The One Identity Manager Authorization and Authentication Guide describes the basics and features of the internal One Identity Manager roles and permission model.

You will find an overview of the default application roles, default permissions groups and system users of the One Identity Manager. You will learn how to get the application roles up and running. The guide also explains how you grant permissions for the tables and columns of the One Identity Manager schema. In addition, you will find an overview of the various One Identity Manager authentication modules.

This guide is intended for end users, system administrators, consultants, analysts, and any other IT professionals using the product.

NOTE: This guide describes One Identity Manager functionality available to the default user. It is possible that not all the functions described here are available to you. This depends on your system configuration and permissions.

Available documentation

You can access the One Identity Manager documentation in Manager and in Designer by selecting **Help | Search**. The online version of the One Identity Manager documentation is available in the Support-Portal under [Online-Documentation](#). You will find videos with additional information at www.YouTube.com/OneIdentity.

One Identity Manager Application roles

You can use the One Identity Manager role model to control edit permissions for One Identity Manager users. This role model takes into account technical aspects, for example, One Identity Manager tool administrative rights, as well as functional aspects, which result from One Identity Manager user tasks within the company structure (for example, permissions for approving requests). The One Identity Manager makes so-called application roles available.

Application roles have the following aims:

- Program functions, employees, company resources, approval workflows and approval policies are assigned to fixed application roles. Write permissions for these application roles do not need to be defined specifically for the company. This simplifies administration of access permissions.
- Enables audit secure internal administration of One Identity Manager users and their write permissions. Permissions can be granted through assignment, request and approval or by calculation on account of specific properties. Furthermore, issuing permissions with the attestation function is integrated into the attestation process.
- Users are provided with initial permissions, which they required for carrying out their tasks. This is a way, for example, to create initially required user accounts.

Application roles can be limited to permissions groups whose write permissions are predefined by One Identity Manager. Controlling write permissions:

- Navigation configuration in administration tools
- Access to objects and their properties
- Which interface forms and tasks are displayed
- Availability of special program functionality

Users must be role-based to use application roles for logging in to One Identity Manager. Role-based authentications module finds the valid write permissions from all the user's application roles. This provides the One Identity Manager user with permissions corresponding to their application roles for the One Identity Manager functions when they log onto One Identity Manager tools.

Detailed information about this topic

- [Application roles overview](#) on page 9
- [Implementing the application roles](#) on page 25
- [Creating and editing application roles](#) on page 25

Related Topics

- [Granting One Identity Manager schema permissions](#) on page 34
- [One Identity Manager Authentication modules](#) on page 68

Application roles overview

One Identity Manager supplies default application roles whose permissions are matched to the different task and functions. Assign employees to default applications who take on individual tasks and functions. You can also create your own application roles for custom defined tasks.

NOTE: Default application roles are defined in One Identity Manager modules and are not available until the modules are installed. You cannot delete default application roles.

The following default application roles are defined:

- [Application roles for basic functions](#)
- [Compliance & Security Officer](#)
- [Auditors](#)
- [Application roles for identity audit](#)
- [Application roles for company policies](#)
- [Application roles for attestation](#)
- [Application roles for subscribable reports](#)
- [Management level](#)
- [Application roles for business roles](#)
- [Application roles for organizations](#)
- [Application roles for employees](#)
- [Application roles for the IT Shop](#)
- [Application roles for target systems](#)
- [Application roles for Universal Cloud Interface](#)
- [Application roles for custom tasks](#)

Application roles for basic functions

NOTE: This application role is available if the Identity Management Base Module is installed.

The following application roles are available to you for the basic functionality in One Identity Manager.

Table 1: Application Roles for Basic Functions

Application role	Description
Administrators	<p>Administrators must be assigned to Base roles Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Administer application roles for administrators.• Assign employees to administrator application roles.• Can other employees Base roles Administrators and edit conflicting application roles.• See the master data for the other application roles.• Can use Password Reset Portal to set passwords for selected system users.
Everyone (change)	<p>Base roles Everyone (change) is automatically assigned to every user.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Can edit certain employee master data in the Web Portal. <p>Should every user be automatically assigned to a custom permissions group when they log in, then this permissions group can be added to the application role.</p> <p>Members of this application role are determined through a dynamic role.</p>
Everyone (lookup)	<p>Base roles Everyone (Lookup) is automatically assigned to every user.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Obtain read access to objects in the Web Portal. <p>Should every user be automatically assigned to a custom permissions group when they log in, then this permissions group can be added to the application role.</p> <p>Members of this application role are determined through a dynamic role.</p>

Application role	Description
Employee managers	<p>Base roles Employee managers is automatically assigned to a user if the user is a manager or supervisor of employees, departments, locations, cost centers, business roles, or IT Shops.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Can edit master data for the objects they are responsible for and assign company resources to them. • Can edit master data for their employees in the Web Portal. • Can add their staff members to the IT Shop. • Employee and department managers can add new employees in the Web Portal. • Can view their staff's compliance rule violations in the Web Portal. <p>Members of this application role are determined through a dynamic role.</p>
Birthright Assignments	<p>Base roles Birthright assignments is used to provide birthrights to employees which are provided to establish their working environment. The application roles are allocated all the resources marked for automatic assignment to all employees. All internal employees are assigned to this application role and obtain the resources. Internal employees are found through a dynamic role.</p>
Operations support.	<p>Employees that use the Operations Support Web Portal, must be assigned the application role Base roles Operations support.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Monitor handling of Job queue processes • Monitor handling of the DBQueue • Create access codes to enable employees to log on to Password Reset Portal

Related Topics

- [Customized extension of application role edit permissions](#) on page 28

Compliance & Security Officer

NOTE: This application role is available if Attestation Module, Compliance Rules Module or Company Policies Module is installed.

Compliance and security officers must be assigned to **Identity & Access Governance | Compliance & Security Officer**.

Users with this application role:

- View all compliance relevant information and other analysis in the Web Portal. This includes attestation policies, company policies and policy violations, compliance rules, and rule violations and risk index functions.
- Edit attestation polices.

Auditors

NOTE: This application role is available if Attestation Module, Compliance Rules Module or Company Policies Module is installed.

Auditors are assigned to the application role **Identity & Access Governance | Auditors**.

Users with this application role:

- See the Web Portal all the relevant data for an audit.

Application roles for identity audit

NOTE: This application role is available if the Compliance Rules Module is installed.

The following application roles are available for managing compliance rule:

Table 2: Application roles for identity audit

Application role	Description
Administrators	<p>Administrators must be assigned to the application role Identity & Access Governance Identity Audit Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Enter base data for for setting up company policies.• Create compliance rules and assign rule supervisors to them.• Can start rule checking and view rule violations as required.• Create reports about rule violations.• Enter mitigating controls.• Create and edit risk index functions.• Monitor Identity Audit functions.

Application role	Description
Rule supervisors	<ul style="list-style-type: none"> • Administer application roles for rule supervisors, exception approvers and attestors. • Set up other application roles as required. <p>Rule supervisors must be assigned to Identity & Access Governance Identity Audit Rule supervisors or to a child role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Are responsible for compliance rule content, for example, an auditor or a auditing department. • Edit the compliance rule working copies, which are assigned to the application role. • Enable and disable compliance rules. • Can start rule checking and view rule violations as required. • Assign mitigating controls.
Exception approvers	<p>Administrators must be assigned to Identity & Access Governance Identity Audit Exception approvers or to a child role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Edit rule violations in the Web Portal. • Can grant exception approval or revoke it in the Web Portal.
Attestors	<p>Attestors must be assigned to Identity & Access Governance Identity Audit Attestors.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Attest compliance rules and exception approvals in the Web Portal for which they are responsible. • Can view master data for these compliance rules but not edit them. <p>i NOTE: This application role is available if the module Attestation Module is installed.</p>
Maintain SAP Functions	<p>Administrators must be assigned to Identity & Access Governance Identity Audit Maintain SAP functions or to a child role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Are responsible for SAP function contents. • Edit working copies of function definitions for which they are

Application role	Description
	<p>responsible.</p> <ul style="list-style-type: none"> Define function instances and variables sets for SAP functions. Assign mitigating controls. <p>NOTE: This application role is available if the module SAP R/3 Compliance Add-on Module is installed.</p>

Application roles for company policies

NOTE: This application role is available if the Company Policies Module is installed.

The following application roles are available for managing company policies:

Table 3: Application Roles for Company Policies

Application role	Description
Administrators	<p>Administrators must be assigned to the application role Identity & Access Governance Company policies Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Enter base data for for setting up company policies. Set up policies and assign policy supervisors to them. Can calculation policies and view policy violations if required. Set up reports about policy violations. Enter mitigating controls. Create and edit risk index functions. Administer application roles for policy supervisors, exception approvers and attestors. Set up other application roles as required.
Policy supervisors	<p>Policy supervisors must be assigned to Identity & Access Governance Company policies Policy supervisors or another child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Are responsible for the contents of company policies. Edit working copies of company policies. Enable and disable company policies.

Application role	Description
	<ul style="list-style-type: none"> • Can calculation policies and view policy violations if required. • Assign mitigating controls.
Exception approvers	<p>Users with this application role:</p> <p>Exception approvers must be assigned to Identity & Access Governance Company policies Exception approvers or to a child role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Edit policy violations. • Can grant exception approval or revoke it.
Attestors	<p>Attestors must be assigned to Identity & Access Governance Company policies Attestors.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Attest company policies and exception approvals in the Web Portal for which they are responsible. • Can view the master data for these company policies but not edit them. <p>i NOTE: This application role is available if the module Attestation Module is installed.</p>

Application roles for attestation

i | **NOTE:** This application role is available if the module Attestation Module is installed.

The following application role is available for managing attestation procedures:

Table 4: Application Roles for Attestation

Application role	Description
Administrators	<p>Administrators are assigned to Identity & Access Governance Attestation Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Define attestation procedures and attestation policies. • Create approval policies and approval workflows. • Specify which approval procedure to use to find attestors.

Application role	Description
	<ul style="list-style-type: none"> • Set up attestation case notifications. • Configure attestation schedules. • Enter mitigating controls. • Create and edit risk index functions. • Monitor attestation cases.
Chief approval team	<p>The chief approver must be assigned to Identity & Access Governance Attestation Chief approval team.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Approve using attestation cases. • Assign attestation cases to other attestors.

NOTE: Attestors in charge are determined through approval procedures. Other application roles may be applied here. Application roles for attestors are defined in different module and are available if the Attestation Module is installed.

Application roles for subscribable reports

NOTE: This application role is available if the module Report Subscription Module is installed.

The following application role is available for managing subscribable reports:

Table 5: Application Roles for Subscribable Reports

Application role	Description
Administrators	<p>Administrators must be assigned to Identity & Access Governance Company policies Report Subscriptions.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Create subscribable reports from existing reports. • Configure report parameters for subscribable reports. • Assign subscribable reports to employees, company structures or IT Shop shelves. • Create custom mail templates for sending subscribed reports by email.

Management level

NOTE: This application role is available if the Identity Management Base Module is installed.

The user must be assigned to the application role **Identity Management | Management level**.

Users with this application role:

- Can view reports and statistics for management levels in the Web Portal.

Application roles for business roles

NOTE: This application role is available if the module Business Roles Module is installed.

The following application roles are available for the administration of business roles:

Table 6: Application Roles for Business Roles

Application role	Description
Administrators	<p>Administrators must be assigned to the application role Identity Management Business roles Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Create and edit business roles.• Assign company resources to business roles.• Administrate application roles for role approvers, role approvers (IT), and attestors.• Set up other application roles as required.
Attestors	<p>Attestors must be assigned to Identity Management Business roles Attestors or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Attest correct assignment of company resource to business roles for which they are responsible.• Can view master data for these business roles but not edit them. <p>NOTE: This application role is available if the module Attestation Module is installed.</p>
Role approver	<p>Approvers must be assigned to the application role Identity</p>

Application role	Description
	<p>Management Business roles Role approvers or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Are approvers for the IT Shop. • Approve requests from business roles for which they are responsible.
Role approver (IT)	<p>IT role approvers must be assigned to Identity Management Business roles Role approvers (IT) or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Are IT role approvers for the IT Shop. • Approve requests from business roles for which they are responsible.

Application roles for organizations

NOTE: This application role is available if the Identity Management Base Module is installed.

The following application roles are available for the administration of departments, cost centers and locations:

Table 7: Application Roles for Organizations

Application role	Description
Administrators	<p>Administrators must be assigned to the application role Identity Management Organizations Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Set up and edit departments, cost centers and locations. • Assign company resources to departments, cost centers and locations. • Administrate application roles for role approvers, role approvers (IT), and attestors. • Set up other application roles as required.
Attestors	<p>Attestors must be assigned to the application role Identity Management Organizations Attestors or a child application role.</p>

Application role	Description
	<p>Users with this application role:</p> <ul style="list-style-type: none"> • Attest correct assignment of company resources to departments, cost centers and locations for which they are responsible. • Can view master data for departments, cost centers and locations but cannot edit them. <p>i NOTE: This application role is available if the module Attestation Module is installed.</p>
Role approver	<p>Role approvers must be assigned to the Identity Management Organizations Role approvers application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Are approvers for the IT Shop. • Approve request from departments, cost centers, and locations for which they are responsible.
Role approver (IT)	<p>IT role approvers must be assigned to Identity Management Organizations Role approvers (IT) or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Are IT role approvers for the IT Shop. • Approve request from departments, cost centers, and locations for which they are responsible.

Application roles for employees

i | **NOTE:** This application role is available if the Identity Management Base Module is installed.

The following application role is available for employee administration:

Table 8: Application Roles for Employees

Application role	Description
Administrators	<p>Employee administrators must be assigned to the application role Identity Management Employees Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Can edit master data for all employees

Application role	Description
------------------	-------------

- Can assign a manager.
- Can assign company resources to employees.
- Check and authorize employee master data.
- Create and edit risk index functions.
- Edit password policies for employee passwords

Application roles for the IT Shop

NOTE: This application role is available if the Identity Management Base Module is installed.

The following application roles are available for the IT Shop administration:

Table 9: Application Roles for the IT Shop

Application role	Description
Administrators	<p>Administrators must be assigned to the Request & Fulfillment IT Shop Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Create the IT Shop structure with shops, shelves, customers, templates and service catalog. • Create approval policies and approval workflows. • Specify which approval procedure to use to find attestors. • Create products and service items. • Set up request notifications. • Monitor request procedures. • Administrate application roles for product owners and attestors. • Set up other application roles as required. • Create extended properties for company resources of any type. • Edit the resources and assign them to IT Shop structures and employees. • Assign system entitlements to IT Shop structures.
Product owners	<p>Product owners must be assigned to the Request & Fulfillment IT Shop Product owner application role or a child application role.</p>

Application role	Description
	<p>Users with this application role:</p> <ul style="list-style-type: none"> • Approve through requests. • Edit service items and service categories under their management.
Attestors	<p>Attestors must be assigned to the Request & Fulfillment IT Shop Attestors application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Attest correct assignment of company resource to IT Shop structures for which they are responsible. • Can view master data for these IT Shop structures but not edit them. <p>i NOTE: This application role is available if the module Attestation Module is installed.</p>
Chief approval team	<p>Chief approvers must be assigned to the Request & Fulfillment IT Shop Chief approval team application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Approve through requests. • Assign requests to other approvers. <p>i NOTE: Approvers in charge are determined through approval procedures. Other application roles may be applied here. Application roles for approvers are defined in different modules and are available there.</p>

Application roles for target systems

i **NOTE:** Application roles are dependent on the target system and are contained in One Identity Manager modules. Application roles are not available until the modules are installed.

The following application roles are available for target system administration:

Table 10: Application Roles for Target Systems

Users	Task
Target system administrators	Target system administrators must be assigned to the Target systems Administrators application role.

Users	Task
	<p>Users with this application role:</p> <ul style="list-style-type: none"> • Administrate application roles for individual target systems types. • Specify the target system manager. • Set up other application roles for target system managers if required. • Specify which application roles are conflicting for target system managers • Authorize other employee to be target system administrators. • Do not assume any administrative tasks within the target system.
<p>Target system managers</p>	<p>Target system managers must be assigned to the application role Target systems <target system> or a sub application role.</p> <p>i NOTE: There is at least one application role per target system for target system managers. This application role is available if the target system module is installed.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Assume administrative tasks for the target system. • Create, change or delete target system objects, like user accounts or groups. • Edit password policies for the target system. • Prepare system entitlements for adding to the IT Shop. • Can create employees with an identity that differs from the Primary identity. • Configure synchronization in the Synchronization Editor and defines the mapping for comparing target systems and One Identity Manager. • Edit the synchronization's target system types and outstanding objects. • Authorize other employees within their area of responsibility as target system managers and create child application roles if required.
<p>Target system managers for Unified Namespace</p>	<p>Target system managers must be assigned to the Target systems Unified Namespace application role or a child role.</p>

Users**Task**

Users with this application role:

- Obtain view of the objects in the connected target systems across all target systems.
- Can create reports across all target systems.

If the users are also target system managers of the basic underlying target systems, you can manage these target systems through the Unified Namespace.

Application roles for Universal Cloud Interface

NOTE: Application roles are available if the Universal Cloud Interface Module is installed.

The following application roles are available for managing cloud systems.

Table 11: Application Roles for the Universal Cloud Interface

Users	Task
Cloud administrators	<p>Administrators must be assigned to the Universal Cloud Interface Administrators application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Manage application roles for the Universal Cloud Interface. • Set up other application roles as required. • Configure synchronization in the Synchronization Editor and define the mapping for comparing tcloud applications and One Identity Manager. • Edit cloud application in the Manager. • Edit pending, manual provisioning processes in the Web Portal and obtain statistics. • Obtain information about the cloud objects in the Web Portal and the Manager.
Cloud operators	<p>Operators must be assigned to the Universal Cloud Interface Operators application role or a child application role.</p> <p>Users with this application role:</p>

Users	Task
	<ul style="list-style-type: none"> Edit pending, manual provisioning processes in the Web Portal and obtain statistics.
Cloud auditors	<p>Auditors must be assigned to the Universal Cloud Interface Auditors application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Can view manual provisioning processes in the Web Portal and obtain statistics.

Application roles for custom tasks

NOTE: This application role is available if the Identity Management Base Module is installed.

The following application roles are available for customer features and tasks.

Table 12: Application Roles for Custom Tasks

Application role	Description
Administrators	<p>Administrators must be assigned to Custom Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Administrate custom application roles. Set up other application roles for managers if required.
Manager/supervisor	<p>Managers must be assigned to Custom Managers or a subordinate role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Add custom task in One Identity Manager. Configure and start synchronization in the Synchronization Editor. Edit the synchronization's target system types as well as outstanding objects in the Manager.

You can use these application roles, for example, to guarantee One Identity Manager users write permissions on custom tables or columns. All application roles that you define here must obtain their write permissions through custom permissions groups.

Implementing the application roles

- ❶ **IMPORTANT:** To use application roles you must add one employee to the application role **Base roles | Administrators**. This employee is the authorized to assigned administrative One Identity Manager application roles to other employees.

Run this task once.

*To initially add an employee to the application role **Base roles | Administrators***

1. Log into the Manager as a non role-based administrative user.
2. Select the **Employees | Employees**.
3. Select the employee to be assigned to the application role **Base role | Administrators**.
4. Select the **Authorize as One Identity Manager administrator** task.

- ❶ **NOTE:** Once you update the view in Manager, the **Authorize as One Identity Manager administrator** task is no longer displayed in the task view. That means that the task can only be run when there are no other employees assigned to this application role.

After you have been working with One Identity Manager for a while, it is possible that no more employees are assigned to the **Base roles | Administrators** application role. In this case, proceed as described above in order to reassign an employee to this application role.

The One Identity Manager user with the application role **Base roles | Administrators** can now add more employees to application roles and edit the application role master data.

Related Topics

- [Assigning employees to application roles](#) on page 28
- [Creating and editing application roles](#) on page 25

Creating and editing application roles

To set up your first application roles you need to add an employee to the application role **Base roles | Administrators**. This employee is authorized to add more employees to different administration application roles. For more information, see [Implementing the application roles](#) on page 25.


Administrators can edit child application roles, set up more application roles and assigned employees.

- ❶ **NOTE:** To edit the application role, log on to the Manager using a role-based authentication module.

To edit an application role

1. In Manager in the **One Identity Manager Administration** category, select the Application role.
2. Select **Change master data**.
3. Edit the application role's master data.
4. Save the changes.

To create a new application role

1. In the Manager in the **One Identity Manager Administration** category, select the application role under which you want to create a new application role.
2. Click  in the result list toolbar.
3. Enter the application role master data.
4. Save the changes.

 **NOTE:** You cannot delete default application roles.

Related Topics

- [Master data of application roles](#) on page 26
- [Assigning employees to application roles](#) on page 28
- [Customized extension of application role edit permissions](#) on page 28
- [One Identity Manager Authentication modules](#) on page 68

Master data of application roles

Table 13: Application Role Properties

Property	Meaning
Application role	Application role name.
Internal name	Empty text field for a internal company identifier
Full name	Full name of application role. Is made up automatically from the application role name and the parent application role.
Parent application role	Application role to which the application role being edited is subordinate.
Department, location,	Additional information for the application role definition. These input fields are only used for information. They do not indicate for which department,

Property	Meaning
cost center	cost center or location the application roles are responsible.
Permissions group	<p>Permissions group for determining write permissions on role-based login. The application role is given access permissions of the associated permissions group. If there is no permissions group assigned, the application role gets write permissions from the parent application role.</p> <p>Administrators can assign the rest of the application roles to custom defined permissions groups. For more information, see Customized extension of application role edit permissions on page 28.</p> <p>i NOTE: Permissions groups for default administrator application roles for cannot be edited.</p>
Description	Spare text box for additional explanation.
Comment	Spare text box for additional explanation.
Certification status	<p>Status of the application role's certification. The following values can be selected.</p> <ul style="list-style-type: none"> • New: The application role was newly created in the One Identity Manager database. • Certified: The master data of the application role is approved by a manager. • Denied: The application role master data was not approved by a manager.
Block inheritance	<p>i NOTE: This option available on compatibility grounds with older versions of the program. It is recommended that you set this option.</p> <p>Specifies whether employees from parent application roles can also be determined as approvers for requests in the IT Shop that use the approval methods RD, RL, RO or RP. If this option is set, only employee that are assigned to exactly this application can be determined as approvers.</p> <p>For detailed information about the approval procedure in IT Shop, see the <i>One Identity Manager IT Shop Administration Guide</i>.</p>
Dynamic roles not allowed	Specifies whether a dynamic role can be created for the application role.
Spare field no. 01 ... Spare field no. 10	Additional company specific information. Use Designer to customize display names, formats and templates for the input fields.

Assigning employees to application roles

Assigned employees obtain all the write permissions of the permission group to which the application role (or a parent application role) is assigned. In addition, employees obtain the company resources assigned to the application role.

Employees of the parent application role are inherited if no employees are directly assigned to an application role.


- NOTE:** The application roles for **Base roles | Everyone (Change)**, **Base roles | Everyone (Lookup)**, **Base roles | Employee Managers** and **Base roles | Birth-right Assignments** are automatically assigned to employees. Do not make any manually assignments to these application roles.

To assign employees to an application role

1. In Manager in the **One Identity Manager Administration** category, select the Application role.
2. Select **Assign employees** in the task view.
3. Assign employees in **Add assignments**.

- TIP:** In the **Remove assignments** area, you can remove the assignment of employees.

To remove an assignment

- Select the employee and double click .
4. Save the changes.

Related Topics

- [Creating dynamic roles for application roles](#) on page 29

Customized extension of application role edit permissions

For role-based login, the application roles require a link to a permissions group in which write permissions for One Identity Manager are defined. The application role is given access permissions of the associated permissions group. If there is no permissions group assigned, the application role gets write permissions from the parent application role.

Some of the default application roles are already assigned permissions groups. These permissions groups have the edit permissions for the tables and columns and are equipped with menu items, forms, tasks and program functions, which allow the application data to be edited in Manager and in Web Portal.

You can assign customized permissions groups to application roles so that the write permissions for application roles meet your company requirements. You need to ensure

that your custom permissions groups contain all the write permissions of the default permissions groups for these application roles. This allows users with these application roles to use all default One Identity Manager functionality.

- ① **NOTE:** You can simplify grouping of permissions by using hierarchical linking of permissions groups. Permissions from hierarchical permissions groups are inherited from top to bottom. That means that a permissions group contains all the permissions belonging parent permissions groups.

Proceed as follows:

1. Create a new permissions group in the Designer.
 - ① **NOTE:** Set the **Only use for role-based authentication** option for the permissions group.
2. In Designer, make the new permissions group dependent on the default permissions group of the application role. Assign the default permissions group as a parent permissions group. As a result, the newly defined permissions group inherits the properties of the default permissions group.
3. In Designer, grant additional edit permissions for menu items, forms, tables or columns.
4. In Manager, assign the new permissions group to the application role.

A user who logs in to the Manager or to the Web Portal with an application role changed in this way receives – in addition to the default privileges of this application role – the custom edit permissions.

Related Topics

- [Master data of application roles](#) on page 26
- [Granting One Identity Manager schema permissions](#) on page 34

Additional tasks for managing application roles

After you have entered the master data, you can apply different tasks to it. The task view contains different forms with which you can run the following tasks.

Creating dynamic roles for application roles

Use this task to assign employees to an application role through dynamic roles. For detailed information about using dynamic roles, see the *One Identity Manager Identity Management Base Module Administration Guide*.

- NOTE:** The task **Create dynamic role** is only available for application roles, which do not have the option **Dynamic roles not allowed** set.

To create a dynamic role for the application role

1. In Manager in the **One Identity Manager Administration** category, select the Application role.
2. Select **Create dynamic role** in the task view.
3. Enter the required master data. The following applies to dynamic roles for application roles:
 - **Object class:** Select **Employee**.
 - **Application role:** This data is preset with the selected application role. If these objects fulfill the dynamic role conditions, they become members in the application role.
 - **Dynamic role:** The dynamic role name is made up of the object class and the full name of the application role by default.
4. Save the changes.

To edit a dynamic role

1. In Manager in the **One Identity Manager Administration** category, select the Application role.
2. Select **Application role overview** in the task view.
3. In the overview form, click the dynamic role name in the **Dynamic roles** form element.
4. Select **Change master data**.
5. Edit the dynamic role.
6. Save the changes.

Related Topics

- [Master data of application roles](#) on page 26

Specifying mutually exclusive application roles

It is possible that employees cannot own certain system roles at the same time. Thus, for example, exception approvers for rule violations may not be rule supervisors at the same time. To implement this behavior, you can specify mutually exclusive application roles. Then you cannot assign these application roles to the same person anymore.

- NOTE:** Only system roles, which are defined directly as conflicting application roles cannot be assigned to the same employee. Definitions made on parent or child application roles do not effect the assignment.

To configure inheritance exclusion

- In Designer, enable the **QER | Structures | ExcludeStructures** configuration parameter and compile the database.

To specify inheritance exclusion for application roles

1. In Manager in the **One Identity Manager Administration** category, select the application role for which you want to define an inheritance exclusion.
2. Select **Edit conflicting application roles** in the task view.
3. Assign the application roles that are mutually exclusive to the selected application role in **Add assignments**.
 - OR -
 - Remove the application roles that are no longer mutually exclusive in the **Remove assignments** area.
4. Save the changes.

Assigning subscribable reports to application roles

Use this task to assign subscribable reports to an application role. All employee in this application role can subscribe to reports in the Web Portal. For detailed information about subscribable reports, see the *One Identity Manager Report Subscriptions Administration Guide*.

i NOTE:

- This function is only available if the Report Subscription Module is installed.
- The task is only available if a permissions group is assigned to the application role (or a parent application role).
- Subscribable reports cannot be assigned to the application roles **Base roles | Employee Managers**, **Base roles | Everyone (Lookup)** and **Base roles | Everyone (Change)**.

1. In Manager in the **One Identity Manager Administration** category, select the Application role.
2. Select **Assign subscribable reports** in the task view.
3. Assign reports in **Add assignments**.
 - OR -
 - In the **Remove assignments** area, remove the reports.
4. Save the changes.

Assigning extended properties to application roles


Extended properties are meta objects that cannot be mapped directly in One Identity Manager, for example, operating codes, cost codes or cost accounting areas. For detailed information about using extended properties, see the *One Identity Manager Identity Management Base Module Administration Guide*.

To specify extended properties for an application role

1. In Manager in the **One Identity Manager Administration** category, select the Application role.
2. Select **Assign extended properties** in the task view.
3. Assign extended properties in **Add assignments**.

TIP: In the **Remove assignments** area, you can remove the assignment of extended properties.

To remove an assignment

- Select the extended property and double click .
4. Save the changes.

Generating assignment resources for application roles

It is possible to create assignment resources for individual application roles. This means you can limit assignment resources to individual application roles in the Web Portal. When the assignment resource is requested, it is no longer necessary to select the application role as well. The application role is automatically a part of the assignment request. For detailed information about assignment requests, see the *One Identity Manager IT Shop Administration Guide*.

To limit an assignment resource to one application role

1. In Manager in the **One Identity Manager Administration** category, select the Application role.
2. Select the **Create assignment resource** task.
This starts a wizard, which takes you through adding an assignment resource.

Reports about application roles

One Identity Manager makes various reports available containing information about the selected base object and its relations to other One Identity Manager database objects. The following reports are available for application roles.

Table 14: Reports about Application Roles

Report	Description
Overview of all assignments	This report identifies all departments, cost centers, locations, business roles or IT Shop structures in which employees from the selected application role are also members. For detailed information about analyzing role memberships, see the <i>One Identity Manager Identity Management Base Module Administration Guide</i> .
Show historical memberships	This report lists all members of the selected application role and the length of their membership.

Granting One Identity Manager schema permissions

Permissions for accessing tables and columns of the One Identity Manager schema are themselves mapped in the schema through permissions groups. You can assign permissions groups to system users and to application roles.

The user's effective permissions depend on the authentication module used for logging into One Identity Manager tools.

- The permissions assigned to the system user are found from the permissions groups for logging into One Identity Manager tools with an authentication module that expects a defined system user.
- Dynamic system users are used for logging into One Identity Manager tools with role-based authentication modules. First, the employee memberships in the One Identity Manager application roles are determined during login. Assignments of permissions group to One Identity Manager application roles are used to determine which permissions groups apply to the employee. A dynamic system user is determined from these permissions groups that will be used for the employee's login.

The system user's effective permissions that are found are not saved in the One Identity Manager schema, but are determined when logging into One Identity Manager tools and then they are loaded.

Permissions groups are also used to control access to parts of the user interface, such as, menu items, forms, tasks and program functions. When a user logs into the One Identity Manager tools, menus, forms and methods are loaded depending on the system user's permissions groups, displaying a user interface customized for this system user. For more detailed information about editing the user interface, see the *One Identity Manager Configuration Guide*.

The One Identity Manager provides permissions groups and system users with a predefined user interface and edit permissions to the One Identity Manager schema's tables and columns. These predefined configurations are maintained by the schema installation and cannot be edited apart from a few properties.

Detailed information about this topic

- [Predefined permissions groups and system users](#) on page 35
- [Rules for determining the valid permissions for tables and columns](#) on page 38
- [Processing permissions groups](#) on page 40
- [Editing system users](#) on page 45
- [Editing table permissions and column permissions](#) on page 51
- [Managing permissions to program features](#) on page 61
- [Displaying permissions for objects](#) on page 58
- [Displaying permissions for the current user](#) on page 59
- [Assigning permissions groups to applications](#) on page 60

Related Topics

- [One Identity Manager Application roles](#) on page 8
- [One Identity Manager Authentication modules](#) on page 68

Predefined permissions groups and system users

The One Identity Manager provides permissions groups and system users with a predefined user interface and special edit permissions to the One Identity Manager schema's tables and columns. These predefined configurations are maintained by the schema installation and cannot be edited apart from a few properties.

Table 15: Predefined Permissions Groups

Permissions group	Description
Permissions group QBM_BaseRights	The QBM_BaseRights permissions group defines the base rights that are required for a system user to log in to the administration tools. This permissions group is always assigned implicitly.
Permission group VID_Features	The VID_Features permissions group covers all program functions required for starting the One Identity Manager tools. The permissions group covers additional program functions for executing special functions in the One Identity Manager
Permissions group VI_View	The VI_View permissions group has viewing permissions for all tables and columns of the One Identity Manager application data model.

Permissions group	Description
	<p>NOTE: Assign viewing permissions of custom schema extensions to the permissions group.</p>
Permissions group VI_Everyone	<p>The VI_Everyone permissions group is assigned to form elements of the overview forms that use links to the corresponding menu items. These permissions groups also provide functions for Web Portal users.</p> <p>NOTE: Assign the permissions group to your custom system users such that the overview form is fully displayed to the users.</p>
Permissions groups for the One Identity Manager application data model	<p>Permissions groups have edit permissions for One Identity Manager application data model tables and columns. These permissions groups are equipped with menu items, forms, tasks and program functions which allows the application data to be edited with the Manager.</p>
Permissions groups for the One Identity Manager system data model	<p>These permissions groups have permissions for the One Identity Manager system data model tables and columns. These permissions groups are equipped with menu items, forms, tasks and program functionality which allows the application data to be edited, for example, with Designer editors.</p> <p>The vid permissions group has all edit permissions for the system configuration with the Designer.</p>
Role-based permissions group VI_4_ALLUSER	<p>The VI_4_ALLUSER permissions group provides the base rights as well as menu items, forms, task and program functions to enable the application data to be edited with the Manager and the Web Portal. This permissions group is always assigned implicitly.</p>
Role-based permissions group vi_4_ADMIN_LOOKUP	<p>The vi_4_ADMIN_LOOKUP permissions group has the viewing permissions for all tables and columns of the One Identity Manager application data model.</p> <p>NOTE: Assign viewing permissions of custom schema extensions to the permissions group. Assign viewing permissions of the module's own tables and columns to the permissions group.</p>
Role-based permissions group QER_OperationsSupport	<p>The QER_OperationsSupport permissions group has special permissions for working with the Operations Support Web Portal. The permissions group is assigned to the OperationsSupportWebPortal application. The permissions of the permissions group apply only in the Operations Support Web Portal.</p>

Permissions group Description

Role-based permissions groups	Role-based permissions groups have edit permissions for One Identity Manager application data model tables and columns. These permissions groups are equipped with menu items, forms, tasks and program functionality which allow the application data to be edited with the Manager and Web Portal. These permissions groups are linked to the One Identity Manager application roles and simplify administration of access permissions in the One Identity Manager role model.
-------------------------------	--

Table 16: Predefined system users

System user	Description
Dynamic system user	Dynamic system users are used for logging into One Identity Manager tools with role-based authentication modules. First, the employee memberships in the One Identity Manager application roles are determined during login. Assignments of permissions group to One Identity Manager application roles are used to determine which permissions groups apply to the employee. A dynamic system user is determined from these permissions groups that will be used for the employee's login.
System user sa	The sa system user is used exclusively by the One Identity Manager Service. This system user is not allocated a permissions groups but has all access permissions, tasks and program functionality.
System user viadmin	<p>The viadmin system user is the default system user in One Identity Manager. This system user can be used to compile and initialize the One Identity Manager database and for the first user login to the administration tools.</p> <p>IMPORTANT: Do not use the viadmin system user in a live environment. Create your own system user with the appropriate permissions.</p> <p>The system user has all of the specified permissions and the complete user interface. The system user implicitly receives the authorizations and user interface parts of the custom permissions groups. The system user has the permission to set up an employee as a One Identity Manager administrator for the role-based login. The system user is not a member of the application role themselves.</p>
System user Synchronization	The Synchronization system user has the necessary permissions to set up and run target system synchronizations using an application server.
System user viHelpdesk	The viHelpdesk system user has the necessary permissions and the user interface to use the Manager to access the helpdesk resources of the One Identity Manager.

System user	Description
System user viITShop	The viITShop system user has the necessary permissions and the user interface to use the Manager to access the IT Shop.

Related Topics

- [Deleting dynamic system users](#) on page 50
- [Permissions group dependencies](#) on page 42
- [Processing permissions groups](#) on page 40

Rules for determining the valid permissions for tables and columns

When a system user is used to log into the system, the currently effective permissions for the objects are determined based on the permissions groups. The following rules are used to determine the resulting permissions:

- Permissions from hierarchical permissions groups are inherited from top to bottom. That means that a permissions group contains all the permissions belonging parent permissions groups.
- The number of objects is determined first for hierarchical permissions groups. Column permissions are decided afterwards. In some cases, this results in more permissions than are defined on individual permissions groups.
- A system user receives a permission when at least one of its permissions groups has the permission (directly or inherited).
- The limiting permissions conditions for all the system user's permissions groups are grouped together and used to determine a valid condition for each permission for viewing, editing, inserting and deleting an object.
- Fixed viewing permissions for the database system files are granted by the system, which are sufficient for logging a system user into One Identity Manager tools.
- A system user with read-only permissions only obtains viewing permissions to objects irrespective of any other permissions.
- If permissions are granted on a table for inserting, editing or deleting, viewing permissions are implicit.
- If permissions are granted on a column for inserting, editing or deleting, viewing permissions are implicit.
- If permissions are granted for a table, then viewing permissions are implicitly granted on the primary key column of the table.
- If viewing permissions are granted on a primary key column as a minimum, then viewing permissions are implicitly granted for references table, the primary key

column and the columns that are necessary on the referenced table for viewing according to the defined display pattern.

- Permissions for database views of the **Proxy** type also apply to the underlying tables.
- For database views of the **ReadOnly** type, only the viewing permissions apply irrespective of other permissions.
- If a table or column is disabled due to preprocessor conditions, permissions are not determined for those tables and columns. The table or column is considered not to exist.
- If a permissions group is disabled due to preprocessor conditions, permissions are not taken into account for this permissions group. The permissions group is considered not to exist.

Example of Permissions Grouping using Permissions Groups

The following example shows how to group permissions if the user is directly assigned in permissions groups and the permissions groups are not connected hierarchically.

A system user obtains permissions to the table ADSAccount through different permissions groups.

Permissions group	Viewable	Editable	Insertable	Deletable
A	1	1	1	1
B	0	0	0	0

In addition, it is granted permissions to the table LDAPAccount through these permissions groups.

Permissions group	Viewable	Editable	Insertable	Deletable
A	1	0	0	0
B	1	1	1	0

Therefore, the system user has effectively the following permissions:

Table	Viewable	Editable	Insertable	Deletable
ADSAccount	1	1	1	1
LDAPAccount	1	1	1	0

Example of Limiting Conditions

A system user obtains viewing permissions to the table Person through different permissions groups:

Permissions group	Viewing Condition	Column Viewing Permissions
A		Lastname
B	Lastname like 'B%'	Lastname, Firstname, Entrydate
C	Lastname like 'Be%'	Lastname, Firstname, Gender
D	Lastname like 'D%'	Lastname

This results in the following permissions for the individual employee objects.

Person.Lastname	Visible Columns
Smith	Lastname
Bishop	Lastname, Firstname, Entrydate
Bennett	Lastname, Firstname, Gender
Dummy	Lastname

Processing permissions groups

The One Identity Manager provides permissions groups with a predefined user interface and special edit permissions for the One Identity Manager schema's tables and columns. In certain isolated cases, it may be necessary to define custom permissions groups. You need custom permissions groups, for example, if:

- The default permissions groups grant too many permissions,
- Selected default permissions groups are to be summarized to form a new permissions group,
- Additional role-based permissions groups are required for the custom application roles,
- Permissions for custom adjustments such as schema extensions, forms or menu structures.

When the One Identity Manager database is installed using the Configuration Wizard, custom permissions groups that you can use are already created.

- For non-role-based login, the permission groups **CCCViewPermissions** and **CCCEditPermissions** are created. Administrative system users are automatically added to these permissions groups.
- For-role-based login, the permission groups **CCCViewRole** and **CCCEditRole** are created.

Permissions groups are managed in Designer in the **Permissions | Permissions groups** category. Here you will find an overview of edit permissions and user interface

components that are assigned to individual permissions groups. In addition, the system users are displayed, which the permissions groups are assigned.

Use User & Permissions Group Editor to create and edit permissions groups in Designer. User & Permissions Group Editor displays the permissions groups in their hierarchy. Each permissions group is represented by a permissions group element. Each permissions group element has a tooltip. The contents of the tooltip is made up of the name and description of the permissions group.

You can run the following tasks:

- Editing the master data of a permissions group
- Defining new permissions group dependencies
- Copying Permissions Groups
- Creating a new permissions group

Related Topics

- [Predefined permissions groups and system users](#) on page 35
- [Permissions groups properties](#) on page 41
- [Editing the dependencies of permissions groups](#) on page 43
- [Copying permissions groups](#) on page 44
- [Creating permissions groups](#) on page 45
- [Managing permissions to program features](#) on page 61

Permissions groups properties

Table 17: Permissions Group Properties

Property	Description
Permissions group	Name of the permissions group. Label custom permission groups with the prefix CCC .
Description	Detailed description of the permissions group's purpose.
Remarks	Spare text box for additional explanation.
Preprocessor condition	You can add a preprocessor condition to permissions groups. This means that the permissions group is only effective when the condition is met.
Permissions group binary pattern	The permissions group binary pattern is used to calculate effective system user permissions. It is provided by the DBQueue Processor.
Only use for role-based authentication	This group includes permissions, form assignments, menu items and program functions for role-based authentication. The permissions group

Property	Description
	<p>can be assigned to One Identity Manager application roles and is assigned to dynamically determined system users. A direct assignment to non-dynamic system user is not permitted.</p> <p>NOTE: This function is available if the Identity Management Base Module is installed.</p>

Related Topics

- [Copying permissions groups](#) on page 44
- [Creating permissions groups](#) on page 45

Permissions group dependencies

You can enable permissions and user interface components to be passed on from one permissions group to other permissions groups by structuring permissions groups hierarchically. This means that inheritance is top down within the hierarchy.

The following applies to permissions group dependencies:

- A role-based permissions group can inherit from role-based permissions groups and non role-based permissions groups.
- A non-role-based permissions group can inherit from non-role-based permissions groups. A non-role-based permissions group must not inherit from role-based permissions groups.

Example

Two permissions groups are defined with the following permissions and user interface components.

Permissions group	Permissions	User interface
A	Viewing permissions	Menu structures and forms
B	Edit permissions	Task definitions

Permissions group B is arranged below permissions group A in the hierarchy and inherits from permissions group A. Consequently, a user of permissions group B has access to the viewing permissions and editing permissions as well as the menu structure, forms and task definitions.

Related Topics

- [Editing the dependencies of permissions groups](#) on page 43

Editing the dependencies of permissions groups

You edit dependencies between permissions groups in the hierarchical view of the User & Permissions Group Editor. Permissions groups that are higher up in the hierarchy are displayed further to the right in the hierarchical view of User & Permissions Group Editor. When a permissions group is selected in the hierarchical view, the dependencies to other permissions groups are marked in color which also is also used to show the direction of inheritance.

Figure 1: Diagram of Permissions Group Hierarchy (Direction of Inheritance from Right to Left)



Table 18: Meaning of Colors in the Hierarchical Representation

Color	Meaning
Blue	The selected permissions group.
Purple	This permissions group is a child of the selected permissions group and directly inherits from the selected permissions group.
Light purple	This permissions group inherits indirectly from the selected permissions group over the hierarchy.
Red	This permissions group is a parent of the selected permissions group and passes inheritance to the selected permissions group.
Light red	This permissions group passes inheritance indirectly to the selected permissions group over the hierarchy.
Green	This permissions group does not inherit or pass inheritance to the selected permissions group.

To specify dependencies of a permissions group

1. Select the **Permissions | Permissions groups** category in Designer.
2. Select the permissions group and start User & Permissions Group Editor using the **Edit permissions group** task.
3. In the hierarchical view of the permissions groups, select the permissions group and run one of the following actions.

- Select the **Inherit permissions from** context menu and select the permissions groups from which the selected permissions group is to inherit.
- Select the **Permissions inherited by** context menu and select the permissions groups to be included in the selected permissions group. Permissions subgroups inherit permissions from the selected permissions group.

Copying permissions groups

The User & Permissions Group Editor provides a wizard for copying edit permissions and the user interface of an existing permissions group to a new permissions group.

To copy a permissions group

1. Select the **Permissions | Permissions groups** category in Designer.
2. Select the permissions group you want to copy and start the User & Permissions Group Editor with the task **Edit permissions group**.
3. Select the **Permissions groups | Copy permissions group** menu.
4. On the home page of the wizard for copying permissions groups, click **Next**.
5. On the **Select permissions group** page, enter the following information:
 - **Select permissions group to copy:** The permissions group is pre-selected.
 - **Copy name:** Name of the new permissions group. A name suggestion is already entered in the field which is made up from the customer prefix and the original permissions group name. You can alter this name but the customer prefix has to remain.
6. On the **Select copy options** page, specify which permissions group relations are to be copied. You can select multiple options. The following copy options are available.

Table 19: Copy options for permissions groups

Option	Description
Permissions	Enable this option to copy the table permissions and column permissions of the selected permissions group to the new permissions group.
User interface	Enable this option to copy the menu items, the forms and the task definitions of the selected permissions group to the new permissions group.
System user	Select this option if the system user should be copied to the new permissions group.

NOTE: Note here that predefined system users are not included in the new permissions group.

7. To start compiling, click **Next**.
The copying process may take some time.
8. The **Copy permissions group** page shows the individual copy steps and any error messages. If the copy action is complete, click **Next**.
9. To end the wizard, click **Finish** on the last page.

Related Topics

- [Creating permissions groups](#) on page 45
- [Permissions groups properties](#) on page 41
- [Editing the dependencies of permissions groups](#) on page 43
- [Adding system users to permission groups](#) on page 49
- [Editing table permissions and column permissions](#) on page 51

Creating permissions groups

To create a permissions group

1. In the Designer, select the **Permissions** category.
2. Start the User & Permissions Group Editor with the task **Show / edit permissions group**.
3. Add a new permissions group using the **Permissions groups | New** menu.
4. Edit the master data for the permissions group.
5. Save the changes.

Related Topics

- [Copying permissions groups](#) on page 44
- [Permissions groups properties](#) on page 41
- [Editing the dependencies of permissions groups](#) on page 43
- [Adding system users to permission groups](#) on page 49

Editing system users

One Identity Manager provides various system users whose permissions are matched to the different tasks. Create your own system users if required. Add the system users to permissions groups, thereby granting the system users permissions for the tables and columns of the One Identity Manager data model, and make the user interface available.

The system user's effective permissions that are found are not saved in the One Identity Manager schema, but are determined when logging into One Identity Manager tools and then they are loaded.

When installing the One Identity Manager database using the Configuration Wizard, create an administrative system user that is added to non-role-based permissions groups and receives all permissions of the **viadmin** default system user.

System users are shown in Designer in the **Permissions | System users** category. You will see an overview of the permissions groups that are assigned to each individual system user. Use the User & Permissions Group Editor to create and edit your system user in Designer.

You can run the following tasks:

- Create a new system user, such as an administrative system user or a system user for service accounts
- Configuration of password settings for system users
- Adding a system user to permissions groups
- Determining which employees use a system user

NOTE: You cannot edit dynamic system users.

Related Topics

- [Predefined permissions groups and system users](#) on page 35
- [Creating system users](#) on page 46
- [System users' passwords](#) on page 47
- [System user properties](#) on page 48
- [Adding system users to permission groups](#) on page 49
- [Which employees use the system user?](#) on page 50
- [Deleting dynamic system users](#) on page 50

Creating system users

To create a new system user

1. In the Designer, select the **Permissions** category.
2. Start the User & Permissions Group Editor with the task **Show / edit permissions group**.
3. Add a new system user using the **User | New** menu.
4. Edit the system user's master data.
5. Add the system user to permissions groups.
6. Save the changes.

- NOTE:** You can create an administrative system user in User & Permissions Group Editor using the **Create administrator** menu. Administrative system users are automatically added to all non role-based permissions groups.

Related Topics

- [Predefined permissions groups and system users](#) on page 35
- [System users' passwords](#) on page 47
- [System user properties](#) on page 48
- [Adding system users to permission groups](#) on page 49
- [Deleting dynamic system users](#) on page 50
- [Which employees use the system user?](#) on page 50
- [One Identity Manager Authentication modules](#) on page 68

System users' passwords

The **One Identity Manager password policy** is used for logins on the One Identity Manager with a system user. This password policy defined the settings for the system user passwords (`DialogUser.Password` and `Person.DialogUserPassword`) as well as the access code for a one off log in on the Web Portal (`Person.Passcode`).

If necessary, adjust the password policy to your requirements in Designer. For detailed information about editing password policies, see *One Identity Manager Operational Guide*.

- NOTE:** The **One Identity Manager password policy** is marked as the default policy. This password policy is applied if no other password policy can be found for employees, user accounts or system users.


To prevent passwords expiring for service accounts, for example, you can enable the **Password never expires** (`DialogUser.PasswordNeverExpires`) option in Designer for the respective system users.

Related Topics

- [System user properties](#) on page 48

System user properties

Table 20: Properties of a system user

Property	Description
System user	Name of the system user for logging in to the administration tools.
Password and password confirmation	Password with which the system logs into the administration tools.
Password last changed	Date of last password change.
Password never expires	Specifies whether the password expires. Enable the option for service accounts, for example, to prevent the password from expiring. This option overwrites the maximum age of the password.
Remarks	Spare text box for additional explanation.
Read-only	Set the option if a system user is a member of all permissions groups, but should only have viewing permissions for the objects. This results in overwriting all other edit permissions that the system user obtains through permissions group memberships.
Logins	Logins with which the system user can log in to the One Identity Manager tools. Enter the login in the form: Domain\User. This information is required if the Account based system user authentication module is used to log into the One Identity Manager tools.
administrative user	Specifies whether this is an administrative system user. Administrative system users are automatically added to all non role-based permissions groups.  NOTE: You can create an administrative system user in User & Permissions Group Editor using the Create administrator menu.
Service account	Specifies whether this is a system user that is used by a service account. This system user is not allocated a permissions groups but has all access permissions, tasks and program functionality.
External password management	Specifies whether the system user password is determined by an external password management system. You cannot change the password in One Identity Manager. The determination of the system user password must be customized.

Related Topics

- [System users' passwords](#) on page 47

Adding system users to permission groups

Add the system user to permissions groups, thereby granting the system user permissions for the tables and columns of the One Identity Manager data model and make the user interface available.

NOTE:

- You cannot add system users to role-based permissions groups. Dynamic system users are calculated for role-based login.
- Administrative system users are automatically added to all non role-based permissions groups.
- The **QBM_BaseRights** permissions group defines the base permissions that are required for a system user to log in to the administration tools. This permissions group is always assigned implicitly.
- The **viadmin** system user has all of the specified permissions and the complete user interface. The system user implicitly receives the authorizations and user interface parts of the custom permissions groups.

A system user's memberships of permissions groups are presented in User & Permissions Group Editor. Use the **Options | Display permissions group inheritance** menu to specify whether to display the direct and inherited memberships of permissions groups for system users.

Figure 2: System User Permissions Group Memberships




Table 21: Meaning of Icons in the Hierarchical Display

Icon	Meaning
	The selected system user is not assigned to this permissions group.
	The selected system user is assigned to this permissions group.
	The selected system user is indirectly assigned to this permissions group.
	The selected system user is directly and indirectly assigned to this permissions group.

To assign a system user to a permissions group

1. In Designer, select the **Permissions | System user** category.
2. Select a system user and start the User & Permissions Group Editor with the **Edit system user** task.

3. Select the required permissions group in the hierarchical view. By clicking on the icon you add or delete the selected system user to or from a permissions group.

TIP: To assign a system user to several permissions groups, use the **User | Permissions groups** menu.

Related Topics

- [Deleting dynamic system users](#) on page 50

Which employees use the system user?

Employees obtain a system user directly from their master data or dynamically through their One Identity Manager application roles.

To display which employees are assigned to a system user

1. In Designer, select **Permissions | System users**.
2. Select a system user and start the User & Permissions Group Editor with the **Edit system user** task.
3. Select **View | One Identity Manager employees**.

NOTE: You cannot change the assignments in this view.

Deleting dynamic system users

NOTE: If no role-based logins of employees who use dynamic system users are performed for some time, you should delete the dynamic system users for performance reasons. A new dynamic system user is created during the next role-based employee login.

To delete system users

- In Designer, enable the **Common | DynamicUserLifetime** configuration parameter and enter the maximum retention period in days for dynamic system users.

If the configuration parameter is enabled, system users whose retention period has expired are deleted from the database as part of the daily maintenance tasks.

Editing table permissions and column permissions

You can edit permissions in the Designer using the Permissions Editor. You can also simulate the permissions for the individual system users in Permissions Editor.

With the Permissions Editor you can:

- Assign permissions for custom tables and columns to custom permissions groups
- Assign permissions for predefined tables and columns in the One Identity Manager schema to custom permissions groups
- Assign permissions for custom tables and columns to predefined permissions groups

The permissions for predefined permission groups to predefined tables and columns in the One Identity Manager schema cannot be changed.

For custom schema extensions, use the Schema Extension program, specify a permissions group with read and write permissions as well as a permissions group with read permissions only. This make initial access to the schema extensions possible with One Identity Manager administration tools.

Detailed information about this topic

- [Rules for determining the valid permissions for tables and columns](#) on page 38
- [Displaying the permissions of a permissions group](#) on page 51
- [Displaying permissions for tables](#) on page 52
- [Editing table properties](#) on page 53
- [Editing column permissions](#) on page 54
- [Copying table permissions and column permissions](#) on page 56
- [Simulating permissions for system users](#) on page 57

Displaying the permissions of a permissions group

To display all permissions for a permission group

1. In the Designer, select the **Permissions** category.
2. Start the Permissions Editor using the **Edit permissions** task.
3. In the Permissions Editor toolbar in the **Permissions group** menu, select the permissions group for which you want to display permissions.

The tables and columns of the One Identity Manager schema and the permissions of the selected permissions group are displayed in the upper area of Permissions Editor. Use the following Permissions Editor options to adjust the layout.

- To display tables with permissions first, enable the **Options | Permissions** sort order menu.
- To display disabled tables and columns, enable the **Options | Show disabled tables** menu.
- To use the display names of the tables and columns, enable the **Options | Display name** menu.
- To limit the display of the tables, use the **Show system tables**, **Show non-system tables** and **Show all tables** menu items in the **Options** menu. Alternatively, use the **Define filter** or **Manage filters** menu items to define your own user-defined filters for displaying the tables and columns.

For detailed information about creating user-defined filters in Designer, see the *One Identity Manager User Guide for One Identity Manager Tools User Interface*.

Displaying permissions for tables

In the **Summary of all permissions** view in Permissions Editor, the permissions groups that have permissions for a table or column are displayed. The permissions in this view cannot be edited.

- NOTE:** To display the **Summary of all permissions** view, go to Permissions Editor and enable **View | Object permissions**. The view is displayed in the lower area of Permissions Editor.

To display all permissions for a table and its columns

1. In Designer in the **Permissions | By tables** category, select the table.
2. Start the Permissions Editor using the **Edit permissions for table** task.

The **Summary of all permissions** view displays the permissions groups that have permissions for the selected table.

- TIP:** To display a permissions filter completely, click a condition in the view.

3. (Optional) To display all permissions for a column, open the table entry in the upper area of Permissions Editor and select a column.

The **Summary of all permissions** view displays the permissions groups that have permissions for the selected column.

Editing table properties

Use the table permissions to grant the permissions to display, insert, edit and delete the objects. You can define conditions to further limit the permissions for the objects. You can use the conditions, for example, to link the editability of the employees to their last names. For instance, a user can be given read access only to the employees whose last names begin with A-F, whereas he/she can edit employees with last names beginning with G-Z.

NOTE: The permissions are always edited in Permissions Editor for the permissions group that you selected in the Permissions Editor toolbar in the **Permissions group** menu. If you wish to grant permissions for another permissions group, first select this permissions group in the menu and then edit the permissions.

To edit the permissions for a table for a permissions group

1. In the Designer, select the **Permissions** category.
2. Start the Permissions Editor using the **Edit permissions** task.
3. In the Permissions Editor toolbar in the **Permissions group** menu, select the permissions group for which you want to grant the permissions.
4. Select the table at the top of the Permissions Editor.
 - TIP:** Use **Shift + select** or **Ctrl + select** to select multiple tables.
5. Edit the permissions for the permissions group in the **Permissions** area.
 - To insert new permissions, select the **New** context menu and enable the associated check boxes. You can grant the following permissions.

Table 22: Table permissions

Permissions	Meaning
Viewable	The table data is displayed.
Insertable	New data can be added to the table.
Editable	Table data can be edited.
Deletable	Table data can be deleted.

NOTE: If you grant the **Insertable**, **Editable** or **Deletable** permissions, the **Viewable** permission is also granted.

- To withdraw a permission, disable the associated checkbox.
 - To withdraw all permissions for a table, use the **Delete**.
6. (Optional) To specify other conditions for table permissions, go to the lower part of the Permissions Editor and change to the **Group permissions for table** and view and select the **Permissions filter**.

- i **NOTE:** You can only define permissions filters for the tables of the application data model.
- Enter the conditions as valid WHERE clauses for database queries. You can enter the following permissions filters.

Table 23: Permissions filter

Permissions filter	Meaning
Viewing Condition	Limiting condition for displaying data sets.
Edit condition	Limiting condition for editing data sets.
Insert condition	Limiting condition for inserting data sets.
Deletion condition	Limiting condition for deleting data sets.

Example for permissions filters

A user should be able to see all employees, but only edit the employees whose last names begin with B. Specify the limiting edit condition as follows, for example:

```
Lastname like 'B%'
```

- i **TIP:** Use the **SQL check** button to test the condition. This checks the syntax. The number of objects that match the condition is returned.

Related Topics

- [Editing column permissions on page 54](#)
- [Copying table permissions and column permissions on page 56](#)

Editing column permissions

i IMPORTANT:

- If you grant permissions to columns, you must also grant the permissions to the tables. For example, a column is only viewable if the table is also viewable.
- To insert objects into a table, the **Insert** permissions is required for at least the required fields in the table.
- NOTE:** If you grant the **Insert** or **Edit** permissions, the **View** permission is also granted.

- NOTE:** The permissions are always edited in Permissions Editor for the permissions group that you selected in the Permissions Editor toolbar in the **Permissions group** menu. If you wish to grant permissions for another permissions group, first select this permissions group in the menu and then edit the permissions.

To modify the permissions for a column for a permissions group

1. In the Designer, select the **Permissions** category.
2. Start the Permissions Editor using the **Edit permissions** task.
3. In the Permissions Editor toolbar in the **Permissions group** menu, select the permissions group for which you want to grant the permissions.
4. Select the table at the top of the Permissions Editor and select the column.
 - TIP:** Use **Shift + select** or **Ctrl + select** to select multiple columns.
5. Edit the permissions for the permissions group in the **Permissions** area.
 - To insert new permissions, select the **New** context menu and enable the associated check boxes. You can grant the following permissions.

Table 24: Column permissions

Permissions	Meaning
Viewable	The column is displayed.
Editable	The values in the columns can be changed
Insertable	The value in the column can be edited when a new data record. Once the data record has been saved it can no longer be edited. For example, when an Active Directory User is created, an Active Directory Container is defined. Because this is a key field the Active Directory Container cannot be changed after the object has been saved.

- To withdraw a permission, disable the associated checkbox.
- To withdraw all permissions for a column, use the **Delete** context menu.

Related Topics

- [Editing table properties](#) on page 53
- [Copying table permissions and column permissions](#) on page 56

Copying table permissions and column permissions

To transfer the permissions of a permissions group quickly from one table to another table, you can copy the table permissions and column permissions. Two methods are provided in the Permissions Editor to do this:

- **Copy** and **Insert**: This methods copies the permissions of the source table (source column) to a permissions group. The permissions are copied for the permissions group that you selected in the Permissions Editor toolbar in the **Permissions group** menu.

All copied permissions are inserted for the target table (target column). Any existing rights for the target table (target column) remain unaffected.

- **Copy all permissions** and **Paste all permissions**: This method copies all source table (source column) permissions. The initial selection of the permissions group in Permissions Editor makes no difference here. All permissions from all permissions groups for the source table (source column) are applied.

All copied permissions are inserted for the target table (target column). Existing permissions for target table (target column) that do not exist for the source table (source column) are removed from the target table (target column).

To copy the permissions of a permissions group

1. In the Designer, select the **Permissions** category.
2. Start the Permissions Editor using the **Edit permissions** task.
3. In the Permissions Editor toolbar in the **Permissions group** menu, select the permissions group for which you want to grant the permissions.
4. To transfer the table permissions.
 - a. Select the table at the top of the Permissions Editor from which you want to transfer the permissions.
 - b. Use the **Copy** context menu to copy the permissions to the buffer.
 - c. Select the table at the top of the Permissions Editor for which you want to transfer the permissions.
 - d. Use the **Insert** context menu to insert the permissions.
 - e. If necessary, repeat step c) and d) for other tables.
5. To transfer the column permissions
 - a. Select the table at the top of the Permissions Editor and select the column from which you want to transfer permissions.
 - b. Use the **Copy** context menu to copy the permissions.
 - c. Select the table at the top of the Permissions Editor and select the column for which you want to copy permissions.

- d. Use the **Insert** context menu to insert the permissions.
- e. If necessary, repeat step c) and d) for other columns.

Related Topics

- [Editing table properties](#) on page 53
- [Editing column permissions](#) on page 54

Simulating permissions for system users

By simulating the permissions in Permissions Editor, you can see which permissions a system user has based on his or her permissions group. You can specify which permissions groups of a system user to include in the simulation. The result displayed shows which of the selected permissions groups has which table permissions and column permissions. Effective permissions for the system user are also displayed.

i **NOTE:** Simulation mode remains active until you end it. In simulation mode, you can edit permissions group permissions and update simulation data.

To run a permissions simulation

1. In the Designer, select the **Permissions** category.
2. Start the Permissions Editor using the **Edit permissions** task.
3. From the **Simulation | Start simulation** menu, start the simulation wizard.
4. On the start page of the wizard, click **Next**.
5. On the **Simulation base configuration** page, select the following data.
 - **User:** Select the system user whose permissions you want to simulate.
 - **Direct groups:** Use this button to select all permissions groups that are directly assigned to the system user.
 - **All groups:** Use this button to select all permissions groups that are directly assigned to the system user as well as all permissions groups that the system user inherits indirectly.
 - **Permissions groups:** Select individual permissions groups directly. Use **Ctrl + select** to select multiple tables.
6. On the **Simulation configuration** page, specify the tables for which the permissions are simulated.
 - In the **Selected tables** area, all tables of the One Identity Manager schema are selected. If necessary, limit the selection to individual tables. Click **None** to undo the selection. Use **Shift + select** to select individual tables.
 - Using the **Context table** menu, you can specify a table from whose view implicit permissions to the display values of the foreign key columns are

assigned.

Example:

For the `Employee` table, viewing permissions to the `UID_Org` column have been assigned. As a result, viewing permissions are implicitly assigned for columns of the `Org` table, which are used as a display template, for example, `Org.Ident_Org`.

To simulate this example, select the **Employee table** under `Context table` and the **Org table** under `Selected tables`.

7. The processing progress of the simulation is displayed on the **Simulation** page. The simulation process can take some time.

8. To end the wizard, click **Finish** on the last page.

After you complete simulation wizard, the system user's effective table permissions and column permissions are displayed in the upper area of the Permissions Editor in the **Simulation** area.

9. To determine which table permission or column permission results from which of the system user's permissions groups, select the table or column in the upper area of the Permissions Editor.

The permissions and permissions groups are displayed in the **Permissions simulation** view in the lower area of Permissions Editor.

10. To end the simulation mode, select the **Simulation | End simulation** menu.

The simulation data is deleted and the **Permissions simulation** view is closed.

Displaying permissions for objects

You can display object properties and permissions in the One Identity Manager tools.



To show extended object properties

- Select the object and open the **Properties** context menu.

On **General**, you can see the object's general properties, for example, ID, status, or primary key.

All the object columns are displayed in a grid on **Properties** with their values. You can choose between a simple column view and the advanced view with additional data for column definitions.

Table 25: Icon used for Column Properties

Icon	Meaning
	Required field.
	No viewing permissions.

Icon	Meaning
	No edit permissions.

On **Access permissions**, you can see which permissions are valid for an object based on permissions groups. The first entry shows the basic permissions for the table. The permissions for this particular object are displayed beneath that. The other entries show the column permissions.

TIP: Double-click the table entry, the object entry, or a column entry to display the permissions group from which the permissions were determined.

Table 26: Icon used for permissions

Icon	Meaning
✓	Permissions exist.
•	Permissions have been removed by the object layer.
☑	Permissions limited by conditions.

Displaying permissions for the current user

To get more information about the current user

- To display additional user information, double-click the  icon in the status bar

Table 27: Extra Information about the Current User

Property	Meaning
System user	Name of system user
Authenticated by	Name of the authentication module used for logging in.
Employee UID (UserUID)	Unique ID for the current user's employee if an employee related authentication module is used to log in.
Read-only	The system user has only has read permissions. Modification to data are not possible.
Dynamic user	The current user uses a dynamic system user. Dynamic system users are applied when a role-based authentication module is used.

Property	Meaning
Remarks	More details about the system user in use.
Permissions groups	Permissions groups that are assigned to the system user. Which user interface and editing permissions apply depend on the permissions groups.
Program functions	Program functions assigned to the system user. The menu items and functions available depend on the program functions.

Assigning permissions groups to applications

If you assign a permissions group to an application, the permissions of the group apply only to this application. When a user logs on to the application, they receive the permissions of the permissions group in addition to their own permissions.

To assign a permissions group to an application

1. Select the **Permissions | Permissions groups | Role based permissions groups** category in Designer.
2. Select the **View | Select table relations** menu item and enable the `DialogGroupInProductLimited` table.
3. In the List Editor, select the permissions group.
4. Assign the application in the **Applications** edit view.

For detailed information about applications in One Identity Manager, see the *One Identity Manager Configuration Guide*.

Managing permissions to program features

Program functions are part of the permission model in One Identity Manager. They allow you to enable and disable features. Program functions are not assigned to single users but to permissions groups. The set of program functions defined for a user is determined by his or her permissions groups and their program functions.

The One Identity Manager tools can only be started if the user has the relevant program function permissions. Furthermore, some functions in the One Identity Manager tools are available only if the program functions are assigned to the current user. This includes data export from the Manager, calling the SQL Editor in the Designer or showing DBQueue Processor information in all programs, as examples.

Detailed information about this topic

- [Program functions for starting the One Identity Manager tools](#) on page 61
- [Displaying permissions for the current user](#) on page 59
- [Assigning program function to permissions groups](#) on page 64
- [Permissions for executing scripts](#) on page 64
- [Permissions for executing methods](#) on page 65
- [Permissions for triggering processes](#) on page 66
- [Modifying permissions for executing actions in the Launchpad](#) on page 67

Program functions for starting the One Identity Manager tools

The One Identity Manager tools can only be started if the user has the relevant program function permissions. The following program functions allow the One Identity Manager tools to be started.

To make the program function available to users

- In the Designer under **Permissions | Program functions**, check which permissions group contains the required program function and assign the program functions to other permissions groups as necessary.
- For non-role-based logins: Add the system user to the permissions group in the Designer under **Permissions | System users**.
- For role-based logins: Ensure that the user is assigned to the application role that contains the program function.

Table 28: Program functions for starting the One Identity Manager tools

Program function	Description
ApplicationStart_Analyzer	Allows the program Analyzer (Analyzer.exe) to be started.
ApplicationStart_ApiDesigner	Allows the program API Designer (ApiDesigner.exe) to be started.
ApplicationStart_ConfigWizard	Allows the program Configuration Wizard (ConfigWizard.exe) to be started.
ApplicationStart_CryptoConfig	Allows the program Crypto Configuration (CryptoConfig.exe) to be started.
ApplicationStart_DataImporter	Allows the program Data Import (DataImporter.exe) to be started.
ApplicationStart_DBClone	Allows the program (DBCClone.exe) to be started.
ApplicationStart_DBComparer	Allows the program (DBComparer.exe) to be started.
ApplicationStart_DBCompiler	Allows the program Database Compiler (DBCompiler.exe) to be started.
ApplicationStart_Designer	Allows the program Designer (Designer.exe) to be started.
ApplicationStart_JobQueueInfo	Allows the program Job Queue Info (JobQueueInfo.exe) to be started.
ApplicationStart_LaunchPad	Allows the program Launchpad (LaunchPad.exe) to be started.
ApplicationStart_LicenseMeter	Allows the program License Meter (LicenseMeter.exe) to be started.
ApplicationStart_Manager	Allows the program Manager (Manager.exe) to be started.
ApplicationStart_ObjectBrowser	Allows the program Object Browser (ObjectBrowser.exe) to be started.
ApplicationStart_OpSupport	Enables start-up of the Operations Support Web Portal.
ApplicationStart_	Allows the program Report Editor (ReportEdit2.exe) to be


Program function	Description
ReportEdit	started.
ApplicationStart_SchemaExtension	Allows the program Schema Extension (SchemaExtension.exe) to be started.
ApplicationStart_ServerInstaller	Allows the program Server Installer (ServerInstaller.exe) to be started.
ApplicationStart_SoftwareLoader	Allows the program Software Loader (SoftwareLoader.exe) to be started.
ApplicationStart_SynchronizationEditor	Allows the program Synchronization Editor (SynchronizationEditor.exe) to be started.
ApplicationStart_SystemDebugger	Allows the program System Debugging (SystemDebugger.exe) to be started.
ApplicationStart_Transporter	Allows the program Database Transporter (Transporter.exe) to be started.
ApplicationStart_WebDesignerCompiler	Allows the program (VI.WebDesigner.CompilerCmd.exe) to be started.
ApplicationStart_WebConfig	Allows the program Web Designer Configuration Editor (WebConfigEditor.exe) to be started.
ApplicationStart_WebDesigner	Allows the program Web Designer (WebDesigner.exe) to be started.
ApplicationStart_WebDesignerInstall	Allows the program Web Installer (WebDesigner.Installer.exe) to be started.

Related Topics

- [Assigning program function to permissions groups](#) on page 64
- [Adding system users to permission groups](#) on page 49
- [Assigning employees to application roles](#) on page 28

Display program functions available to a user

To identify the program functions available to the current user:

- To display user information, double-click the icon in the program status bar 

The **Program functions** tab shows the program functions that are available.

Assigning program function to permissions groups

To assign a program function to a permissions group

1. Select **Permissions | Program functions** in Designer.
2. Select the **View | Select table relations** menu item and enable the DialogGroupHasFeature table.
3. Select the program function in the List Editor.
4. Assign the Permissions groups in the **Permissions groups** edit view.
5. Save the changes.

Related Topics

- [Adding system users to permission groups](#) on page 49

Permissions for executing scripts

The basic permissions for executing scripts are granted to the logged in user via the program feature **Allow the starting of arbitrary scripts from the frontend** (Common_StartScripts).

If a script also uses a program function (table QBMScriptHasFeature), the user can only run this script if the necessary program function is granted to him. An error occurs if the user does not own this program function and tries to run it.

To control execution of a script using a program function

1. Create a new program function.
 - a. Select **Permissions | Program functions** in Designer.
 - b. Select **Object | New**.
 - c. Enter the following information:
 - **Program function:** Name of the program function.
 - **Description:** Short description of the program function.
 - **Function group:** Property for grouping program functions.
2. Connect the program function with the scripts that the user will trigger.
 - a. Select **Permissions | Program functions** in Designer.
 - b. Select the **View | Select table relations** menu item and enable the QBMScriptHasFeature table.

- c. Select the newly created program function in List Editor.
 - d. Assign the scripts in the **Scripts** edit view.
3. Assign the required program functions to the custom permissions group whose systems users will trigger these scripts.
 - a. Select **Permissions | Program functions** in Designer.
 - b. Select the **View | Select table relations** menu item and enable the DialogGroupHasFeature table.
 - c. Select your newly created program function in List Editor.
 - d. In the List Editor, use **Ctrl+Selection** to select your newly created program function and the function **Allow the starting of arbitrary scripts from the frontend** (Common_StartScripts).
 - e. Assign the permissions group in the **Permissions groups** edit view.

Related Topics

- [Processing permissions groups](#) on page 40

Permissions for executing methods

If a task definition is assigned a program function (QBMethodHasFeature), users can only execute this task if they are also assigned the necessary program function. An error occurs if the user does not own this program function and tries to run it. Program functions are not assigned to single users but to permissions groups. All users that are assigned to these groups can use the program function.

To make a task definition available to users using a program function

1. Create a new program function.
 - a. Select **Permissions | Program functions** in Designer.
 - b. Select **Object | New**.
 - c. Enter the following information:
 - **Program function:** Name of the program function.
 - **Description:** Short description of the program function.
 - **Function group:** Property for grouping program functions.
2. Connect the program function with the task definition events that the user will trigger.
 - a. Select **Permissions | Program functions** in Designer.
 - b. Select the **View | Select table relations** menu item and enable the QBMethodHasFeature table.

- c. Select the newly created program function in List Editor.
 - d. In the **Tasks** edit view, assign the task definitions.
3. Assign the required program functions to the custom permissions group whose systems users will trigger these tasks.
 - a. Select **Permissions | Program functions** in Designer.
 - b. Select the **View | Select table relations** menu item and enable the DialogGroupHasFeature table.
 - c. Select your newly created program function in List Editor.
 - d. Assign the permissions group in the **Permissions groups** edit view.

Related Topics

- [Processing permissions groups](#) on page 40

Permissions for triggering processes

The basic permissions for triggering processes are granted to the logged in user via the programm feature **Allow to trigger any events from the frontend** (Common_TriggerEvents).

In One Identity Manager, the triggering of events on stored processes is linked to the permissions concept. Users can only trigger events on objects like this if they own edit permissions for them. This can lead to table users who only have viewing permissions not being able to trigger additional events for processes.

In this case, it is possible to connect the object events (QBMEvent table) with a program function (QBMFeature table). An event (JobEventGen table), which is defined for a process, is linked with an object event (JobEventGen.UID_QBMEvent column). If the object event is assigned a program function (QBMEventHasFeature table), users that own this program function can trigger the associated object event and therefore the process, depending on their permissions.

To control triggering a process through a program function

1. Create a new program function.
 - a. Select **Permissions | Program functions** in Designer.
 - b. Select **Object | New**.
 - c. Enter the following information:
 - **Program function:** Name of the program function.
 - **Description:** Short description of the program function.
 - **Function group:** Property for grouping program functions.
2. Connect the program function with object events that the user will trigger.

- a. Select **Permissions | Program functions** in Designer.
 - b. Select the **View | Select table relations** menu item and enable the QBMEventHasFeature table.
 - c. Select the newly created program function in List Editor.
 - d. Assign the object events in the **Object events** edit view.
3. Assign the required program functions to the custom permissions group whose systems users will trigger these events.
 - a. Select **Permissions | Program functions** in Designer.
 - b. Select the **View | Select table relations** menu item and enable the DialogGroupHasFeature table.
 - c. In List Editor, use **Ctrl+Selection** to select your newly created program function and the function **Allow to trigger any events from the frontend** (Common_TriggerEvents).
 - d. Assign the permissions group in the **Permissions groups** edit view.

Related Topics

- [Processing permissions groups](#) on page 40

Modifying permissions for executing actions in the Launchpad

One Identity Manager supplies a number of Launchpad actions that you can use to start applications via the Launchpad. You can also start your own applications over the Launchpad.

If some actions in the Launchpad should not be made available to all users, you can manage the permissions by assigning Launchpad to program functions (table QBMLaunchActionHasFeature). Only tasks containing actions that the user's program function permissions permit him to run are shown in the Launchpad.

To assign a program function to Launchpad actions

1. Select **Permissions | Program functions** in Designer.
2. Select the **View | Select table relations** menu item and enable the QBMLaunchActionHasFeature table.
3. Select the program function in the List Editor.
4. Assign the actions in the **Actions** edit view.
5. Save the changes.

One Identity Manager Authentication modules

One Identity Manager uses different authentication modules for logging in to administration tools. Authentication modules identify the system users to be used and load the user interface and database resource editing permissions depending on their permission group memberships.

Before you can use an authentication module for logging on, the following prerequisites must be fulfilled:

1. The authentication module must be enabled.
2. The authentication module must be assigned to the application.
3. The assignment of the authentication module to the application must be enabled.

This allows you to log in to the assigned application using this authentication module. Ensure that users found through the authentication module also have the required program function to use the program.

- ❶ **NOTE:** After the initial schema installation, only the **System user** and **Component authenticator** authentication modules and the role-based authentication modules are enabled in One Identity Manager.
- ❶ **NOTE:** Authentication modules are defined in the One Identity Manager modules and are not available until the modules are installed.

System users

Credentials	The system user's identifier and password.
Prerequisites	<ul style="list-style-type: none"> • The system user with permissions exists in the One Identity Manager database.
Set as default	Yes

Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	No
Remarks	The user interface and the write permissions are loaded through the system user. Data modifications are attributed to the system user.

IMPORTANT: The **viadmin** system user is available by default. The system user has the predefined user interface and access permissions to database resources. The user interface and the permissions structure for the system user must not be used or changed in the production system because this system user is overwritten as a template user with each schema update.

TIP: Create your own system user with the appropriate permissions. This can be done on initial installation of the One Identity Manager database. This system user can compile an initial One Identity Manager database and can be used to log into the administration tools for the first time.

Generic single sign-on (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials	The authentication module uses the login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none"> The employee exists in the One Identity Manager database. The employee is assigned at least one application role. The user account exists in the One Identity Manager database and the employee is entered in the user account's master data.
Set as default	No
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	Yes

Remarks

One Identity Manager searches for the user account according to the configuration and finds the employee assigned to the user account.

If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If the parameter is not set, the employee's subidentity is used for authentication.

A dynamic system user determined from the employee's application roles. The user interface and the write permissions are loaded through this system user.

Changes to the data are assigned to the logged in employee.

Modify the following configuration parameters in the Designer to implement the authentication module.

Table 29: Configuration Parameters for the Authentication Module

Configuration parameter	Meaning
QER Person GenericAuthenticator	This configuration parameter specifies whether authentication through single sign-on is supported.
QER Person GenericAuthenticator SearchTable	This configuration parameter contains the table in the One Identity Manager schema in which user information is stored. The table must contain a foreign key with the name UID_Person, which points to the table Person. Example: ADSAccount
QER Person GenericAuthenticator SearchColumn	This configuration parameter contains the column from the One Identity Manager table (SearchTable), which is used to search for user name of the current user. Example: CN
QER Person GenericAuthenticator EnabledBy	This configuration parameter contains a pipe () delimited list of Boolean columns from the One Identity Manager table (SearchTable), which enables the user account for login.
QER Person GenericAuthenticator DisabledBy	This configuration parameter contains a pipe () delimited list of Boolean columns from the One Identity Manager table (SearchTable), which disables the user account for login. Example: AccountDisabled

Employee

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials	Employee's central user account and password.
Prerequisites	<ul style="list-style-type: none">• The system user with permissions exists in the One Identity Manager database.• The employee exists in the One Identity Manager database.• The central user account is entered in the employee's master data.• The system user is entered in the employee's master data.• The system user password is entered in the employee's master data.
Set as default	Yes
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none">• If this configuration parameter is set, the employee's main identity is used for authentication.• If the parameter is not set, the employee's subidentity is used for authentication. <p>The user interface and the write permissions are loaded through the system user that is directly assigned to the logged in employee.</p> <p>Changes to the data are assigned to the logged in employee.</p>

Employee (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials	Employee's central user account and password.
Prerequisites	<ul style="list-style-type: none"> • The employee exists in the One Identity Manager database. • The central user account is entered in the employee's master data. • The system user password is entered in the employee's master data. • The employee is assigned at least one application role.
Set as default	Yes
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> • If this configuration parameter is set, the employee's main identity is used for authentication. • If the parameter is not set, the employee's subidentity is used for authentication. <p>A dynamic system user determined from the employee's application roles. The user interface and the write permissions are loaded through this system user.</p> <p>Changes to the data are assigned to the logged in employee.</p>

Employee (dynamic)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials	Employee's central user account and password.
Prerequisites	<ul style="list-style-type: none"> • The employee exists in the One Identity Manager database. • The central user account is entered in the employee's master data. • The system user password is entered in the employee's master data. • The configuration data for dynamically determining the system user is defined in the application. Thus, an employee can, for example, be

assigned a system user dynamically depending on their department membership.

Set as default Yes

Single sign-on No

Front-end login allowed Yes

Web Portal login allowed Yes

Remarks If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If the parameter is not set, the employee's subidentity is used for authentication.

The application configuration data is used to determine a system user, which is automatically assigned to the employee. The user interface and write permissions are loaded through the system user that is dynamically assigned to the logged in employee.

Changes to the data are assigned to the logged in employee.

Related Topics

- [Configuration data for system user dynamic authentication](#) on page 100

User account

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials The authentication module uses the Active Directory login data of the user currently logged in on the workstation.

- Prerequisites
- The system user with permissions exists in the One Identity Manager database.
 - The employee exists in the One Identity Manager database.
 - Permitted logins are entered in the employee's master data. The logins

are expected in the form: domain\user.

- The system user is entered in the employee's master data.

Set as default No

Single sign-on Yes

Front-end login allowed Yes

Web Portal login allowed Yes

Remarks All employee logins saved in the One Identity Manager database are found. The employee whose login data matches that of the current user is used for logging in.

If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If the parameter is not set, the employee's subidentity is used for authentication.

The user interface and access permissions are loaded through the system user that is directly assigned to the employee found.

Data modifications are attributed to the current user account.

User account (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials The authentication module uses the Active Directory login data of the user currently logged in on the workstation.

Prerequisites

- The employee exists in the One Identity Manager database.
- Permitted logins are entered in the employee's master data. The logins are expected in the form: domain\user.
- The employee is assigned at least one application role.

Set as default No

Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>All employee logins saved in the One Identity Manager database are found. The employee whose login data matches that of the current user is used for logging in.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> • If this configuration parameter is set, the employee's main identity is used for authentication. • If the parameter is not set, the employee's subidentity is used for authentication. <p>A dynamic system user determined from the employee's application roles. The user interface and the write permissions are loaded through this system user.</p> <p>Data modifications are attributed to the current user account.</p>

Account-based system user

Credentials	The authentication module uses the Active Directory login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none"> • The system user with permissions exists in the One Identity Manager database. • Permitted logins are entered in the system user's master data. The logins are expected in the form: <code>domain\user</code>.
Set as default	No
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	No
Remarks	All system user logins saved in the One Identity Manager database are

found. The system user whose login data matches that of the current user is used for logging in.

The user interface and the write permissions are loaded through the system user.

Data modifications are attributed to the current user account.

Active Directory user account

NOTE: This authentication module is available if the module Active Directory Module is installed.

Credentials	The authentication module uses the Active Directory login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none">• The system user with permissions exists in the One Identity Manager database.• The employee exists in the One Identity Manager database.• The system user is entered in the employee's master data.• The Active Directory user account exists in the One Identity Manager database and the employee is entered in the user account's master data.
Set as default	Yes
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>The appropriate user account is found in the One Identity Manager database through the user's SID and the domain given at login. One Identity Manager determines which employee is assigned to the user account.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none">• If this configuration parameter is set, the employee's main identity is used for authentication.• If the parameter is not set, the employee's subidentity is used for

authentication.

The user interface and access permissions are loaded through the system user that is directly assigned to the employee found. If a system user is not assigned to the employee, the system user from the **SysConfig | Logon | DefaultUser** configuration parameter is used.

Data modifications are attributed to the current user account.

NOTE: If the option **Connect automatically** is set, authentication is no longer necessary for subsequent logins.

Active Directory user account (role-based)

NOTE: This authentication module is available if the module Active Directory Module is installed.

Credentials	The authentication module uses the Active Directory login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The employee is assigned at least one application role.• The Active Directory user account exists in the One Identity Manager database and the employee is entered in the user account's master data.
Set as default	Yes
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>The appropriate user account is found in the One Identity Manager database through the user's SID and the domain given at login. One Identity Manager determines which employee is assigned to the user account.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p>

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If the parameter is not set, the employee's subidentity is used for authentication.

A dynamic system user determined from the employee's application roles. The user interface and the write permissions are loaded through this system user.

Data modifications are attributed to the current user account.

NOTE: If the option **Connect automatically** is set, authentication is no longer necessary for subsequent logins.

Active Directory user account (manual input)

NOTE: This authentication module is available if the module Active Directory Module is installed.

Credentials Login name and password for registering with Active Directory. You do not have to enter the domain.

Prerequisites

- The employee exists in the One Identity Manager database.
- The Active Directory user account exists in the One Identity Manager database and the employee is entered in the user account's master data.
- The permitted domains for login are entered in the **TargetSystem | ADS | AuthenticationDomains** configuration parameter.
- The configuration data for dynamically determining the system user is defined in the application. Thus, an employee can, for example, be assigned a system user dynamically depending on their department membership.

Set as default No

Single sign-on No

Front-end login allowed Yes

Web Portal login allowed Yes

Remarks The user's identity is determined from a predefined list of permitted Active Directory domains. The corresponding user account and employee are determined in the One Identity Manager database, which the user account is assigned to.

If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If the parameter is not set, the employee's subidentity is used for authentication.

The application configuration data is used to determine a system user, which is automatically assigned to the employee. The user interface and write permissions are loaded through the system user that is dynamically assigned to the logged in employee.

Data modifications are attributed to the current user account.

Active Directory user account (manual input/role-based)

NOTE: This authentication module is available if the module Active Directory Module is installed.

Credentials	Login name and password for registering with Active Directory. You do not have to enter the domain.
Prerequisites	<ul style="list-style-type: none"> • The employee exists in the One Identity Manager database. • The employee is assigned at least one application role. • The Active Directory user account exists in the One Identity Manager database and the employee is entered in the user account's master data. • The permitted domains for login are entered in the TargetSystem ADS AuthenticationDomains configuration parameter.
Set as default	Yes
Single sign-on	No
Front-end login allowed	Yes

Web Portal login allowed	Yes
Remarks	<p>The user's identity is determined from a predefined list of permitted Active Directory domains. The corresponding user account and employee are determined in the One Identity Manager database, which the user account is assigned to.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> • If this configuration parameter is set, the employee's main identity is used for authentication. • If the parameter is not set, the employee's subidentity is used for authentication. <p>A dynamic system user determined from the employee's application roles. The user interface and the write permissions are loaded through this system user.</p> <p>Data modifications are attributed to the current user account.</p>

Active Directory user account (dynamic)

NOTE: This authentication module is available if the module Active Directory Module is installed.

Credentials	The authentication module uses the Active Directory login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none"> • The employee exists in the One Identity Manager database. • The Active Directory user account exists in the One Identity Manager database and the employee is entered in the user account's master data. • The configuration data for dynamically determining the system user is defined in the application. Thus, an employee can, for example, be assigned a system user dynamically depending on their department membership.
Set as default	No
Single sign-on	Yes
Front-end login allowed	Yes

Web Portal login allowed Yes

Remarks The appropriate user account is found in the One Identity Manager database through the user's SID and the domain given at login. One Identity Manager determines which employee is assigned to the user account.

If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If the parameter is not set, the employee's subidentity is used for authentication.

The application configuration data is used to determine a system user, which is automatically assigned to the employee. The user interface and write permissions are loaded through the system user that is dynamically assigned to the logged in employee.

Data modifications are attributed to the current user account.

NOTE: If the option **Connect automatically** is set, authentication is no longer necessary for subsequent logins.

Related Topics

- [Configuration data for system user dynamic authentication](#) on page 100

LDAP user account (role-based)

NOTE: This authentication module is available if the module LDAP Module is installed.

Credentials Login name, identifier, distinguished name or user ID of an LDAP user account.

LDAP user account's password.

- Prerequisites
- The employee exists in the One Identity Manager database.
 - The employee is assigned at least one application role.
 - The LDAP user account exists in the One Identity Manager database and the employee is entered in the user account's master data.
 - The configuration data for dynamically determining the system user is defined in the application. Thus, an employee can, for example, be

assigned a system user dynamically depending on their department membership.

Set as default	No
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes

Remarks If you log in using a login name, identifier or user ID, the corresponding user account is determined in the One Identity Manager database through the container's domain. Logging in with a distinguished name is done directly. One Identity Manager determines which employee is assigned to the LDAP user account.

If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If the parameter is not set, the employee's subidentity is used for authentication.

A dynamic system user determined from the employee's application roles. The user interface and the write permissions are loaded through this system user.

Data modifications are attributed to the current user account.

Modify the following configuration parameters in the Designer to implement the authentication module.

Table 30: Configuration Parameters for the Authentication Module

Configuration parameter	Meaning
--------------------------------	----------------

TargetSystem LDAP Authentication	The configuration parameter allows configuration of the LDAP authentication module.
TargetSystem LDAP Authentication Authentication	The configuration parameter specified the authentication mechanism. Permitted values are Secure, Encryption, SecureSocketsLayer, ReadonlyServer, Anonymous, FastBind, Signing, Sealing, Delegation and ServerBind . The value can be combined with commas (,). For more information about authentication types, see the MSDN Library .

Configuration parameter Meaning

	The default is ServerBind .
TargetSystem LDAP Authentication Port	LDAP server's port. The default is port 389 .
TargetSystem LDAP Authentication RootDN	The configuration parameter contains the root domain's distinguished name. Syntax: dc=MyDomain
TargetSystem LDAP Authentication Server	The configuration parameter contains the name of the LDAP server.

LDAP user account (dynamic)

NOTE: This authentication module is available if the LDAP Module is installed.

Credentials Login name, identifier, distinguished name or user ID of an LDAP user account.

LDAP user account's password.

Prerequisites

- The employee exists in the One Identity Manager database.
- The LDAP user account exists in the One Identity Manager database and the employee is entered in the user account's master data.
- The configuration data for dynamically determining the system user is defined in the application. Thus, an employee can, for example, be assigned a system user dynamically depending on their department membership.

Set as default No

Single sign-on No

Front-end login allowed Yes

Web Portal Yes

login allowed

Remarks If you log in using a login name, identifier or user ID, the corresponding user account is determined in the One Identity Manager database through the container's domain. Logging in with a distinguished name is done directly. One Identity Manager determines which employee is assigned to the LDAP user account.

If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If the parameter is not set, the employee's subidentity is used for authentication.

The application configuration data is used to determine a system user, which is automatically assigned to the employee. The user interface and write permissions are loaded through the system user that is dynamically assigned to the logged in employee.

Data modifications are attributed to the current user account.

Modify the following configuration parameters in the Designer to implement the authentication module.

Table 31: Configuration Parameters for the Authentication Module

Configuration parameter	Meaning
TargetSystem LDAP Authentication	The configuration parameter allows configuration of the LDAP authentication module.
TargetSystem LDAP Authentication Authentication	The configuration parameter specified the authentication mechanism. Permitted values are Secure, Encryption, SecureSocketsLayer, ReadonlyServer, Anonymous, FastBind, Signing, Sealing, Delegation and ServerBind . The value can be combined with commas (,). For more information about authentication types, see the MSDN Library . The default is ServerBind .
TargetSystem LDAP Authentication Port	LDAP server's port. The default is port 389 .
TargetSystem LDAP Authentication RootDN	The configuration parameter contains the root domain's distinguished name. Syntax:

Configuration parameter Meaning

dc=MyDomain

TargetSystem | LDAP | Authentication | Server The configuration parameter contains the name of the LDAP server.

Related Topics

- [Configuration data for system user dynamic authentication](#) on page 100

HTTP Header

The authentication module supports authentication via web single sign-on solutions that work with a proxy--based architecture.

Credentials Employee's central user account or personnel number.

Prerequisites

- The system user with permissions exists in the One Identity Manager database.
- The employee exists in the One Identity Manager database.
- The central user account or personnel number is entered in the employee's master data.
- The system user is entered in the employee's master data.

Set as default No

Single sign-on Yes

Front-end login allowed No

Web Portal login allowed Yes

Remarks You must pass the user (in the form: UserName =<user name of authenticated user>) in the HTTP header. The employee is found in the One Identity Manager database whose central user account or personnel number matches the user name passed down.

If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If the parameter is not set, the employee's subidentity is used for authentication.

The user interface and the write permissions are loaded through the system user that is directly assigned to the logged in employee. If a system user is not assigned to the employee, the system user from the **SysConfig | Logon | DefaultUser** configuration parameter is used.

Changes to the data are assigned to the logged in employee.

HTTP Header (role-based)

The authentication module supports authentication via web single sign-on solutions that work with a proxy-based architecture.

Credentials	Employee's central user account or personnel number.
Prerequisites	<ul style="list-style-type: none"> • The employee exists in the One Identity Manager database. • The central user account or personnel number is entered in the employee's master data. • The employee is assigned at least one application role.
Set as default	Yes
Single sign-on	Yes
Front-end login allowed	No
Web Portal login allowed	Yes
Remarks	<p>You must pass the user (in the form: <code>UserName =<user name of authenticated user></code>) in the HTTP header. The employee is found in the One Identity Manager database whose central user account or personnel number matches the user name passed down.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> • If this configuration parameter is set, the employee's main identity is used for authentication. • If the parameter is not set, the employee's subidentity is used for

authentication.

A dynamic system user determined from the employee's application roles. The user interface and the write permissions are loaded through this system user.

Changes to the data are assigned to the logged in employee.

OAuth 2.0 / OpenID Connect

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authorization module supports the authorization code for OAuth 2.0 and OpenID Connect. For more detailed information about the authorization code flow, see, for example, the [OAuth Specification](#) or the [OpenID Connect Specification](#).

This authentication module uses a Secure Token Service for logging in. This login procedure can be used with every Secure Token Service that can return an OAuth 2.0 token.

Credentials	Dependent on the authentication method of the secure token service.
Prerequisites	<ul style="list-style-type: none">• The system user with permissions exists in the One Identity Manager database.• The employee exists in the One Identity Manager database.• The system user is entered in the employee's master data.• The user account exists in the One Identity Manager database and the employee is entered in the user account's master data.
Set as default	No
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>One Identity Manager determines which employee is assigned to the user account.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p>

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If the parameter is not set, the employee's subidentity is used for authentication.

The user interface and access permissions are loaded through the system user that is directly assigned to the employee found.

Data modifications are attributed to the current user account. To do this, the claim type whose value is used for labeling data changes must be declared.

Related Topics

- [OAuth 2.0/OpenID Connect configuration](#) on page 105
- [Expiry of the OAuth 2.0/OpenID Connect authentication](#) on page 105

OAuth 2.0 / OpenID Connect (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authorization module supports the authorization code for OAuth 2.0 and OpenID Connect. For more detailed information about the authorization code flow, see, for example, the [OAuth Specification](#) or the [OpenID Connect Specification](#).

This authentication module uses a Secure Token Service for logging in. This login procedure can be used with every Secure Token Service that can return an OAuth 2.0 token.

Credentials	Dependent on the authentication method of the secure token service.
Prerequisites	<ul style="list-style-type: none"> • The employee exists in the One Identity Manager database. • The employee is assigned at least one application role. • The user account exists in the One Identity Manager database and the employee is entered in the user account's master data.
Set as default	No
Single sign-on	No
Front-end login allowed	Yes

Web Portal login allowed	Yes
Remarks	<p>One Identity Manager determines which employee is assigned to the user account.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> • If this configuration parameter is set, the employee's main identity is used for authentication. • If the parameter is not set, the employee's subidentity is used for authentication. <p>Data modifications are attributed to the current user account. To do this, the claim type whose value is used for labeling data changes must be declared.</p>

Related Topics

- [OAuth 2.0/OpenID Connect configuration](#) on page 105
- [Expiry of the OAuth 2.0/OpenID Connect authentication](#) on page 105

Synchronization authentication module

NOTE: This authentication module is available if the module Target System Synchronization Module is installed.

This authentication module integrates the default method for Synchronization Editor login.

Credentials	Login uses the sa system user.
Prerequisites	
Set as default	Yes
Single sign-on	No
Front-end login allowed	No
Web Portal login allowed	No
Remarks	You should not change the system user sa . The system user is overwritten with each schema update.

Web agent authentication module

The authentication module integrates the default method for Web Designer login, to access the database before the first user login.

Credentials	Login uses the sa system user.
Prerequisites	
Set as default	Yes
Single sign-on	No
Front-end login allowed	No
Web Portal login allowed	No
Remarks	You should not change the system user sa . The system user is overwritten with each schema update.

Component authentication module

This authentication module integrates the default method for registering process components.

Credentials	Login uses the sa system user.
Prerequisites	
Set as default	Yes
Single sign-on	No
Front-end login allowed	No
Web Portal login allowed	No
Remarks	You should not change the system user sa . The system user is overwritten with each schema update.

Crawler

The authentication module is used by the application server to compile search indexes for full text search over the database.

Credentials	Login uses the sa system user.
Prerequisites	
Set as default	Yes
Single sign-on	No
Front-end login allowed	No
Web Portal login allowed	No
Remarks	You should not change the system user sa . The system user is overwritten with each schema update.

Password reset

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authentication module is used for login to Password Reset Portal. The authentication module checks the access code or the employee's answers to the password questions. In the case of login with an access code, this information is deleted after a successful login.

Credentials	Central user account and access code. - OR - Central user account and answers to the password questions.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The central user account is entered in the employee's master data.• The employee is not deactivated or has the certification status New.• The employee has an access code or the questions and answers for the password prompt have been specified.
Set as default	No
Single sign-on	No

Front-end login allowed	No
Web Portal login allowed	No
Remarks	The application token for Password Reset Portal must be specified. You set the application token when installing Password Reset Portal. The application token is saved as a hash value in the database in the QER Person PasswordResetAuthenticator ApplicationToken parameter and stored encrypted in the web.config file. For detailed information about configuring Password Reset Portal, see the <i>One Identity Manager Web Application Configuration Guide</i> .

Password reset (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authentication module is used for login to Password Reset Portal. The authentication module checks the access code or the employee's answers to the password questions. In the case of login with an access code, this information is deleted after a successful login.

Credentials	Central user account and access code. - OR - Central user account and answers to the password questions.
Prerequisites	<ul style="list-style-type: none"> The employee exists in the One Identity Manager database. The central user account is entered in the employee's master data. The employee is not deactivated or has the certification status New. The employee has an access code or the questions and answers for the password prompt have been specified. The employee is assigned at least one application role.
Set as default	Yes
Single sign-on	No
Front-end login allowed	No
Web Portal login allowed	No

Remarks The application token for Password Reset Portal must be specified. You set the application token when installing Password Reset Portal. The application token is saved as a hash value in the database in the **QER | Person | PasswordResetAuthenticator | ApplicationToken** parameter and stored encrypted in the web.config file. For detailed information about configuring Password Reset Portal, see the *One Identity Manager Web Application Configuration Guide*.

A dynamic system user determined from the employee's application roles. The user interface and the write permissions are loaded through this system user.

Editing authentication modules

Before you can use an authentication module for logging on, the following prerequisites must be fulfilled:

1. The authentication module must be enabled.
2. The authentication module must be assigned to the application.
3. The assignment of the authentication module to the application must be enabled.

This allows you to log in to the assigned application using this authentication module. Ensure that users found through the authentication module also have the required program function to use the program.

Detailed information about this topic

- [Enabling authentication modules](#) on page 94
- [Assigning authentication modules to applications](#) on page 94
- [Disabling or enabling authentication modules for applications](#) on page 94
- [Authentication module properties](#) on page 95
- [Initial data for authentication modules](#) on page 96
- [Configuration data for system user dynamic authentication](#) on page 100
- [One Identity Manager Authentication modules](#) on page 68
- [Managing permissions to program features](#) on page 61

Enabling authentication modules

To enable an authentication module

1. In Designer, select **Base data | Security settings | Authentication modules**.
2. In List Editor, select the authentication module.
3. In the **Properties** view, set the **Activated** property to **True**.
4. Save the changes.

Related Topics

- [Disabling or enabling authentication modules for applications](#) on page 94

Assigning authentication modules to applications

If create custom authentication modules, assign them to the existing programs. In general, you do not need to change assignments of predefined authentication modules.

To assign an authentication module to applications

1. In Designer, select **Base data | Security settings | Authentication modules**.
2. Select **View | Select table relations** and enable the `DialogProductHasAuthentifier` table.
3. In List Editor, select the authentication module.
4. Assign the application in the **Application** edit view.
5. Save the changes.

Related Topics

- [Disabling or enabling authentication modules for applications](#) on page 94

Disabling or enabling authentication modules for applications

To disable an authentication module for an application

1. Select **Base data | Security settings | Programs** in Designer.
2. In List Editor, select the application and click on **Usage overview**.

3. In the **Effective authenticators** form element, select the authentication module.
4. Start the Object Editor using **Edit object**.
5. In the **Disabled** property, set the value to **True**.
6. Save the changes.

To enable an authentication module for an application

1. Select **Base data | Security settings | Programs** in Designer.
2. In List Editor, select the application and click on **Usage overview**.
3. In the **Disabled authenticators** form element, select the authentication module.
4. Start the Object Editor using **Edit object**.
5. In the **Disabled** property, set the value to **False**.
6. Save the changes.

Related Topics

- [Assigning authentication modules to applications](#) on page 94
- [Enabling authentication modules](#) on page 94

Authentication module properties

Table 32: Authentication Module Properties

Property	Meaning
Enabled	Specifies whether the authentication module can be used.
Display name	This name is used to identify the authentication module in the administration tool's login window.
Authentication module	Internal name of the authentication module.
Authentication type	Specifies the type of authentication module. You can choose Dynamic and Role based .
Processing status	The processing status is used for creating custom configuration packages.
Initial data	Initial data for logging in with this authentication module.
Class	Authentication module class.
Assembly name	Name of the assembly file.
Sort order	Specify the order in which the modules are displayed in the login window.

Property	Meaning
Single sign-on	Specifies whether the authentication module may be authenticated without a password.
Select in front-end	Specifies whether the authentication module can be selected in the login window.

Initial data for authentication modules

The initial data is one part of the authentication string (parameter-value pair without module ID). Initial data from the authentication string is preallocated by default for each authentication instance.

The authentication string is formatted as follows:

Module=<name>;<property1>=<value1>;<property2>=<value2>,...

Example:

Module=DialogUser;User=<user name>;Password=<password>

To specify initial data

1. In Designer, select **Base data | Security settings | Authentication modules**.
2. Select the authentication module and enter the data in **Initial data**.

Syntax:

property1=value1;property2=value2

Example:

User=<user name>;Password=<password>

You can use different initial data depending on the authentication module.

Table 33: Initial data for authentication modules

Module Display Name	Authentication module	Parameter	Meaning/Comment
System user	DialogUser	User	User name.
		Password	User password.
Active Directory user account	ADSAccount		
Active Directory	DynamicADSAccount	Product	Use case. The system user is determined through the use

Module Display Name	Authentication module	Parameter	Meaning/Comment
user account (dynamic)			case configuration data.
Active Directory user account (manual input)	DynamicManualADS	Product	Use case. The system user is determined through the use case configuration data.
		User	User name. The user's identity is determined from a predefined list of permitted Active Directory domains. Enter the permitted Active Directory domains in the TargetSystem ADS AuthenticationDomains configuration parameter.
		Password	User password.
Active Directory user account (role-based)	RoleBasedADSAccount		No parameters required
Active Directory user account (manual input/role-based)	RoleBasedManualADS	User	User name. The user's identity is determined from a predefined list of permitted Active Directory domains. Enter the permitted Active Directory domains in the TargetSystem ADS AuthenticationDomains configuration parameter.
		Password	User password.
Employee	Employee	User	Employee's central user account.
		Password	User password.
Employee (dynamic)	DynamicPerson	Product	Use case. The system user is determined through the use case configuration data.

Module Display Name	Authentication module	Parameter	Meaning/Comment
		User	User name.
		Password	User password.
Employee (role-based)	RoleBasedPerson	User	User name.
		Password	User password.
HTTP header	HTTPHeader	Header	HTTP Header to use.
		KeyColumn	Comma delimited list of key columns in the table Person to be searched for user names. Default: CentralAccount, PersonnelNumber
HTTP header (role-based)	RoleBasedHTTPHeader		HTTP header to use.
		KeyColumn	Comma delimited list of key columns in the table Person to be searched for user names. Default: CentralAccount, PersonnelNumber
LDAP user account (dynamic)	DynamicLdap	User	User name. Default: CN, DistinguishedName, UserID, UIDLDAP
		Password	User password.
LDAP user account (role-based)	RoleBasedLdap	User	User name. Default: CN, DistinguishedName, UserID, UIDLDAP
		Password	User password.
Generic single sign-on (role-based)	RoleBasedGeneric	SearchTable	Table in which to search for the user name of the logged in user. This table must contain a FK named UID_Person which points to the table Person.
		SearchColumn	Column from the SearchTable in which to search for the user

Module Display Name	Authentication module	Parameter	Meaning/Comment
			name of the logged-in user.
		DisabledBy	Pipe () delimited list of Boolean columns which block a user account from logging in.
		EnabledBy	Pipe () delimited list of Boolean columns which release a user account for logging in.
OAuth 2.0/OpenID Connect	OAuth		Dependent on the authentication method of the secure token service.
OAuth 2.0/OpenID Connect (role-based)	OAuthRoleBased		Dependent on the authentication method of the secure token service.
Account based system user	DialogUserAccountBased		No parameters required
User account	QERAccount		No parameters required
User account (role-based)	RoleBasedQERAccount		No parameters required
Password reset	PasswordReset		No parameters required
Password reset (role-based)	RoleBasedPasswordReset		No parameters required

Related Topics

- [Configuration data for system user dynamic authentication](#) on page 100
- [One Identity Manager Authentication modules](#) on page 68

Configuration data for system user dynamic authentication

In the case of dynamic authentication modules, the system user assigned to the employee is not used for the log in. The system user which is configured using the user interface special configuration data is taken instead.

To specify configuration data

1. Select **Base data | Security settings | Programs** in Designer.
2. Select the application and adjust the **Configuration data**.

Use XML syntax for entering the configuration data:

```
<DialogUserDetect>
  <Usermappings>
    <Usermapping
      DialogUser = "System user name"
      Selection = "Selection criterion"
    />
    <Usermapping
      DialogUser = "System user name"
    />
    ...
  </Usermappings>
</DialogUserDetect>
```

Enter the system user (`DialogUser`) in `Usermappings` section. Specify which employee the given system user should use with the selection criterion (`Selection`). You are not obliged to enter a selection criterion for the assignment. The first system user that has the required assignment is used for the log in.

You can assign function groups to permissions groups on order to deal with complex rights and user interface structures. The function groups allow you to map the functions an employee has in the company, for example, IT controller or branch manager. Assign the function groups to the permissions groups. A function group can refer to several permissions groups and several function groups can refer to one permissions group.

If the section `FunctionGroupMapping` is in the configuration data, this is evaluated first and the system user that is found is used. The authentication module uses the system user that is the exact member of the permissions group found for the login. If none is found the section `Usermapping` is evaluated.

```
<DialogUserDetect>
  <FunctionGroupMapping
    PersonToFunction = "View mapping employee to function group"
  </FunctionGroupMapping>
</DialogUserDetect>
```

```

        FunctionToGroup = "View mapping function group to permissions group"
    />
    <Usermappings>
        <Usermapping
            DialogUser = "System user name"
            Selection = "Selection criterion"
        />
        ...
    </Usermappings>
</DialogUserDetect>

```

Related Topics

- [Example of a simple system user assignment on page 101](#)
- [Example of a system user assignment using a selection criterion on page 102](#)
- [Example of a function group assignment on page 103](#)
- [Granting One Identity Manager schema permissions on page 34](#)

Example of a simple system user assignment

All employees should be able to see the user interface for an IT Shop in a web front-end, without taking table and column permissions into account.

To do this, set up a new application, for example **WebShop_Customer**, and adapt the configuration data as follows:

```

<DialogUserDetect>
    <Usermappings>
        <Usermapping
            DialogUser = "dlg_all"
        />
    </Usermappings>
</DialogUserDetect>

```

Create a new **WebShop_Customer** permissions group, which receives the user interface for the application comprising the menu items, interface forms and task definitions. The user interface could consist of the following menu items:

- Employee contact data
- Requesting a product
- Unsubscribing a product

Define a new **dlg_all** system user and include it in the **vi_DE-CentralPwd**, **vi_DE-ITShopOrder** and **WebShop_Customer** permissions groups.

Related Topics

- [Configuration data for system user dynamic authentication](#) on page 100
- [Example of a system user assignment using a selection criterion](#) on page 102
- [Example of a function group assignment](#) on page 103
- [Granting One Identity Manager schema permissions](#) on page 34

Example of a system user assignment using a selection criterion

The scenario described in the previous example is extended such that only the cost center manager can see an employee's leaving date. You need to add the input field **LeavingDate** to the contact data form to do this.

Permissions are used for controlling viewing and editing. Set up a new **dlg_kst** system user and include the system user in the **vi_DE-CentralPwd**, **vi_DE-ITShopOrder** and **WebShop_Customer** permissions groups. You should also give the system user read and write access to the column `Person.Exitdate`.

Extend the application configuration data in such a way that the cost center managers use the **dlg_kst** system user to log in. All other employees use the **dlg_all** system user to log in.

Change the configuration data as follows:

```
<DialogUserDetect>
  <Usermappings>
    <Usermapping
      DialogUser = "dlg_kst"
      Selection = "select 1 where %uid% in (select uid_personhead from
profitcenter)"
    />
    <Usermapping
      DialogUser = "dlg_all"
    />
  </Usermappings>
</DialogUserDetect>
```

Related Topics

- [Configuration data for system user dynamic authentication on page 100](#)
- [Example of a simple system user assignment on page 101](#)
- [Example of a function group assignment on page 103](#)
- [Granting One Identity Manager schema permissions on page 34](#)

Example of a function group assignment

To assign function groups to permissions groups you have to define two database views. The first database view shows the assignment of employees to function groups. The database view contains two columns UID_Person and FunctionGroup.

Example:

```
create view custom_Person2Fu as
    select uid_personHead as UID_Person, 'Cost center manager' as FunctionGroup
    from Profitcenter
    where isnull(uid_personHead, '') > ' '
    union all
    select uid_personHead, 'Department manager' as FunctionGroup
    from Department
    where isnull(uid_personHead, '') > ' '
```

The second database view assigns function groups to permissions groups. This database view contains two columns FunctionGroup and DialogGroup.

Example:

```
create view custom_Fu2D as
    select 'Cost center manager' as FunctionGroup, '<UID_Custom_Dialoggroup_ChefP>'
    as DialogGroup
    union all select 'Department manager', '<UID_Custom_Dialoggroup_ChefD>' as
    DialogGroup
```

Set up role-based permissions groups with the required permissions.

- **TIP:** A role-based permissions group can inherit from a non role-based permissions group. This allows you to build up an inheritance hierarchy to making it easier to grant permissions.

Change the configuration data for assigning function groups to permissions groups as follows:

```
<DialogUserDetect>
    <FunctionGroupMapping
        PersonToFunction = "custom_Person2Fu"
```

```
        FunctionToGroup = "custom_Fu2D"  
    />  
</DialogUserDetect>
```

Related Topics

- [Configuration data for system user dynamic authentication](#) on page 100
- [Example of a simple system user assignment](#) on page 101
- [Example of a system user assignment using a selection criterion](#) on page 102
- [Granting One Identity Manager schema permissions](#) on page 34

Enabling the validity of a login

The system runs validity checks to prevent users from working with established connections, if they were deactivated after they logged in.

The check takes place when the next permissions based action on the connection at a fixed interval of 20 minutes.

- TIP:** You can adjust the interval using the **Common | Authentication | CheckInterval** configuration parameter. Edit the configuration parameter in the Designer.

OAuth 2.0/OpenID Connect configuration

The **OAuth2.0/OpenID Connect** and **OAuth2.0/OpenID Connect (role-based)** authentication modules support the authorization code flow for OAuth 2.0 and OpenID Connect. For more detailed information about the authorization code flow, see, for example, the [OAuth Specification](#) or the [OpenID Connect Specification](#).

To use the OAuth2.0/OpenID Connect authentication:

- In the Designer, create the identity provider and the OAuth2.0/OpenID Connect applications for the identity provider. A wizard is available in the Designer to assist in this process.
- Assign the OAuth2.0/OpenID Connect application to the web applications.

Related Topics

- [Expiry of the OAuth 2.0/OpenID Connect authentication](#) on page 105
- [Creating the OAuth 2.0/OpenID Connect configuration](#) on page 107
- [Assigning OAuth 2.0/OpenID Connect configuration to web applications](#) on page 111
- [Defining enabling and disabling columns for the determination of user accounts](#) on page 113
- [OAuth 2.0 / OpenID Connect](#) on page 87
- [OAuth 2.0 / OpenID Connect \(role-based\)](#) on page 88

Expiry of the OAuth 2.0/OpenID Connect authentication

At the endpoint of the authorization, the web application (or native application) requests the authorization code. The login endpoint is used to call an advanced login window, which serves to determine the authorization code. The authentication module requires an access token from the token endpoint and the certificate is required to check the security token.

In the process, an attempt is made to find the certificate from the web application configuration. If this is not possible, the settings of the identity provider are used. To find the certificate for testing the token, the certificate stores are queried in the following order:

1. Configuration of the OAuth 2.0/OpenID Connect application (table `QBMIIdentityClient`)
 - a. Certificate text (`QBMIIdentityClient.CertificateText`).
 - b. Subject or fingerprint from the local memory (`QBMIIdentityClient.CertificateSubject` and `QBMIIdentityClient.CertificateThumbPrint`).
 - c. Certificate endpoint (`QBMIIdentityClient.CertificateEndpoint`).

In addition, the subject or fingerprint is used to check certificates from the server if they are specified and do not exist locally on the server.

2. Configuration of the identity provider (table `QBMIIdentityProvider`)
 - a. Certificate text (`QBMIIdentityProvider.CertificateText`).
 - b. Subject or fingerprint from the local memory (`QBMIIdentityProvider.CertificateSubject` and `QBMIIdentityProvider.CertificateThumbPrint`).
 - c. Certificate endpoint (`QBMIIdentityProvider.CertificateEndpoint`).

In addition, the subject or fingerprint is used to check certificates from the server if they are specified and do not exist locally on the server.

 - d. JSON-Web-Key endpoint (`QBMIIdentityProvider.JsonWebKeyEndpoint`).

To identify the user account, the system determines which claim type is used to find the user information and which information from the One Identity Manager schema is used to find the user account.

Authentication through OpenID is built on OAuth 2.0. The OpenID Connect authentication uses the same mechanisms, but makes the claims available either in an ID token or via a `UserInfo` endpoint. Other configuration settings are required for using OpenID Connect. If the **Scope** contains the **openid** value, the authentication module uses OpenID Connect for authentication.

Related Topics

- [Creating the OAuth 2.0/OpenID Connect configuration](#) on page 107
- [OAuth 2.0 / OpenID Connect](#) on page 87
- [OAuth 2.0 / OpenID Connect \(role-based\)](#) on page 88

Creating the OAuth 2.0/OpenID Connect configuration

To create an OAuth 2.0/OpenID Connect configuration

1. In the Designer, select **Base data | Security settings | OAuth 2.0/OpenID Connect configuration**.
2. Select **Create a new identity provider**.
3. On the start page of the wizard, click **Next**.
4. On the **New identity provider** page, enter the display name for the configuration and a description.
5. Click **Next**.
6. On the **Automatic configuration discovery** page, you define how you want to enter the information about the identity provider.
 - If the configuration data can be determined automatically via OpenID Connect Discovery:
 - a. Select **Automatic configuration data discovery**.
 - b. Enter the address (URL) for automatic determination of the configuration data in the input field, or select an example address via the selection menu.
 - c. Click on **Execute**.
 - d. The configuration data is determined and a dialog window is displayed. To accept the configuration data, click **OK**.
 - If you do not want to determined the configuration data automatically, select **Manual data input**.
Enter the configuration data on the next page of the wizard.
7. Click **Next**.
8. On the **Configuration data** page, enter the general information for the database user.

NOTE: If you selected automatic determination of configuration data, some of the information is already completed.

Table 34: General configuration data for the identity provider

Property	Description
Login endpoint	Uniform Resource Locator (URL) of the Secure Token Service login page. Example: http://localhost/rsts/login

Property	Description
Logout endpoint	URL of the log-out endpoint Example: http://localhost/rsts/login?wa=wsignout1.0
Token endpoint	Uniform Resource Identifier (URL) of the token endpoint of the authorization server for returning the access token to the client for logging in. Example: https://localhost/rsts/oauth2/token
UserInfo endpoint	URL of the OpenID Connect UserInfo endpoint.
Self-signed certificates allowed	Specifies whether self-signed certificates are allowed for connecting to the token endpoint and UserInfo endpoint.
Issuer	Uniform Resource Identifier (URI) of the certificate issuer for verifying the security token. Example: urn:STS/identity
Scope	Protocol for authentication. If the value is openid , OpenID Connect is used for authentication, otherwise OAuth 2.0 is used.
Shared Secret	Shared-Secret value used for authentication at the token endpoint. If all applications of the identity provider use the same Shared Secret, enter the value here. If the applications use different Shared Secrets, enter the Shared Secret values when creating the applications.

9. Click **Next**.
10. On the **Configure certificates** page, enter the information for the identity provider's certificate. If all applications use the same certificate, enter the information here. NOTE: If you selected automatic determination of configuration data, some of the information is already completed.

NOTE: If you selected automatic determination of configuration data, some of the information is already completed.

Table 35: Information about the identity provider certificate

Property	Description
Certificate endpoint	Uniform Resource Locator (URL) of the certificate end point on the authorization server. Example: https://localhost/RSTS/SigningCertificate

Property	Description
Subject of the certificate	Subject of the certificate used for verification. The subject or fingerprint must be set.
Fingerprint	Fingerprint of the certificate used to verify the security token.
JSON-Web-Key endpoint	URL of the JSON web key endpoint providing the token signing keys.
Certificate	Character string of the certificate content. It is used if no certificate is configured.

- Click **Next**.
- On the **Search rule for user information** page, you define how the login information is determined between the identity provider and the One Identity Manager database.

Table 36: Determining the login information

Property	Description
Value for the search	<p>Full name of the claim type from which the login information is determined on the identity provider.</p> <p>Example: name of an entity</p> <p>http://schemas.xmlsoap.org/ws/2005/05/identity/claims/nameidentifier</p> <p>If you have determined the configuration data automatically, select a value from the list.</p>
Column to search	<p>Table and column in the One Identity Manager database in which the user information is stored. The table must contain a foreign key with the name UID_Person, which points to the Person table.</p> <p>Example: ADSAccount.ObjectGUID</p>
User name value	<p>Full name of the claim type from which the user name is determined on the identity provider. The user name is used, for example, to identify data changes in One Identity Manager (column XUserInserted and XUserUpdated).</p> <p>Example: User Principle Name (UPN)</p> <p>http://schemas.xmlsoap.org/ws/2005/05/identity/claims/upn</p> <p>If you have determined the configuration data automatically, select a value from the list.</p>

- Click **Next**.
- On the **Create OAuth 2.0/OpenID Connect applications**, enter the application

information for the identity provider.


- a. Click on  next to the Applications input field.
- b. On the **General** tab, enter the general information for the application.

Table 37: General information about the application

Property	Description
Display name	Display name of the application.
Description	Spare text box for additional explanation.
Client ID	ID of the application on the identity provider. For native applications, enable the Default option. Example: urn:OneIdentityManager/Web
Shared Secret	Application-specific Shared Secret value used for authentication at the token endpoint.
Resource to request	URN of the resource to be requested, for example for ADFS. Only required if the identity provider requires this value.
Redirect URI	Forwarding address for redirection of applications. Example: urn:InstalledApplication
Default	Specifies whether this is a standard application for native applications.

- c. On the **Certificate** tab, enter the information for the application certificate.

Table 38: Information about the application certificate

Property	Description
Certificate endpoint	Uniform Resource Locator (URL) of the certificate end point on the authorization server. Example: https://localhost/RSTS/SigningCertificate
Fingerprint	Fingerprint of the certificate used to verify the security token.
Subject of the certificate	Subject of the certificate used for verification. The subject or fingerprint must be set.
Certificate	Content of the certificate. It is used if no certificate is configured.

- d. On the **Authentication** tab, enter the following information

Table 39: Information about the application certificate

Property	Description
Authentication method	Authentication method at the token endpoint. Permitted values are: <ul style="list-style-type: none">• client_secret_basic (default value): HTTP basic authentication method. The Shared Secret is transferred in the HTTP header.• client_secret_post: The Shared Secret is transferred in the client_secret value of the POST-Body.• none: No authentication at the token endpoint.• client_secret_jwt: The Shared Secret is transferred as a JSON web token (JWT).• private_key_jwt: The Shared Secret is transferred as JWT. Encryption with the private key is also applied.
Private key	Private key in text form, which is used for the authentication.

15. To create the identity provider and the application in the One Identity Manager database, click on **Next**.
16. Click **Finish** to complete the wizard.

Assigning OAuth 2.0/OpenID Connect configuration to web applications

To use the **OAuth2.0/OpenID Connect** and **OAuth2.0/OpenID Connect (role-based)** authentication modules in the One Identity Manager web applications, assign the OAuth2.0/OpenID Connect application to the web application.

To assign an OAuth2.0/OpenID Connect application to a web application

1. In the Designer, select **Base data | Security settings | Web server configurations**.
2. Select the web application in List Editor.
3. In the **Properties** edit view, assign the application in the **OAuth2.0/OpenID Connect application** selection list.
4. Save the changes.

TIP: For some web applications, for example the Web Portal, you can customize the OAuth2.0/OpenID Connect configuration in the configuration file (web.config). For more detailed information about configuring the Web Portal, see the *One Identity Manager Installation Guide*.

Displaying the configuration of the identity provider and the OAuth 2.0/OpenID Connect applications

To display the configuration of an identity provider

1. In the Designer, select **Base data | Security settings | OAuth 2.0/OpenID Connect configuration**.
2. Select the identity provider in List Editor. The configuration data is displayed on the following tabs in the edit view.
 - **General**: Displays the general configuration data of the identity provider.
 - **Certificate**: Shows the information about the identity provider certificate.
 - **Applications**: Displays the configuration of the OAuth 2.0/OpenID Connect applications.
 - **Columns for enabling**: Displays the table and the columns that identify a user account as activated.
 - **Columns for disabling**: Displays the table and the columns that identify a user account as deactivated.

To display the configuration of an OAuth 2.0/OpenID Connect application

1. In the Designer, select **Base data | Security settings | OAuth 2.0/OpenID Connect configuration**.
2. Select the identity provider in List Editor.
3. In the edit view, select the **Applications** tab.
4. To display the configuration of an application, select the OAuth 2.0/OpenID Connect application in the **Application** view.

i NOTE:

Click on **Add** to add a new OAuth 2.0/OpenID Connect application to the configuration of the identity provider.

Click on **Remove** to remove an OAuth 2.0/OpenID Connect application that is no longer required from the configuration of the identity provider.

Related Topics

- [Creating the OAuth 2.0/OpenID Connect configuration on page 107](#)
- [Defining enabling and disabling columns for the determination of user accounts on page 113](#)

Defining enabling and disabling columns for the determination of user accounts

In the determination of the user account for the OAuth 2.0/OpenID Connect authentication, the system checks whether the user account is enabled or disabled. You define which columns can mark a user account as enabled or disabled.

The columns of the table that you selected in the OAuth 2.0/OpenID Connect configuration of the identity provider in the **Column to search** are offered.

To define which columns can enable a user account for login

1. In the Designer, select **Base data | Security settings | OAuth 2.0/OpenID Connect configuration**.
2. In the List Editor, select the configuration.
3. Select the **Columns for enabling** tab in the edit view.
4. In the **Add assignment** view, assign the columns that enable the user account for logon.
5. Save the changes.

To define which columns can disable a user account for login

1. In the Designer, select **Base data | Security settings | OAuth 2.0/OpenID Connect configuration**.
2. In the List Editor, select the configuration.
3. Select the **Columns for disabling** tab in the edit view.
4. In the **Add assignment** view, assign the columns that disable the user account for logon.
5. Save the changes.

Multi-factor authentication in One Identity Manager

Table 40: Multi-factor authentication configuration parameters

Configuration parameter	Meaning
QER Person Defender	This configuration parameter specifies whether classic Starling Two-Factor Authentication integration is supported.
QER Person Defender ApiEndpoint	This configuration parameter contains the URL of the Starling 2FA API end point used to register new users.
QER Person Defender ApiKey	This configuration parameter contains your company's subscription key for accessing the Starling Two-Factor Authentication interface.
QER Person Starling	This configuration parameter specifies whether One Identity Hybrid Subscription is supported. Extend the functional scope of One Identity Manager with a One Identity Hybrid Subscription, which offers a range of additional cloud functions and services. Use the universal Starling Two-Factor Authentication to protect administrator access. Force additional authentication when you request a critical access or to enable out-of-brand user verification for password requirements.
QER Person Starling ApiEndpoint	This configuration parameter contains the touch endpoint for login to the One Identity Starling software-as-a-service platform. The value is determined by the Starling configuration wizard.
QER Person Starling ApiKey	This configuration parameter contains the credential string for login to the One Identity Starling software-as-a-service platform. The value is determined by the Starling configuration wizard.

You can set up multi-factor authentication for specific security-critical actions in One Identity Manager. You can use these, for example, for attestations or when approving requests in Web Portal.

For multi-factor authentication, One Identity Manager uses One Identity Starling Two-Factor Authentication. This service is supplied by default by means of a One Identity Hybrid Subscription. If your company does not use a One Identity Hybrid Subscription, select the conventional Starling Two-Factor Authentication integration. Use configuration parameters to specify which of the two solutions are applied in your company.

To be able to use multi-factor authentication

1. Register your company in Starling Two-Factor Authentication.

For more detailed information, see the Starling Two-Factor Authentication documentation.

2. Specify which authentication solution is used.

- To use One Identity Hybrid Subscription

- a. Start the Launchpad.

- b. Select **Connection to One Identity Hybrid Subscription** and click **Run**.

The Starling Hybrid configuration wizard starts.

- c. Follow the instructions of the Starling Hybrid configuration wizard.

The configuration parameters under **QER | Person | Starling** are enabled and the authentication information is entered.

- To use conventional Starling Two-Factor Authentication integration

- a. In Designer, enable the **QER | Person | Defender** configuration parameter.

- Enable the **QER | Person | Defender | ApiKey** configuration parameter and enter your company's subscription key as the value for accessing the Starling Two-Factor Authentication interface.

The default URL of the Starling 2FA API end point is already entered in the **QER | Person | Defender | ApiEndpoint** configuration parameter.

3. Enable assigning by event for the table PersonHasQERRResource. For more information, see [Editing table properties](#) on page 116.
4. (Optional) Specify whether the security code must be requested from the Starling 2FA app. For more information, see [Requesting a security code](#) on page 117.
5. In Manager, enable the **New Starling 2FA token** service item. For more information, see [Preparing the Starling 2FA token request](#) on page 116.

If the user's telephone number has changed, cancel the current Starling 2FA token and request a new one. If the Starling 2FA token is no longer required, cancel it anyway.

For detailed information, see the following guides:

Theme

Guide

Preparing the IT Shop for multi-factor authen- One Identity Manager IT Shop Admin-

Theme	Guide
tication	istration Guide
Setting up multi-factor authentication for attestation	One Identity Manager Attestation Administration Guide
Setting up Starling Two-Factor Authentication in the web project	One Identity Manager Web Application Configuration Guide
Requesting the Starling 2FA Token	
Requesting products requiring multi-factor authentication	One Identity Manager Web Portal User Guide
Approving requests with multi-factor authentication	
Attestation with multi-factor authentication	

Editing table properties

NOTE: If the **Assign by event** option is enabled, the `HandleObjectComponent` process is placed in the job queue as soon as a resource assignment is added to or removed from an employee.

To enable assigning by event for a table

1. In Designer, select the **One Identity Manager Schema** category.
2. Select the `PersonHasQERRResource` table and start Schema Editor using the **Show table definition** task.
3. In the **Table properties** view, select the **Table** tab and enable the **Assign by event** option.
4. Save the changes.

For detailed information about editing table definitions, see the *One Identity Manager Configuration Guide*.

Preparing the Starling 2FA token request

One Identity Manager users must be registered with Starling Two-Factor Authentication in order to use multi-factor authentication. To register, a user must request the Starling 2FA Token in the Web Portal. Once the request has been granted approval, the user receives a link to the Starling Two-Factor Authentication app and a Starling 2FA user ID. The app

generates one-time passwords, which are required for authentication. The Starling 2FA user ID is saved in the user's employee master data.

NOTE: The user's default email address, mobile phone and country must be stored in their master data. This data is required for registering.

To facilitate requesting a Starling 2FA token

1. Select the category **IT Shop | Service catalog | Predefined**.
2. Select **New Starling 2FA token** in the results list.
3. Select **Change master data**.
4. Disable **Not available**.
5. Save the changes.

The Starling 2FA token request must be granted approval by the request recipient's manager.

Requesting a security code

Table 41: Configuration Parameter for Requesting Starling 2FA Security Codes

Configuration parameter	Meaning
QER Person Defender DisableForceParameter	The configuration parameters specify whether Starling 2FA is forced to send the security code by SMS or phone call if one of these options is selected for multi-factor authentication. If the configuration parameters are enabled, Starling 2FA can refuse this request; the user must then request the security code via the Starling 2FA app.
QER Person Starling DisableForceParameter	

If the security code is requested for an attestation, request or request approval, the user decides how the security code is sent. The following options are available:

- By Starling 2FA app
- By SMS
- By phone call

By default, Starling 2FA is forced to send the OTP by SMS or by phone call if the user has selected one of these options. However, for security reasons, the user should use the Starling 2FA app to generate the OTP. If the app is installed on the user's mobile phone, Starling 2FA can refuse the SMS or phone demand and the user must generate the OTP using the app.

To use this method

- If you use the One Identity Hybrid Subscription, enable the **QER | Person | Starling | DisableForceParameter** configuration parameter in Designer.
- OR -
- If you use classic Starling Two-Factor Authentication, integration, enable the **QER | Person | Defender | DisableForceParameter** configuration parameter in Designer.

Starling 2FA can refuse to transmit the OTP by SMS or phone call if the Starling 2FA app is installed on the phone. Then the OTP must be generated by the app.

If the configuration parameter is not set (default), Starling 2FA is forced to send the OTP by SMS or phone call.

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales or other inquiries, visit <https://www.oneidentity.com/company/contact-us.aspx> or call +1-800-306-9329.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to-videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product

A

application

- assign authentication module 94
- configuration data 100

application role 8

- administrators 10, 12, 14-21, 23-24
- approver 17-18
- approver (IT) 17-18
- assign employees 28-29
- assign extended property 32
- assign reports 31
- attestors 12, 14, 17-18, 20
- auditors 12
- authorize as One Identity Manager administrator 25

base roles 10

- administrators 10, 25
- employee managers 10
- everyone (change) 10
- everyone (lookup) 10
- internal permissions 10
- operations support 10

chief approval team 15, 20

cloud administrators 23

compliance and security officer 11

conflicting 30

custom 24

- administrators 24
- manager/supervisor 24

dynamic 29

edit 25-26

employee managers 10

exception approvers 14

extend edit permissions 28

identity and access governance 11-12, 14-16

attestation 15

- administrators 15
- chief approval team 15

auditors 12

company policies 14

- administrators 14
- attestors 14
- exception approvers 14
- policy supervisors 14

compliance & security officer 11

identity audit 12

- administrators 12
- attestors 12
- maintenance SAP features 12
- rule administrators 12

subscribable reports 16

- administrators 16

identity management 17

business roles 17

- administrators 17
- approver 17
- approver (IT) 17
- attestors 17

employees 19

- administrators 19

management level 17

- organizations 18
 - administrators 18
 - approver 18
 - approver (IT) 18
 - attestors 18
- implement 25
- internal permissions 10
- management level 17
- overview 9
- permissions group 26, 28
- policy supervisors 14
- product owner 20
- reports 32
- request and fulfillment 20
 - IT Shop 20
 - administrators 20
 - attestors 20
 - chief approval team 20
 - product owner 20
- rule administrators 12
- target system manager 21
- target systems
 - administrators 21
 - target system manager 21
- Universal Cloud Interface
 - administrator 23
- assignment resource
 - for an application role 32
- authentication
 - check 104
- authentication module
 - account-based system user 75
 - Active Directory user account 76
 - Active Directory user account (dynamic) 80
 - Active Directory user account (manual input/role-based) 79
 - Active Directory user account (manual) 78
 - Active Directory user account (role-based) 77
 - assign application 94
 - component authentication module 90
 - crawler 91
 - employee 71
 - employee (dynamic) 72
 - employee (role-based) 71
 - enable 94
 - generic single sign-on (role-based) 69
 - HTTP header 85
 - HTTP header (role-based) 86
 - initial data 96
 - LDAP user account (dynamic) 83
 - LDAP user account (role-based) 81
 - OAuth 2.0/OpenID Connect 87
 - OAuth 2.0/OpenID Connect (role-based) 88
 - password reset 91
 - password reset (role-based) 92
 - synchronization authentication module 89
 - system users 68
 - user account 73
 - user account (role-based) 74
 - web agent authentication module 90

D

- dynamic role
 - application role 29

E

- employee
 - authorize as One Identity Manager administrator 25
- event
 - object event 66
 - program function 66

L

- Launchpad
 - actions
 - program function 67

M

- Multi-factor authentication 114

O

- OAuth 2.0/OpenID Connect
 - application 112
 - authentication 105
 - authentication module 87-88
 - certificate 107
 - configuration 105, 112
 - configurations 107
 - disabling columns 113
 - enabling columns 113
 - identity provider 107, 112
 - openid 107
 - scope 107
 - Shared Secret 107
 - use case 107
 - web application 111

- object
 - permissions 58
- object event 66
 - program function 66
- One Identity Hybrid Subscription 114
- One Identity Hybrid Subscription security code 117
- One Identity Starling software-as-a-service 114

P

- permissions
 - column permissions 54
 - copying 56
 - determine 38
 - edit 51
 - object 58
 - permissions filter 53
 - permissions group 51
 - rules 38
 - simulation 57
 - table 52
 - table permissions 53
 - user 59
- Permissions Editor 51
- permissions group
 - assign application 60
 - copy 44
 - dependencies 42-43
 - hierarchy 42
 - only use for role-based authentication 41
 - permissions 51
 - predefined 35
 - program function 64-66

- QBM_BaseRights 35
 - QER_OperationsSupport 35
 - role-based 35
 - setting up 40-41, 45
 - vi_4_ADMIN_LOOKUP 35
 - VI_4_ALLUSER 35
 - VI_Everyone 35
 - VI_View 35
 - vid 35
 - VID_Features 35
 - program function 61, 64, 66
 - Launchpad actions 67
 - permissions group 64-66
 - permissions group
 - program function 64
 - script 64
 - task definition 65
- S**
- script
 - program function 64
 - security code
 - demand
 - by app 117
 - by call 117
 - by text 117
 - Starling 2FA 114, 116
 - Starling 2FA security code 117
 - Starling Two-Factor Authentication 114
 - system user
 - administrative user 48
 - dynamic 35
 - dynamically determine 100
 - employees 50
 - logins 48
 - password 47-48
 - password never expires 47-48
 - permissions group 49
 - predefined 35
 - read-only 48
 - sa 35
 - service account 48
 - setting up 45-46
 - support 35
 - synchronization 35
 - user 50
 - viadmin 35
 - viHelpdesk 35
 - viITShop 35
 - system users
 - dynamic 50
- T**
- table
 - permissions 52
 - task definition
 - program function 65
 - token 116
- U**
- use case
 - assign permissions group 60
 - user
 - authentication module 59
 - dynamic 59
 - permissions 59
 - permissions groups 59
 - program function 59
 - read permissions 59

system user 59