

One Identity Manager 8.1.1

Attestation Administration Guide

Copyright 2019 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC .

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC. Attn: LEGAL Dept 4 Polaris Way Aliso Viejo, CA 92656

Refer to our Web site (http://www.OneIdentity.com) for regional and international office information.

Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at http://www.OneIdentity.com/legal/patents.aspx.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.oneIdentity.com/legal. All other trademarks are the property of their respective owners.

Legend

- **WARNING:** A WARNING icon indicates a potential for property damage, personal injury, or death.
- **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.
- 1 IMPORTANT, NOTE, TIP, MOBILE, or VIDEO: An information icon indicates supporting information.

One Identity Manager Attestation Administration Guide Updated - August 2019 Version - 8.1.1

Contents

Attestation and recertification	8
One Identity Manager users for attestation	8
Attestation base data	10
Attestation types	10
Default attestation types	11
Additional tasks for attestation types	11
Attestation procedure	12
General master data for an attestation procedure	12
Defining reports for attestation	15
Default attestation procedures	15
Additional tasks for attestation procedures	16
Schedules	17
Default schedules	19
Additional tasks for schedules	20
Compliance frameworks	22
Additional tasks for compliance frameworks	22
Chief approval team	23
Standard reasons for attestation	24
Predefined Standard Reasons	25
Attestation policies	25
General master data for attestation policies	26
Risk assessment	28
Default attestation policies	29
Additional tasks for attestation policies	29
The attestation policy overview	30
Assigning approvers	30
Assigning compliance frameworks	30
Mitigating controls	31
Running attestation for single objects	32
Showing or hiding conditions	33
Creating a copy	33



Showing selected objects	33
Deleting attestation policies	34
Disabling attestation policies	34
Custom mail templates for notifications	35
Creating and editing attestation mail templates	35
General properties of a mail template	35
Creating and editing a mail definition	37
Using base object properties	37
Use of Hyperlinks in the Web Portal	38
Customizing email signatures	40
Copying mail templates for attestation	40
Displaying attestation mail templates previews	41
Deleting mail templates for attestation	41
Custom notification processes	41
Approval processes for attestation cases	43
Approval policies for attestations	
General master data for approval policies	
Default approval policies	
Additional tasks for approval policies	
Editing approval workflows	
Validity checking	
Approval workflow for attestations	
Working with the workflow editor	
Setting up approval workflows	
Editing approval levels	
Editing approval steps	
Properties of an approval step	
Connecting approval levels	
Additional tasks for approval workflows	
The approval workflow overview	56
Copying approval workflows	56
Deleting approval workflows	56
Default approval workflows	
Selecting attestors	57
Default approval procedures	50



Finding attestors using the attestation policy	53
Finding attestors using the role of the employee to be attested	63
Finding attestors using attestation objects	63
Finding attestors from attestation object managers	65
Determining attestors from persons responsible for the attestation objects	66
Finding attestors using a specified role	68
Defining product owners as attestors	68
Determining owners of a privileged object as attestors	69
Finding attestors from additional Active Directory group owners	69
Determining attestors from owners of the attestation objects	69
Calculated approval	70
Approvals to be made externally	71
Waiting for further approval	72
Setting up approval procedures	73
General master data for an approval procedure	74
Queries for finding attestors	74
Additional tasks for approval procedures	77
Overview of the approval procedure	77
Specifying permitted approval procedures for tables	77
Copying an approval procedure	78
Deleting approval procedures	78
Determining the responsible attestors	79
Setting up multi-factor authentication for attestation	81
Prevent attestation by employee awaiting attestation	82
Managing attestation cases	82
Getting more information	83
Appointing other attestors	83
Escalating an attestation case	84
Attestors cannot be established	86
Automatic approval on timeout	87
Aborting an attestation case on timeout	89
Attestation through chief approval team	90
Attestation sequence	92
Starting attestation	92
Additional tasks for attestation cases	93



Attestation case overview	94
Approval sequence	94
Attestation history	95
lodifying approval workflows for pending attestation cases	96
losing attestation cases for deactivated employees	97
eleting attestation cases	98
otifications in the attestation process	99
Demanding attestation	100
Reminding attestors	101
Scheduling attestation demands	103
Reminding attestors about attestation objects	103
Granting or denying attestation cases	103
Notifying delegates	105
Aborting attestation cases	106
Escalation of attestation cases	106
Delegating attestations	107
Rejecting approvals	107
Notifications with questions	108
Notifications from additional attestors	108
Link for verifying new external users	109
Default mail templates	109
ttestation by mail	110
Processing attestation mails	112
Default attestation and withdrawal of entitlements	114
ystem entitlements attestation	116
ystem role attestation	118
pplication role attestation	121
usiness role attestation	121
ser attestation and recertification	123
one Identity Manager users for attesting and recertifying users	
onfiguring user attestation and recertification	
ttesting new users	
Self-registration of new users in the Web Portal	
Adding new employees using a manager or employee administrator	



Importing new employee master data	130
Scheduled attestations	131
Limiting attestation objects for certification	132
Recertifying existing users	134
Preparing for recertification	135
The recertification sequence	135
Limiting attestation objects for recertification	136
Mitigating controls	138
General master data for mitigating controls	138
Additional tasks for mitigating controls	139
Mitigating controls overview	139
Assigning attestation policies	139
Calculating mitigation	140
Appendix: Configuration parameters for attestation	141
About us	151
Contacting us	151
Technical support resources	151
Index	152



Attestation and recertification

Managers or others responsible for compliance can use the One Identity Manager attestation functionality to certify correctness of access permissions, authorizations, requests or exception approvals either scheduled or on demand. "Recertification" is the term generally used to describe regular certification of permissions. One Identity Manager uses the same workflows for recertification and attestation.

Attestation policies are defined in the One Identity Manager, which you use to carry out attestations. Attestation policies specify which objects are attested when, how often and by whom. Once an attestation is performed, One Identity Manager creates attestation cases, which contain all the necessary information about the attestation objects and the attestor responsible. The attestor checks the attestation objects. They verify the correctness of the data and initiate any changes that need to be made if the data conflicts with internal rules.

Attestation cases record the entire attestation sequence. Each attestation step in the attestation case can be audit-proof reconstructed. Attestations are run regularly using scheduled tasks. You can also trigger single attestations manually.

Attestation is complete when the attestation case has been granted or denied approval. You specify how to deal with granted or denied attestations on a company basis.

TIP: One Identity Manager provides various default attestation procedures for different data situations and default attestation procedures. If you use these default attestation procedures, you can configure how you deal with denied attestations.

For more information, see Default attestation and withdrawal of entitlements on page 114.

To use attestation functionality

• In Designer, set the **QER | Attestation** configuration parameter.

One Identity Manager users for attestation

The following users are used for attestation.



Table 1: User

User	Tasks
Administrators for attestation	Administrators are assigned to Identity & Access Governance Attestation Administrators .
cases	Users with this application role:
	 Define attestation procedures and attestation policies.
	 Create approval policies and approval workflows.
	 Specify which approval procedure to use to find attestors.
	Set up attestation case notifications.
	Configure attestation schedules.
	Enter mitigating controls.
	Create and edit risk index functions.
	 Monitor attestation cases.
One Identity Manager	 Create customized permissions groups for application roles for role-based login to administration tools in Designer as required.
administrators	 Create system users and permissions groups for non-role-based login to administration tools in Designer as required.
	 Enable or disable additional configuration parameters in Designer as required.
	 Create custom processes in Designer as required.
	 Create and configures schedules as required.
	 Create and configure password policies as required.
Attestors	Check attestation objects in the Web Portal.
	Confirm data correctness.
	 Initiate changes if data conflicts with internal rules.
	Attestators in charge are determined through approval procedures.
Compliance and security	Compliance and security officers must be assigned to Identity & Access Governance Compliance & Security Officer.
officer	Users with this application role:
	 View all compliance relevant information and other analysis in the Web Portal. This includes attestation policies, company policies and policy violations, compliance rules, and rule violations and risk index functions.
	Edit attestation polices.
Auditors	Auditors are assigned to the application role Identity & Access



User	Tasks	
	Governance Auditors.	
	Users with this application role:	
	See the Web Portal all the relevant data for an audit.	
Chief approval team	The chief approver must be assigned to Identity & Access Governance Attestation Chief approval team .	
	Users with this application role:	
	 Approve using attestation cases. 	
	 Assign attestation cases to other attestors. 	

Attestation base data

The attestation framework and the objects to be attested are specified in the attestation policy. You require certain base data to define attestation policies.

Attestation types: Attestation types on page 10 Approval policies for attestations on page 43 Approval policies: Approval workflows: Approval workflow for attestations on page 46 Setting up approval procedures on page 73 Approval procedures: Attestation procedures: Attestation procedure on page 12 Schedules: Schedules on page 17 Compliance frameworks: Compliance frameworks on page 22 Mail templates: Custom mail templates for notifications on page 35 Chief approval team: Chief approval team on page 23 Standard reasons: Standard reasons for attestation on page 24

Attestation types

Attestation types are used to group attestation procedures. These make it easier to assign a matching attestation procedure to the attestation policies.



To edit attestation types

- 1. Select Attestation | Basic configuration data | Attestation types.
- 2. Select an attestation type in the result list and run **Change master data**.
 - OR -
 - Click in the result list.
- 3. Edit the attestation type master data.
- 4. Save the changes.

Default attestation types

You cannot edit default attestation types and their attestation procedure assignments.

The One Identity Manager supplies attestation types, by default. These attestation types are assigned to default attestation procedures. They are necessary for setting up attestation policies in the Web Portal.

To display default attestation types

In Manager, select the category Attestation | Basic configuration data |
 Attestation types | Predefined.

For detailed information about using default attestation types, see the *One Identity Manager Web Portal User Guide*.

Additional tasks for attestation types

After you have entered the master data, you can run the following tasks.

Overview of the attestation type

You can see the most important information about an attestation type on the overview form.

To obtain an overview of an attestation type

- In Manager, select the category Attestation | Basic configuration data | Attestation types.
- 2. Select the attestation type in the result list.
- 3. Select **Attestation type overview** in the task view.



Assigning attestation procedures

Use this task to assign the selected attestation type to all the attestation procedures that should be included in the group.

To assign attestation procedures to attestation types

- 1. In Manager, select the category **Attestation | Basic configuration data | Attestation types**.
- 2. Select the attestation type in the result list.
- 3. Select **Assign attestation procedure** in the task view.

Assign the attestation procedures in **Add assignments**.

TIP: you can remove the assignment of attestation procedures in **Remove** assignments.

To remove an assignment

- Select the attestation procedure and double click

 ✓.
- 4. Save the changes.

Attestation procedure

Attestation procedures specify the attestation base object. They define which attestation object properties are to be attested. Attestation object data can be provided in list or report form.

To edit an attestation procedure

- 1. In Manager, select the category **Attestation | Basic configuration data | Attestation procedures**.
- 2. Select an attestation procedure in the result list and run **Change master data**.
 - OR -
 - Click din the result list.
- 3. Edit the attestation procedure master data.
- 4. Save the changes.

General master data for an attestation procedure

Enter the following properties for an attestation procedure.



Table 2: General master data for an attestation procedure

Property	Description
Attestation procedure	Any name for the attestation procedure.
Attestation type	Criteria for grouping attestation procedures. Attestation types make it easier to assign a matching attestation procedure to the attestation policies.
Description	Spare text box for additional explanation.
Report	Report for the attestor containing all the necessary information about the attestation objects.
	Predefined reports are supplied in a menu. If you do not want to assign a report, you can specify additional information about the attestation objects in the boxes Property 1-4 (template) .
Table	Database table in which the attestation objects are to be found (= attestation base object). All tables, which fulfill the following conditions, are available:
	a. The table contains a XObjectKey column.
	b. The table type is Table , View , ReadOnly or Proxy .
	 c. The usage type is User data, Materialized data or Read only data.
	 It is not the basetree table. It is not an assignment table referencing basetree.
	e. Table belongs to the application data model.
	f. Table is not disabled.
	For detailed information about table types and usage types, see the <i>One Identity Manager Configuration Guide</i> .
Preprocessor condition	Specifies the preprocessor configuration parameters on which the attestation procedure depends. Attestation procedures, which are disabled through a preprocessor condition, are not displayed in the One Identity Manager.
Grouping column 1-3	A value template for formatting the value used to group and filter pending attestation cases in the Web Portal.
(template)	Enter a value template in \$ notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
Grouping column 1-3	Column headers for Grouping column 1-3 (template) . The columns are multi-language. To enter a translation, click ©.
Property 1-4	Templates for formulating a value that supplies additional information



Property	Description
(template)	about the attestation object. Use these fields to show additional information about the attestation object in the Web Portal.
	Enter a value template in \$ notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
Property 1-4	Column headers for Property 1-4 (template) . The columns are multilanguage. To enter a translation, click .
Risk index template	Template for formulating the value for the attestation case's risk index.
	Enter a value template in \$ notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
Related object 1-3 (template)	Template for formulating an object key for an object related to the attestation base object.
	Enter a value template in \$ notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
	Define the display value for this object in Grouping column 1-3 (template).

Example

You want to attest Active Directory Group memberships. Group the attestation cases by user account display value, Active Directory group display value and the display value of associated employees. The Active Directory group's canonical name should be displayed with every group membership in Web Portal. The attestation case's risk index can be determined from the group membership's risk index. The object key for the object relation can be found from the Active Directory user account. The information required about the attestation objects will be summarized in a report. To do this, enter the following data on the master data form.

Table 3: Example of an attestation case definition

Property	Value
Table	Database table ADSAccountInADSGroupTotal
Report	<report name=""></report>
Grouping column 1	\$UID_ADSAccount[d]\$
Grouping column 2	\$UID_ADSGroup[d]\$
Grouping column 3	\$FK(UID_ADSAccount).UID_Person[d]\$
Property 1 (template)	\$FK(UID_ADSGroup).CanonicalName\$



Property	Value	
Risk index template	\$RiskIndexCalculated\$	
Object relation 1	\$FK(UID_ADSAccount).XObjectKey\$	

Detailed information about this topic

- Attestation types on page 10
- Defining reports for attestation on page 15

Defining reports for attestation

Define attestation reports with the Report Editor. Note the following when you define a report for attestation:

- The base table for the report must be identical to the one for the attestation procedure.
- Enter **Attestation** as the report category. This ensures that the report is displayed in the **Report** menu of the attestation procedure.
- In order to create a report for each attestation object with the information relating exactly to the attestation object, define a <code>ObjectKeyBase</code> parameter for the attestation object in the report. Use the parameters in the data source definition for the report in <code>Condition</code> text box.

Example: XObjectKey = @ObjectKeyBase

Default reports

One Identity Manager supplies some default reports for attestation. These are used in the default attestation procedures, amongst others. Default report are given the prefix **VI**_.

1 TIP: Default reports cannot be changed. If you want to customize a default report, create a copy and edit it according to your requirements. Then assign the copy to the attestation procedure.

Default attestation procedures

One Identity Manager provides a default approval procedure for default attestation of new users and recertification of all employees stored in the One Identity Manager database. Moreover, default approval procedures are supplied through which the different roles, user accounts, and system entitlements mapped in the Unified Namespace can be attested. Using these default approval policies you can create attestation procedures easily in the Web Portal.



To display default attestation procedures

In Manager, select the category Attestation | Basic configuration data |
 Attestation procedures | Predefined.

For detailed information about using default attestation procedures, see the *One Identity Manager Web Portal User Guide*.

Related topics

- User attestation and recertification on page 123
- Default attestation and withdrawal of entitlements on page 114

Additional tasks for attestation procedures

After you have entered the master data, you can run the following tasks.

Overview of the attestation procedure

You can see the most important information about an attestation procedure on the overview form.

To obtain an overview of an attestation procedure

- In Manager, select the category Attestation | Basic configuration data | Attestation procedures.
- 2. Select the attestation procedure in the result list.
- 3. Select **Attestation procedure overview** in the task view.

Assigning Approval Policies

Use this task to assign the selected attestation procedure to the approval policies that should be used in this attestation procedure. All approval policies permitted for the attestation base object are listed.

To assign approval policies to attestation procedures

- 1. In Manager, select the category **Attestation | Basic configuration data | Attestation procedures.**
- 2. Select the attestation procedure in the result list.
- 3. Select **Assign approval policies** in the task view.



Assign the approval policies in **Add assignments**.

TIP: In **Remove assignments**, you can remove the assignment of approval policies.

To remove an assignment

- Select the approval policy and double-click

 ✓.
- 4. Save the changes.

Which approval policies are permitted depends on the approval procedures in use. Approval procedures dictate to which tables an approval procedure can be assigned.

Related topics

• Specifying permitted approval procedures for tables on page 77

Creating a copy

You can make copies of attestation procedures and those copies allow you to modify default attestation procedures.

To copy an attestation procedure

- 1. In Manager, select the category **Attestation | Basic configuration data | Attestation procedures**.
- 2. Select the attestation procedure in the result list.
- 3. Select **Create copy** in the task view.
- 4. Confirm the security prompt with **Yes**.
- 5. Decide whether the condition types should be copied for the attestation wizard in the Web Portalas well.
 - Condition types are required if attestation policies are created and edited with the attestation wizard in the Web Portal. For detailed information, see *One Identity Manager Web Portal User Guide*.
- 6. Edit the attestation procedure copy and save the changes.
 - The attestation procedure copy is displayed on the master data form with the name <**Name of original attestation procedure>(copy)**. You can rename and edit this attestation policy.

Schedules

Use schedules to automate attestation. These specify when and how often attestation cases are created. One Identity Manager supplies several default schedules for attestation.



To edit schedules

1. In Manager, select the category **Attestation | Basic configuration data | Schedules**.

The result list shows all schedules configured for attestation policies (table AttestationPolicy).

- 2. Select a schedule in the result list and run the task **Change master data**.
 - OR -
 - Click din the result list.
- 3. Edit the schedule's master data.
- 4. Save the changes.

Enter the following properties for a schedule.


Table 4: Schedule properties

Property	Meaning
Name	Schedule ID. Translate the given text using the © button.
Description	Detailed description of the schedule. Translate the given text using the $\ensuremath{\mathfrak{C}}$ button.
Table	Table whose data can be used by the schedule. Schedules for the attestation must refer to the AttestationPolicy table.
Enabled	Specifies whether the schedule is enabled or not.
	NOTE: Only active schedules are run.
Time zones	Unique identifier for the time zone that is used for running the schedule. Choose between Universal Time Code or one of the time zones in the menu. NOTE:
	When you add a new schedule, the time zone is preset to that of the client from which you started the Manager.
Start (date)	The day on which the schedule should be run for the first time.
Validity period	Period within which the schedule is run.
	 If the schedule will be run for an unlimited period, select the option Unlimited duration.
	 To set a validity period, select the option Limited duration and enter the day the schedule will be run for the last time in End (date).
Occurs	Interval in which the task is run. Permitted interval types are Every minute , Hourly , Daily , Weekly , Monthly and Yearly .



Property Meaning

For the **Weekly** interval type, specify the precise weekday. For the **Monthly** interval type, specify the day of the month (1st to 31st day of the month). For the **Yearly** interval type, specify the day of the year (1st to 366th day of the year).



day of the current month is used.

Example:

A schedule that is run on the 31st day of each month is run on 30th April. In February, the schedule is run on the 28th (or 29th in leap year).

Schedules with the interval type **Yearly** with sub interval **366** are only run in leap year.

Start time

Fixed start type for the **Daily**, **Weekly**, **Monthly** and **Yearly** interval types. Enter the time in local format for the chosen time zone.

For the interval types **Every minute** and **Hourly**, the start time is calculated from the rate of occurrence and the interval type.

Repeat every

Rate of occurrence for running the schedule within the selected time interval. For the **Weekly** interval type, select at least one weekday.

Last planned run/Next planned run

Execution time calculated by the DBQueue Processor. Execution times are recalculated whilst the schedule is running. The time of the next run is calculated from the interval type, rate of occurrence and the start time.

NOTE: The One Identity Manager provides the start information in the time zone of the client where the program was started. Changes due to daylight saving are taken into account.

Default schedules

One Identity Manager supplies the following attestation schedules by default:



Table 5: Default attestation schedules

Schedule	Description
Half-Yearly	Default schedules for any attestation.
Monthly	
Quarterly	
Weekly (Monday)	
Yearly	
Deactivated	Default schedule for default attestation policies.
	The schedule is disabled by default and should not be enabled. To run attestation, assign another schedule to the attestation policies and enable that one.
Daily	Default schedules for any attestation.
	This schedule is assigned to the New user certification attestation policy by default.

Related topics

- Preparing for recertification on page 135
- Scheduled attestations on page 131

Additional tasks for schedules

After you have entered the master data, you can run the following tasks.

Schedule overview

You can see the most important information about a schedule on the overview form.

To obtain an overview of a schedule

- 1. In Manager, select the category **Attestation | Basic configuration data | Schedules**.
- 2. Select the schedule in the result list.
- 3. Select Schedule overview.



Assigning attestation policies

Use this task to assign attestation policies to the selected schedule, which will runs them. If you double-click on one of the attestation policies you assign it to the current schedule.

To assign attestation policies to a schedule

- 1. In Manager, select the category **Attestation | Basic configuration data | Schedules**.
- 2. Select the schedule in the result list.
- 3. Select **Assign attestation polices** in the task view.
- 4. In **Add assignments**, double-click the attestation policies that are to be assigned.
- 5. Save the changes.

To change an assignment

- In Manager, select the category Attestation | Basic configuration data | Schedules.
- 2. Select the schedule in the result list.
- 3. Select **Assign attestation polices** in the task view.
- 4. Select **Show objects already assigned to other objects** in the assignment form context menu.
 - This shows attestation policies that are already assigned in other schedules.
- 5. Double-click on one of these attestation policies in **Add assignments**. The attestation policy is assigned to the currently selected schedule.
- 6. Save the changes.
- NOTE: Assignments cannot be removed. Attestation policies must be assigned a schedule, it is compulsory.

Starting schedules immediately

• NOTE: If a schedule is started, it starts attestation for all active attestation policies assigned with the schedule.

To start a schedule immediately

- 1. In Manager, select the category **Attestation | Basic configuration data | Schedules**.
- 2. Select the schedule in the result list.
- 3. Select **Start immediately** from the task view.

A message appears confirming that the schedule was started.



Compliance frameworks

Compliance frameworks are used for classifying attestation policies, compliance rules and company policies according to regulatory requirements.

Compliance frameworks can be organized hierarchically. To do this, assign a parent framework to the compliance frameworks.

To edit compliance frameworks

- 1. In Manager, select the category **Attestation | Basic configuration data | Compliance Frameworks**.
- 2. Select a Compliance Framework in the result list and run Change master data.
 - OR -
 - Click **New** in the result list toolbar.
- 3. Edit the compliance framework master data.
- 4. Save the changes.

Enter the following properties for compliance frameworks.

Table 6: Compliance framework properties

Property	Description
Compliance framework	Name of the compliance framework.
Parent framework	Parent compliance framework in the framework hierarchy. Select an existing compliance framework in the menu to organize compliance frameworks hierarchically.
Manager/supervisor	Application role whose members are allowed to edit all attestation policies assigned to this compliance framework
Description	Spare text box for additional explanation.

Additional tasks for compliance frameworks

After you have entered the master data, you can run the following tasks.

Compliance framework overview

You can see the most important information about a compliance framework on the overview form.



To obtain an overview of a compliance framework

- In Manager, select the category Attestation | Basic configuration data | Compliance Frameworks.
- 2. Select the compliance framework from the result list.
- 3. Select Compliance framework overview.

Assigning attestation policies

Use this task to assign attestation policies to the selected compliance framework.

To assign attestation policies to a compliance framework

- 1. In Manager, select the category **Attestation | Basic configuration data | Compliance Frameworks**.
- 2. Select the compliance framework from the result list.
- 3. Select **Assign attestation polices** in the task view.

Assign the attestation policies in **Add assignments**.

TIP: In **Remove assignments**, you can remove the assignment of attestation policies.

To remove an assignment

- Select the approval policy and double-click

 ✓.
- 4. Save the changes.

Chief approval team

Sometimes, approval decisions cannot be made for attestation cases because an attestor is not available or does not have access to One Identity Manager tools. To complete these attestations, you can define a chief approval team whose members are authorized to intervene in the approval process at any time.

There is a default application role in One Identity Manager for the chief approval team. Assign this application role to all employees who are authorized to approve, deny, abort attestations in special cases or to authorize other attestors. For detailed information about application roles, see the *One Identity Manager Authorization and Authentication Guide*.

Table 7: Default application role for chief approval team

User	Tasks
Chief approval team	The chief approver must be assigned to Identity & Access Governance Attestation Chief approval team .
	Users with this application role:



- Approve using attestation cases.
- Assign attestation cases to other attestors.

To add members to the chief approval team

- 1. In Manager, select the category **Attestation | Basic configuration data | Chief approval team**.
- 2. Select **Assign employees** in the task view.

In **Add assignments**, assign the employees who are authorized to approve all attestations.



To remove an assignment

- Select the employee and double-click

 ✓.
- 3. Save the changes.

Detailed information about this topic

• Attestation through chief approval team on page 90

Standard reasons for attestation

For attestations, you can specify reasons in the Web Portal that explain the individual approval decisions. You can freely formulate this text. You also have the option to predefine reasons. The attestors can select a suitable text from these standard reasons in the Web Portal and store it with the attestation case.

Standard reasons are displayed in the attestation history.

To edit standard reasons

- 1. Select Attestation | Basic configuration data | Standard reasons.
- 2. Select a standard reason in the result list and run **Change master data**.
 - OR -
 - Click in the result list.
- 3. Edit the master data for a standard reason.
- 4. Save the changes.

Enter the following properties for the standard reason.



Table 8: General master data for a standard reason

Property	Description
Standard reason	Reason text as displayed in the Web Portal and in the attestation history
Description	Spare text box for additional explanation.
Automatic Approval	Specifies whether the reason text is only used for automatic approvals by the One Identity Manager. This standard reason cannot be selected by manual approvals in the Web Portal. Do not set the option if the you want to select the standard reason in the Web Portal.
Additional text required	Specifies whether an additional reason should be entered in free text for the attestation
Usage type	Usage type of standard reason Assign one or more usage types to allow filtering of the standard reasons in theWeb Portal.

Predefined Standard Reasons

One Identity Manager provides predefined standard reasons. These standard reasons are entered into the attestation case in the case of automatic approval by One Identity Manager.

To display predefined standard reasons

• In Manager, select the **Attestation | Basic configuration data | Standard reasons | Predefined** category.

Attestation policies

Attestation policies specify the concrete conditions for attestation. Use the master data form to enter the attestation procedure, approval policy and the schedule. You can use a WHERE clause to limit the attestation objects.

To edit attestation polices

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select an attestation policy in the result list and run Change master data.
 - OR -

Click in the result list.



- 3. Edit the master data for the attestation policy.
- 4. Save the changes.

General master data for attestation policies

Enter the following data for attestation policies.

Table 9: General master data for attestation policies

Property	Description
Attestation policy	Name of the attestation policy.
Attestation procedure	Attestation procedure used for attesting. Attestation procedures are displayed in a menu grouped by attestation type.
Approval policies	Approval policy for determining the attestor for the attestation objects.
Owner	Creator of the attestation policy. The name of the user logged into One Identity Manager is entered here by default. This can be changed.
Time required (days)	Number of days within which a decision must be made over the attestation. Enter 0 if you do not want to specify a particular processing period.
	One Identity Manager does not stipulate which actions are carried out if processing times out. Define your own custom actions or evaluations to deal with this situation.
Description	Spare text box for additional explanation.
Risk index	Specifies the risk for the company if attestation for this attestation policy is denied. Use the slider to enter a value between ${\bf 0}$ and ${\bf 1}$.
	• 0: No risk
	• 1: The denied attestation is a problem.
	This input field is only visible if the configuration parameter ${\bf QER}$ ${\bf CalculateRiskIndex}$ is activated.
Risk index (reduced)	Show the risk index taking mitigating controls into account. The risk index for an attestation policy is reduced by the Significance reduction value for all assigned mitigating controls.
	This input field is only visible if the configuration parameter QER CalculateRiskIndex is activated. The value is calculated by the One Identity Manager and cannot be edited.
Calculation schedule	Schedule for running attestation. Attestation cases are started automatically at the times specified by the schedule.



Property	Description
Deactivated	Specifies whether the attestation policy is disabled or not.
	Attestation cases cannot be added to disabled attestation policies and, therefore, no attestation is done. Disabled attestation policies can be deleted.
	Completed attestation cases can be deleted once the attestation policy is disabled.
Close obsolete tasks automat- ically	Specifies whether pending attestation cases are aborted if new ones are added.
	If attestation is started and this option is set, new attestation cases are created according to the condition. All pending, obsolete attestation cases for newly determined attestation objects of this attestation policy are aborted. Attestation cases for attestation objects that are not recalculated, remain intact.
Obsolete tasks limit	Specifies the maximum number of closed attestation cases for each attestation object that should remain in the database when closed attestation cases are deleted.
	• 0: No attestation cases are deleted.
	 > 0: The given number of closed attestation cases for each attestation object to remain in the database.
Reason for decision	Reason which is given if the option Close obsolete tasks automatically is set and pending attestation cases are automatically closed.
Output format	Format in which the report is generated.
	This menu is only visible if the QER Attestation AllowAllReportTypes configuration parameter is set. If the configuration parameter is not set, the default PDF format is used because it is the only format that is version compatible.
Edit connection	Starts the WHERE clause wizard. Use this wizard to create a condition to determine the attestation objects from the database table specified in the attestation procedure.
Condition	Data query for finding attestation objects.
	This option is only available if the task Show condition has been run beforehand.
Attestation with multi- factor authen- tication	Attestation of this attestation policy requires multi-factor authentication.



NOTE: You can only edit attestation policies in the Web Portal that were created in the Web Portal. You will see a corresponding message on the master data form as to whether the attestation policy as created in the Web Portal.

If you want to edit attestation policies like this, create a copy in the Manager.

For detailed information about editing attestation policies in the Web Portal, see the One Identity Manager Web Portal User Guide.

Detailed information about this topic

- Showing or hiding conditions on page 33
- Schedules on page 17
- Disabling attestation policies on page 34
- Mitigating controls on page 138
- Setting up multi-factor authentication for attestation on page 81
- Creating a copy on page 33

Related topics

- Deleting attestation cases on page 98
- Deleting attestation policies on page 34

Risk assessment

You can use One Identity Manager to evaluate the risk of attestation cases. To do this, enter a risk index for the attestation policy. The risk index specifies the risk involved for the company in connection with the data to be attested. The risk index is given as a number in the range $0 \dots 1$. By doing this you specify whether data to be attested is considered not to be a risk (risk index = 0) or whether every denied attestation poses a problem (risk index = 1).

The risk that attestations will be denied approval can be reduced by using the appropriate mitigating controls. Enter these controls as mitigating controls in One Identity Manager. You reduce the risk by the value entered as the significance reduction on the mitigating control. This value is used to calculate the reduced risk index for the attestation policy.

You can create several reports with the Report Editor to evaluate attestation cases depending on the risk index. For more detailed information, see the *One Identity Manager Configuration Guide*.

Risk assessments can be carried out when the **QER | CalculateRiskIndex** configuration parameter is enabled. For more detailed information, see the *One Identity Manager Risk Assessment Administration Guide*.



Detailed information about this topic

Mitigating controls on page 138

Default attestation policies

One Identity Manager provides default attestation policies for default attestation of new users and recertification of all employees stored in the One Identity Manager database. In addition to this, default attestation policies are provided through which various roles, memberships in roles, and system entitlements can be attested.

To display default attestation policies

• In the Manager, select **Attestation | Attestation policies | Predefined**.

You can customize the following properties for default attestation policies:

- Approval policies (if several approval policies can be assigned)
- Owner
- Processing time
- Risk index
- · Calculation schedule
- Deactivated
- · Close obsolete tasks automatically
- Obsolete tasks limit
- Reason for decision
- 1 TIP: If you want to limit the number of attestation objects for default attestation polices, create a copy of the default attestation policy. You can edit the condition in the copy.
- NOTE: You can edit attestation policies, whose condition is stored as a definition (XML), in the Web Portal. The definition (XML) cannot be edited in the Manager. For detailed information, see *One Identity Manager Web Portal User Guide*.

Additional tasks for attestation policies

After you have entered the master data, you can run the following tasks.



The attestation policy overview

You can see the most important information about an attestation policy on the overview form.

To obtain an overview of an attestation policy

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list.
- 3. Select **Attestation policy overview** in the task view.

Assigning approvers

Use this task to assign employees that can be determined as approvers in an attestation case to the selected attestation policy.

To assign approvers to an attestation policy

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list.
- 3. Select **Assign approver** from the task list.

Assign the approvers in **Add assignments**.

• TIP: In **Remove assignments**, you can remove the assignment of approvers.

To remove an assignment

- Select the approver and double click

 ✓.
- 4. Save the changes.

Detailed information about this topic

Selecting attestors on page 57

Assigning compliance frameworks

Use this task to specify which compliance frameworks are relevant for the selected attestation policy. Compliance frameworks are used for classifying attestation policies, compliance rules and company policies according to regulatory requirements.

To assign compliance frameworks to an attestation policy

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list.



3. Select **Assign compliance frameworks** from the task list.

Assign the compliance frameworks in **Add assignments**.

TIP: In **Remove assignments**, you can remove the assignment of compliance frameworks.

To remove an assignment

- Select the compliance framework and double-click ♥.
- 4. Save the changes.

Mitigating controls

Mitigating controls describe controls that are implemented if an attestation rule was violated. The attestation can be approved after the next attestation run, once controls have been applied.

To edit mitigating controls

• In Designer, enable the configuration parameter **QER | CalculateRiskIndex**.

Detailed information about this topic

- Mitigating controls on page 138
- Assigning mitigating controls on page 31
- Creating mitigating controls on page 32

Assigning mitigating controls

Specify which mitigating controls apply to the selected attestation policy.

To assign mitigating controls to an attestation policy

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list.
- 3. Select **Assign mitigating controls** from the task list.

In **Add assignments**, assign the mitigating controls.

1 TIP: In **Remove assignments**, you can remove the assignment of mitigating controls.

To remove an assignment

- 4. Save the changes.



Creating mitigating controls

To create a mitigating control for attestation policies

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select an attestation policy in the result list.
- 3. Select **Assign mitigating controls** from the task list.
- 4. Select Create mitigating controls.
- 5. Enter the master data for the mitigating control.
- 6. Save the changes.
- 7. Select **Assign attestation polices** in the task view.
- 8. In **Add assignments**, double-click the attestation policies that are to be assigned.
- 9. Save the changes.

Detailed information about this topic

Mitigating controls on page 138

Running attestation for single objects

Use this task to start attestations independently from a schedule. If you run the task, a separate window is opened. Select the objects to be attested now from a list of all attestation objects. The selection is one-off.

The **Close obsolete tasks automatically** option is not taken into account for the selected attestation objects.

To start attestation for the selected objects

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list. Select **Change master data**.
- 3. Select Run attestation cases for single objects....
 - This opens a separate window.
- 4. In the **Attestation** column, select every object for which attestation is to be run.
- 5. Click Run.

Attestation cases are generated for the selected attestation objects. As soon as DBQueue Processor has processed the task, you will see the newly created attestation cases in the navigation view under **Attestation runs** | <attestation policy> | Attestation runs | <year> | <month> | <day> | Pending attestations.

6. Click Close.



Showing or hiding conditions

The condition for finding attestation objects can be viewed and edited in the Where Clause Wizard. The SQL query for this condition can be displayed on the master data form.

To show the condition for finding attestation objects on the master data form

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list and run **Change master data**.
- 3. Select the task **Show condition** in the task view.

This displays the **Condition** text box on the master data form. The condition is written like a database query Where clause. You can edit it directly.

To hide the condition for finding attestation objects

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list and run **Change master data**.
- 3. Select **Hide condition** in the task view.

The input field **Condition** is no longer displayed on the master data form.

Creating a copy

You can make copies of attestation policies and use them to modify default attestation policies, for example.

To copy an attestation policy

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list.
- 3. Select Create copy in the task view.
- 4. Confirm the security prompt with **Yes**.

The attestation policy copy is displayed on the master data form with the name **Copy** of **<Name of original attestation policy**>. You can edit this attestation policy.

Showing selected objects

To show a list of attestations found

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list and run **Change master data**.
- Select Show selected objects in the task view.



An additional **Result** tab is shown on the master data form. This displays a list of attestation objects found through the condition.

Deleting attestation policies

1 IMPORTANT: Do not delete attestation policies, for audit reasons.

Attestation policies may still be removed from the One Identity Manager database under specific conditions. Ensure that the attestation policy is archived when deleted.

For detailed information about data archiving, see the *One Identity Manager Configuration Guide*.

Prerequisite

• The attestation policy is disabled.

To delete an attestation policy

- 1. In the Manager, select Attestation | Attestation policies | Disabled policies.
- 2. Select the attestation policy in the result list and run **Change master data**.
- 3. Select **Delete attestation policy** in the task view.
- 4. Confirm the security prompt with **Yes**.

The attestation policy is deleted. All associated attestation cases, approval workflows and the attestation history are deleted.

Related topics

Disabling attestation policies on page 34

Disabling attestation policies

Attestations are run when the schedule assigned to an attestation policy is enabled. You can disabled attestation policies to prevent attestation cases being created for individual attestation policies.

TIP: Numerous default attestation policies are supplied with One Identity Manager. Check which of the default attestation policies are relevant for your data situation when you set up your database. Disable all unnecessary attestation policies.

To disable an attestation policy

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list and run **Change master data**.



- 3. Set **Disabled**.
- 4. Save the changes.

Custom mail templates for notifications

A mail template consists of general master data such as target format, important or mail notification confidentiality and one or more mail definitions. Mail text is defined in several languages in the mail template. This ensures that the language of the recipient is taken into account when the email is generated.

There is a One Identity Manager in the Mail Template Editor to simplify writing notifications. You can use Mail Template Editor to create and edit mail texts in WYSIWYG mode.

Creating and editing attestation mail templates

To edit mail templates

 In Manager, select the category Attestation | Basic configuration data | Mail templates.

This shows all the mail templates that can be used for attestation cases in the result list.

- 2. Select a mail template in the result list and run Change master data.
 - OR -

Click in the result list.

This opens the mail template editor.

- 3. Edit the mail template.
- 4. Save the changes.

Detailed information about this topic

- General properties of a mail template on page 35
- Creating and editing a mail definition on page 37

General properties of a mail template

The following general properties are displayed for a mail template:



Table 10: Mail template properties

	• • •
Property	Meaning
Mail template	Name of the mail template. This name will be used to display the mail templates in the administration tools and in Web Portal. Translate the given text using the button.
Base object	Mail template base object. A base object only needs to be entered if the mail definition properties of the base object are referenced.
	Use the base object AttestationCase or AttestationHelper for notifications about attestation.
Report (parameter set)	Report, made available through the mail template.
Description	Mail template description. Translate the given text using the $^{f C}$ button.
Target format	Format in which to generate email notification. Permitted values are:
	 HTML: The email notification is formatted in HTML. Text formats, for example, different fonts, colored fonts or other text formatting can be included in HTML format.
	 TXT: The email notification is formatted as text. Text format does not support bold, italics or colored font or other text formatting. Images displayed directly in the message are not supported.
Design type	Design in which to generate the email notification. Permitted values are:
	 Mail template: The generated email notification contains the mail body in accordance with the mail definition.
	 Report: The generated email notification contains the report specified under Report (parameter set) as its mail body.
	 Mail template, report in attachment: The generated email notification contains the mail body in accordance with the mail definition. The report specified under Report (parameter set) is attached to the notification as a PDF file.
Importance	Importance for the email notification. Permitted values are Low , Normal , and High .
Confidentiality	Confidentiality for the email notification. Permitted values are Normal , Personal , Private , and Confidential .
Can unsubscribe	Specifies whether the recipient can unsubscribe email notification. If this option is set, the emails can be unsubscribed through the Web Portal.
Deactivated	Specifies whether this mail template is disabled.
Mail definition	Unique name for the mail definition.



Property	Meaning
Language	Language which applies to the mail template. The recipient's language preferences are taken into account when an email notification is generated.
Subject	Subject of the email message
Mail body	Content of the email message.

Creating and editing a mail definition

Mail texts can be defined in these different languages in a mail template. This ensures that the language of the recipient is taken into account when the email is generated.

To create a new mail definition

- 1. Open the mail template in Mail Template Editor.
- 2. Click the disputs button next to the Mail definition list.
- 3. In the result list, select the language for the mail definition in the **Language** menu. All active languages are shown. To use another language, in Designer, enable the corresponding countries. For more detailed information, see the *One Identity Manager Configuration Guide*.
- 4. Enter the subject in **Subject**.
- 5. Edit the mail text in the Mail definition view with the help of the Mail Text Editor.
- 6. Save the changes.

To edit an existing mail definition

- 1. Open the mail template in Mail Template Editor.
- 2. Select the language in Mail definition.
- 3. Edit the mail subject line and the body text.
- 4. Save the changes.

Using base object properties

In the subject line and body text of a mail definition, you can use all properties of the object entered under **Base object**. You can also use the object properties that are referenced by foreign key relation.

To access properties use dollar notation. For more detailed information, see the *One Identity Manager Configuration Guide*.



Example

An attestor should receive email notification of new attestations.

Table 11: Email notification properties

Property Value

Base object	AttestationHelper
Subject	New attestations
Mail body	Dear \$FK(UID_PersonHead).Salutation[D]\$ \$FK(UID_ PersonHead).LastName\$,
	There are new attestations pending for the attestation policy "\$FK(UID_ AttestationCase).UID_AttestationPolicy[D]\$".
	Created: \$FK(UID_AttestationCase).PolicyProcessed:Date\$
	You can see this request in the "One Identity Manager Self Service Portal".
	Best regards

Use of Hyperlinks in the Web Portal

You can add hyperlinks to Web Portal in the mail text of a mail definition. If the recipient clicks on the hyperlink in the email, the Web Portal is opened on that web page and further actions can be carried out. In the default version, this method is implemented in attestations.

Prerequisites for using this method

• The **QER | WebPortal | BaseURL** configuration parameter is enabled and contains the URL path to Web Portal. You edit the configuration parameter in Designer.

```
http://<server name>/<application>
with:
<server name> = name of server
<application> = path to the Web Portal installation directory
```

To add a hyperlink to Web Portal in the mail text

- 1. Click the position in the mail text of the mail definition where you want to insert a hyperlink.
- 2. Open the **Hyperlink** context menu and enter the following information.
 - **Display text**: Enter a caption for the hyperlink.
 - Link to: Select the File or website option.



- Address: Enter the address of the page in the Web Portal that you want to open.
 - NOTE: One Identity Manager provides a number of default functions, which you can use to create hyperlinks in Web Portal.
- 3. To accept the input, click **OK**.

Default Functions for Creating Hyperlinks

Several default functions are available to help you create hyperlinks. You can use the functions directly when you add a hyper ink in the mail body of a mail definition or in processes

Direct function input

You can reference a function when you add a Hyperlink in the **Address** field of the **Hyperlink** context menu.

\$Script(<Function>)\$

Example:

\$Script(VI_BuildAttestationLink_Approve)\$

Default Functions for Requests

The script VI_BuildAttestationLinks contains a collection of default functions for composing hyperlinks to directly grant or deny approval of requests from email notifications.

Table 12: Functions of the VI_BuildAttestationLinks script

Function	Usage
VI_BuildAttestationLink_Show	Opens the attestation page in the Web Portal.
VI_BuildAttestationLink_ Approve	Approves an attestation and opens the attestation page in the Web Portal.
VI_BuildAttestationLink_Deny	Denies an attestation and opens the attestation page in the Web Portal.
VI_BuildAttestationLink_ AnswerQuestion	Opens the page for answering a question in the Web Portal.
VI_BuildAttestationLink_ Pending	Opens the page with pending attestations in the Web Portal.



Customizing email signatures

Configure the email signature for mail templates using the following configuration parameter. Edit the configuration parameters in the Designer.

Table 13: Configuration parameters for email signatures

Configuration parameter	Description	
Common MailNotification Signature	Data for the signature in email automatically generated from mail templates.	
Common MailNotification Signature Caption	Signature under the salutation.	
Common MailNotification Signature Company	Company name.	
Common MailNotification Signature Link	Link to the company's website.	
Common MailNotification Signature LinkDisplay	Display text for the link to the company's website.	

VI_GetRichMailSignature combines the components of an email signature according to the configuration parameters for use in mail templates.

Copying mail templates for attestation

To copy a mail template

In Manager, select the category Attestation | Basic configuration data | Mail templates.

This shows all the mail templates that can be used for attestation cases in the result list.

- 2. Select the mail template that you want to copy in the result list and run **Change** master data.
- 3. Select Copy mail template.
- 4. Enter the name of the new mail template in **Name of copy**.
- 5. Click **OK**.



Displaying attestation mail templates previews

To display a mail template preview

In Manager, select the category Attestation | Basic configuration data | Mail templates.

This shows all the mail templates that can be used for attestation cases in the result list.

- 2. Select a mail template in the result list and run **Change master data**.
- 3. Select Preview.
- 4. Select the base object.
- Click OK.

Deleting mail templates for attestation

To delete a mail template

 In Manager, select the category Attestation | Basic configuration data | Mail templates.

This shows all the mail templates that can be used for attestation cases in the result list.

- 2. Select the template in the result list.
- 3. Click in the result list.
- 4. Confirm the security prompt with Yes.

Custom notification processes

Set up customized processes to send more email notifications within an attestation case. You can use following events for generating processes.

Table 14: Events for the AttestationHelper object

Event	Triggered by
DecisionRequired	New attestation case created
	Move to the next approval level
Remind	Reminder interval expired



Table 15: Events for the AttestationCase object

Event	Triggered by
Granted	Approval granted for an approval step.
Dismissed	Approval denied for an approval step.
OrderGranted	Approval granted for an entire approval procedure.
FinalDismissed	Approval denied for an entire approval procedure.
QueryToPerson	Making a query
AnswerFromPerson	Answering a query
RecallQuery	Recalling a query
Escalate	Attestation case escalated.
Aborted	Attestation case aborted.
Canceled	Obsolete attestation case aborted.

For detailed information about creating processes, see the *One Identity Manager Configuration Guide*.



Approval processes for attestation cases

All attestation procedures are subject to a defined approval process. During this approval process, authorized employees grant or deny approval for attestation objects. You can configure this approval process in various ways and therefore customize it to meet your company policies.

You define approval policies and approval workflows for approval processes. Specify the approval workflows to apply to the attestation cases in the approval policies. Use approval workflows to find out, which employees in which order, can grant or deny attestation. An approval workflow can contain several approval levels and several approval steps. A special approval procedure is used to determine the attestors in each approval step.

Detailed information about this topic

- Approval policies for attestations on page 43
- Approval workflow for attestations on page 46
- Editing approval levels on page 50
- Default approval procedures on page 58

Approval policies for attestations

One Identity Manager uses approval policies to determine the attestor for each attestation case.

To edit an approval policy

- 1. Select Attestation | Basic configuration data | Approval policies.
- 2. Select an approval policy in the result list and run Change master data.
 - OR -
 - Click do in the result list.



- 3. Edit the approval policy master data.
- 4. Save the changes.

General master data for approval policies

Enter the following master data for an approval policy. If you add a new approval step, you must fill out the compulsory fields.

Table 16: General master data for approval policies

Property	Description
Approval policies	Approval step name.
Approval	Workflow for finding attestors.
workflow	Select any approval workflow from the menu or click $\colone{1}{c}$ to set up a new approval workflow.
Mail templates	Mail template used to create email notifications for granting, denying, extending, unsubscribing, or canceling an attestation or for giving notice of its expiry.
Description	Spare text box for additional explanation.

Detailed information about this topic

- Setting up approval workflows on page 49
- Notifications in the attestation process on page 99

Default approval policies

One Identity Manager provides a default approval policy for default attestation of new users and recertification of all employees stored in the One Identity Manager database. Moreover, default approval policies are supplied through which different roles and system entitlements mapped in the Unified Namespace can be attested. You can use default approval policies for creating attestation policies in the Web Portal.

To edit default approval policies

In Manager, select the category Attestation | Basic configuration data |
 Approval policies | Predefined.

For detailed information about using default approval policies, see the *One Identity Manager Web Portal User Guide*.



Related topics

- User attestation and recertification on page 123
- Default attestation and withdrawal of entitlements on page 114

Additional tasks for approval policies

After you have entered the master data, you can run the following tasks.

Editing approval workflows

Here, you can edit the approval workflow assigned to the approval policy.

To edit the assigned approval workflow

- 1. Select Attestation | Basic configuration data | Approval policies.
- 2. Select the approval policy in the result list.
- Select 1. Editing approval workflows.
 This opens the Workflow Editor.

Detailed information about this topic

· Working with the workflow editor on page 46

Validity checking

Once you have edited an approval policy you need to test it. This checks whether the approval steps can be used in the approval workflows in this combination. Non-valid approval steps are displayed in the error window.

To test an approval policy

- In Manager, select the category Attestation | Basic configuration data | Approval policies.
- 2. Select the approval policy in the result list.
- 3. Select Validity check.



Approval workflow for attestations

You need to allocate an approval workflow to the approval policies in order to find the attestors. In an approval workflow, you specify the approval procedures, the number of attestors and a condition for selecting the attestors.

Use the workflow editor to create and edit approval workflows.

To edit an approval workflow


- 1. In Manager, select the category **Attestation | Basic configuration data | Approval workflows**.
- 2. Select the approval workflow in the result list and run **Change master data**.
 - OR -
 - Click in the result list.
 - This opens the Workflow Editor.
- 3. Edit the approval workflow master data.
- 4. Save the changes.

Working with the workflow editor

Use the workflow editor to create and edit approval workflows. The workflow editor allows approval levels to be linked together. Multi-step approval processes are clearly displayed in a graphical form.



Figure 1: workflow editor



Approval levels and approval steps belonging to the approval workflow are edited in the workflow editor using special control elements. The workflow editor contains a toolbox. The toolbox methods are activated or deactivated depending on how they apply to the control. You can move the layout position of the control elements in the workflow editor with the mouse or these can be moved automatically.

Table 17: Entries in the toolbox

Control	Method	Meaning
Workflow	Edit	Edit the properties of the approval workflow.
	Layout automatically	The workflow elements are aligned automatically. The workflow layout is recalculated.
Approval	Add	A new approval level is added to the workflow.
levels	Edit	Edit the properties of the approval workflow.
	Delete	Deletes the approval level.
Approval	Add	Add a new approval step to the approval level.
steps	Edit	Edit the properties of the approval step.
	Delete	Deletes the approval step.
Assignments	Remove positive	The Approved connector for the selected approval level is deleted.



Control	Method	Meaning
	Remove negative	The Deny connector for the selected approval level is deleted.
	Remove reroute	The Reroute connector for the selected approval level is deleted.
	Remove escalation	The Escalate connector for the selected approval level is deleted.

Each of the controls has a properties window for editing the data of the approval workflow, level or step. To open the properties window, choose **Toolbox** | **Control**> | **Edit**.

To delete a control, select the element and choose **Toolbox | <Control> | Delete**.

Individual elements are linked to each other with a connector. Activate the connection points with the mouse. The mouse cursor changes into an arrow icon for this. Hold down the left mouse button and pull a connector from one connection point to the next.

Figure 2: Approval workflow connectors






Table 18: Approval workflow connectors

Connector	Meaning
Approve	Link to next approval level if the current approval level was granted approval.
Deny	Link to next approval level if the current approval level was not granted approval.
Reroute	Link to another approval level to by-pass the current approval.
Escalation	Connection to another approval level when the current approval level is escalated after timing out.

By default, a connection between workflow elements and level elements is created immediately when a new element is added. If you want to change the level hierarchy, drag a new connector to another level element.

Alternatively, you can release connectors between level elements using **Toolbox** | **Assignments**. To do this, mark the level element where the connector starts. Then add a new connector.

Different icons are displayed on the level elements depending on the configuration of the approval steps.

Table 19: Icons on the level elements

Icon	Meaning
%	The approval decision is made by the system.
<u></u>	The approval decision is made manually.
\sim	The approval step contains a reminder function.
Θ	The approval step contains a timeout.

Changes to individual elements in the workflow do not take place until the entire approval workflow is saved. The layout position in the workflow editor is saved in addition to the approval policies.

Setting up approval workflows

An approval workflow consists of one or more approval levels. An approval level can contain one approval step or several parallel approval steps. Within the attestation process, all of the approval steps for one approval level must be executed before the next approval level is called. Use connectors to set up the sequence of approval levels in the approval workflow.

When you add a new approval workflow, the first thing to be created is a new workflow element.



To edit approval level properties

- 1. Open the Workflow Editor.
- 2. Select Toolbox | Workflow | Edit.
- 3. Edit the workflow properties.
- 4. Click OK.

Table 20: Approval workflow properties

Property	Meaning
Name	Approval workflow name
System abort (days)	Number of days to elapse after which the approval workflow, and therefore the system, automatically ends the entire attestation procedure.
Description	Spare text box for additional explanation.

Detailed information about this topic

Aborting an attestation case on timeout on page 89

Editing approval levels

An approval level provides a method of grouping individual approval steps. All the approval steps in one approval level are executed in parallel. All the approval steps for different approval levels are executed one after the other. You use the connectors to specify the order of execution.

Specify the individual approval steps in the approval levels. At least one approval step is required per level. Enter the approval steps first before you add an approval level.

To add an approval level

- Select Toolbox | Approval levels | Add.
 This opens the properties dialog for the first approval step.
- 2. Enter the approval step properties.
- 3. Save the changes.

You can edit the properties of an approval level as soon as you have added an approval level with at least one approval step.

To edit approval level properties

- 1. Select the approval level.
- 2. Select Toolbox | Approval levels | Edit.



- 3. Enter a display name for the approval level.
- 4. Save the changes.
- NOTE: You can define more than one approval step for each approval level. In this case, the attestors of an approval level can make a decision about an attestation case in parallel rather than sequentially. The attestation case cannot be presented to the attestors at the next approval level until all approval steps in one approval level have been completed in the attestation procedure.

To add more approval steps to an approval level

- 1. Select the approval level.
- 2. Select Toolbox | Approval levels | Add....
- 3. Enter the approval step properties.
- 4. Save the changes.

Related topics

- Properties of an approval step on page 51
- Editing approval steps

Editing approval steps

To edit approval level properties

- 1. Select the approval step.
- 2. Select Toolbox | Approval steps | Edit.
- 3. Edit the approval step properties.
- 4. Save the changes.

Detailed information about this topic

Properties of an approval step on page 51

Properties of an approval step

On the **General** tab, enter the following data: On the **Mail templates** tab, you select the mail templates for generating e-mail notifications. If you add a new approval step, you must fill out the required fields.



Table 21: General properties of an approval step

Property	Meaning		
Single step	Approval step name.		
Approval procedure	Procedure to use for determining the attestors		
Role	Hierarchical role from which the attestors are to be determined using the default approval procedures OM and OR		
Fallback approver	Application role whose members are authorized to approve attestation cases if an attestor cannot be determined through the approval procedure. Assign an application from the menu.		
	To create a new application role, click . Enter the application role name and assign a parent application role. For detailed information, see the <i>One Identity Manager Authorization and Authentication Guide</i> .		
	NOTE: The number of approvers is not applied to the fallback approvers. The approval step is considered approved the moment as soon as one fallback approver has approved the request.		
Condition	Condition for calculating approval with approval procedures CD, EX or WC.		
Number of approvers	Number of attestors required to approve an attestation case. Use this number to further restrict the maximum number of approvers of the implemented approval procedure.		
	If there are several people allocated as approvers, then this number specifies how many people from this group have to approve an attestation case. A request can only be passed up to next level afterwards.		
	If not enough attestors can be found, the approval step is presented to the fallback approvers. The approval step is considered approved as soon as one fallback approver has approved the attestation case.		
	If you want approval decisions to be made by all the employees found using the applicable approval procedure, for example all members of a role (default approval procedure OR), enter the value -1 . This overrides the maximum number of attestors defined in the approval procedure.		
	The number of approvers defined in an approval step is not taken into account in the approval procedures CD, EX or WC.		
Description	Spare text box for additional explanation.		
Approval	Reason entered in the attestation case if approval is automatically granted.		
reason	This field is only shown for the approval procedures CD, EX and WC.		
Reject reason	Reason entered in the attestation case and the attestation history, if approval is automatically denied.		
	This field is only shown for the approval procedures CD, EX and WC.		




Property Meaning

Reminder interval (hours)

Number of working hours to elapse after which the attestor is notified by mail that there are still pending attestation cases for attestation.

The reminder interval is set to 30 minutes, by default. To change this interval, modify the **Checks reminder interval and timeout of attestation cases** schedule.



If more than one attestor was found, each attestor will be notified. The same applies if an additional attestor has been assigned.

Base Module Administration Guide.

If an attestor delegated the approval, the time point for reminding the delegation recipient is recalculated. The delegation recipient and all the other attestors are notified. The original attestor is not notified.

If an attestor has made an inquiry, the time point for reminding the queried employee is recalculated. As long as the inquiry has not been answered, only this employee is notified.

TimeOut (working hours)

Number of working hours to elapse after which the approval step is automatically granted or denied approval.

The timeout is check every 30 minutes, by default. To change this interval, modify the **Checks reminder interval and timeout of attestation cases** schedule.

The working hours of the respective approver are taken into account when the time is calculated.

NOTE: Ensure that a state and/or county is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about employees' calculating working hours, see the One Identity Manager Identity Management Base Module Administration Guide.

If more than one approver was found, the an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.

If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.



Property	Meaning
	If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is not recalculated.
Timeout	Action, which is executed if the timeout expires.
behavior	 Approved: The attestation case is approved in this approval step. The next approval level is called.
	 Deny: The attestation case is denied in this approval step. The approval level for denying is called.
	 Escalation: The attestation case is escalated. The escalation approval level is called.
	 Abort: the approval step and, therefore, the attestation case, are canceled.
Additional approver possible	Specifies whether a current attestor is allowed to instruct another employee as an attestor. This additional attestor has parallel authorization to make approvals for the current attestation case. The attestation case is not passed on to the next approval level until both attestors have made a decision.
	This option can only be set for approval levels with a single, manual approval step.
Approval can be delegated	Specifies whether a current attestor can delegate the attestation to another person. This employee is added to the current approval step as the attestor. This employee then makes the approval decision instead of the attestor who made the delegation.
	This option can only be set for approval levels with a single, manual approval step.
Approval by affected employee	Specifies whether the employee who is affected by the approval decision can also approve it. If this option is set, employees to be attested can attest themselves.
	If this option is not set, use the QER Attestation PersonToAt- testNoDecide configuration parameter to define whether the employees to be attested can attest themselves.
Do not show in approval history	Specifies whether or not the approval step should be displayed in the attestation history. For example, this behavior can be applied to approval steps with the CD - calculated approval procedure, which are used only for branching in the approval workflow. It It makes it easier to follow the attestation bistory.

Detailed information about this topic

- Notifications in the attestation process on page 99
- Reminding attestors on page 101

ation history.

• Escalating an attestation case on page 84



- Automatic approval on timeout on page 87
- Aborting an attestation case on timeout on page 89
- Finding attestors using a specified role on page 68
- Calculated approval on page 70
- Approvals to be made externally on page 71
- Waiting for further approval on page 72
- Prevent attestation by employee awaiting attestation on page 82

Related topics

- Selecting attestors on page 57
- Attestors cannot be established on page 86
- Attestation through chief approval team on page 90

Connecting approval levels

When you set up an approval workflow with several approval levels, you have to connect each level with another. You may create the following links:

Table 22: Links to approval levels

Link	Description	
Approve	Link to next approval level if the current approval level was granted approval.	
Deny	Link to next approval level if the current approval level was not granted approval.	
Reroute Link to another approval level to by-pass the current approval.		
	Attestors can pass the approval decision through another approval level, for example, if approval is required by a manager in an individual case To do this, create a connection to the approval level to which the approval can be rerouted. This way approvals can also be rerouted to a previous approval level, for example, if an approval decision is considered not to be well founded.	
	It is not possible to reroute approval steps with the approval procedures EX, CD, SB or WC.	
Escalation	Link to another approval level when the current approval level is escalated after timing out.	

If there are no further approval levels after the current approval level, the attestation case is considered approved if the approval decision was to grant approval. If approval is not



granted, the attestation case is considered to be finally denied. The attestation procedure is closed in both cases.

Additional tasks for approval workflows

After you have entered the master data, you can run the following tasks.

The approval workflow overview

To obtain an overview of an approval workflow

- 1. In Manager, select the category **Attestation | Basic configuration data | Approval workflows**.
- 2. Select the approval workflow in the result list.
- 3. Select Approval workflow overview.

Copying approval workflows

For example, you can copy default approval workflows in order to customize them.

To copy an approval workflow

- 1. In Manager, select the category **Attestation | Basic configuration data | Approval workflows**.
- 2. Select an approval workflow in the result list and run **Change master data**.
- 3. Select Copy workflow.
- 4. Enter a name for the copy.
- 5. Click **OK** to start copying.
 - OR -

Click Cancel to cancel copying.

- 6. To edit the copy immediately, click **Yes**.
 - OR -

To edit the copy later, click No.

Deleting approval workflows

The approval workflow can only be deleted if it is not assigned to an approval policy.



To delete an approval workflow

- 1. Remove all assignments to approval policies.
 - a. Check to which approval policies the approval workflow is assigned.
 - b. Go to the master data form for the approval policy and assign a different approval workflow.
- 2. In Manager, select the category **Attestation | Basic configuration data | Approval workflows**.
- 3. Select an approval workflow in the result list.
- 4. Click .
- 5. Confirm the security prompt with **Yes**.

Detailed information about this topic

- The approval workflow overview on page 56
- General master data for approval policies on page 44

Default approval workflows

One Identity Manager provides a default approval workflow for default attestation of new users and recertification of all employees stored in the One Identity Manager database. Moreover, default approval workflows are supplied through which different roles and system entitlements mapped in the Unified Namespace can be attested. You can use default approval policies for creating attestation policies in the Web Portal.

To edit default approval workflows

In Manager, select the category Attestation | Basic configuration data |
 Approval workflows | Predefined.

For detailed information about using default approval workflows, see the *One Identity Manager Web Portal User Guide*.

Related topics

- User attestation and recertification on page 123
- Default attestation and withdrawal of entitlements on page 114

Selecting attestors

One Identity Manager can make approvals automatically in an attestation procedure or through attestors. An attestor is an employee or a group of employees who can grant or



deny an attestation case within an attestation procedure. It takes several approval procedures to grant or deny approval. You specify in the approval step which approval procedure should be used.

If there are several people are determined as approvers by an approval procedure, the number given in the approval step specifies how many people must approve the step. A request can only be passed up to next level afterwards. The attestation procedure is aborted if an approver cannot be found for an approval step.

One Identity Manager provides approval procedures by default. You can also define your own approval procedures.

The DBQueue Processor calculates which employee is authorized as approver in which approval level. Take into account the special cases for each approval procedure when setting up the approval workflows to determine those authorized to grant approval.

Default approval procedures

To display default approval procedures

Select the Attestation | Basic configuration data | Approval procedures |
 Predefined category.

The following approval procedures are defined to select the responsible attestors, by default.

Table 23: Approval procedures for attestation

Procedure Name	Attestors
AA - Attestor for the role to attest	Attestor of the organization (department, cost center, location), business role, or IT Shop if assignments of system entitlements or system roles to roles are attested.
	 Attestors for departments, cost centers and locations must be assigned to the application role Identity Management Organizations Attestors.
	 Attestors for business roles must be assigned to the application role Identity Management Business roles Attestors.
	 Attestors for requests must be assigned to the Request & Fulfillment IT Shop Attestors application role.
	For more information, see Finding attestors using attestation objects on page 63.
AD - Attestor of recipient's	Attestor of the department to which the attestation object is primarily assigned.
department	Attestors for departments must be assigned to the Identity



Procedure Name	Attestors
	Management Organizations Attestors application role.
	For more information, see Finding attestors using the role of the employee to be attested on page 63.
AL - Attestor for recipient's location	Attestor of the location to which the attestation object is primarily assigned.
	 Attestors for locations must be assigned to the Identity Management Organizations Attestors application role.
	For more information, see Finding attestors using the role of the employee to be attested on page 63.
AM - Manager of account's person	Manager of the employee connected to the user account that is to be attested
	For more information, see Determining attestors from persons responsible for the attestation objects on page 66.
AN - Attestor for the system entitlement to attest	Attestor of the system entitlement or system role if assignments of system entitlements or system roles to roles are attested. Attestors are determined through the assigned service item.
	 Attestors must be assigned to the Request & Fulfillment IT Shop Attestors application role.
	For more information, see Finding attestors using attestation objects on page 63.
AO - Attestor for recipient's primary	Attestor of the business role to which the attestation object is primarily assigned.
role	Attestors for business roles must be assigned to the application role Identity Management Business roles Attestors .
	For more information, see Finding attestors using the role of the employee to be attested on page 63.
AP - Attestor for recipient's cost	Attestor of the cost center to which the attestation object is primarily assigned.
center	 Attestors for cost centers must be assigned to the application role Identity Management Organizations Attestors.
	For more information, see Finding attestors using the role of the employee to be attested on page 63.
AR - Attestor for attestation	Attestor for the compliance rule to be attested.



Procedure Name	Attestors
compliance rule	 Attestors must be assigned to the Identity & Access Governance Identity Audit Attestors application role.
	For more information, see Finding attestors using attestation objects on page 63.
AS - Approver for	All employees assigned to the attestation policy as approver.
attestation policy	For more information, see Finding attestors using the attestation policy on page 63.
AT - Attestor for the organization to be	Attestor of the organization (department, cost center, location), business role, or IT Shop to be attested.
attested	 Attestors for departments, cost centers and locations must be assigned to the application role Identity Management Organizations Attestors.
	 Attestors for business roles must be assigned to the application role Identity Management Business roles Attestors.
	 Attestors for requests must be assigned to the Request & Fulfillment IT Shop Attestors application role.
	For more information, see Finding attestors using attestation objects on page 63.
AY - Attestor for the	Attestor of the company policy to be attested.
company policy to be attested	 Attestors must be assigned to the Identity & Access Governance Company policies Attestors application role.
	For more information, see Finding attestors using attestation objects on page 63.
CD - Calculated	-
approval	For more information, see Calculated approval on page 70.
CM - Recipient's	Manager of the employee to be attested.
manager	For more information, see Finding attestors from attestation object managers on page 65.
DM - Manager of recipient's	Department manager/deputy if employees of secondary memberships are attested in departments.
department	For more information, see Finding attestors from attestation object managers on page 65.
ED - Department	Employee's department manager whose system entitlements are



Procedure Name	Attestors
manager for	to be attested.
permission attestation	For more information, see Determining attestors from persons responsible for the attestation objects on page 66.
EM - Employee manager for	Employee's manager whose system entitlements are to be attested.
permission attestation	For more information, see Determining attestors from persons responsible for the attestation objects on page 66.
EN - Target system	Target system manager of the system entitlements to be attested.
manager of the permission for attestation	For more information, see Determining attestors from persons responsible for the attestation objects on page 66.
EO - Product owner of the system	Product owner whose system entitlements or system roles are to be attested.
entitlement to be attested	For more information, see Determining attestors from persons responsible for the attestation objects on page 66.
EX - Approvals to be	-
made externally	For more information, see Approvals to be made externally on page 71.
LM - Manager of recipient's location	Location manager/deputy if employees of secondary memberships are attested in locations.
	For more information, see Finding attestors from attestation object managers on page 65.
MD - Department manager of	Manager of the main department of the employee who is connected to the user account to be attested
account's person	For more information, see Determining attestors from persons responsible for the attestation objects on page 66.
MO - Role owner	Business role manager/deputy if employees of secondary memberships are attested in roles.
	For more information, see Finding attestors from attestation object managers on page 65.
OA - product owner	All members of the assigned application role if service items, system entitlements or system roles are attested.
	For more information, see Defining product owners as attestors on page 68.
OM - Manager of a	Manager of the role selected in the approval workflow.
specific role	For more information, see Finding attestors using a specified role on page 68.



Procedure Name	Attestors
OP - Owner of a privileged object	All employees that can be determined as owners of the privileged request.
	For more information, see Determining owners of a privileged object as attestors on page 69.
OR - Members of a	All employees that are assigned to a secondary business role.
certain role	For more information, see Finding attestors using a specified role on page 68.
PA - Secondary owner of Active	All employees to be found through the additional owner of the requested Active Directory group.
Directory group	For more information, see Finding attestors from additional Active Directory group owners on page 69.
PM - Manager of recipient's cost	Cost center manager/deputy if secondary memberships in cost centers are attested.
center	For more information, see Finding attestors from attestation object managers on page 65.
PO - Proposed owner	Proposed owner of the attestation object
	For more information, see Determining attestors from owners of the attestation objects on page 69.
RE - Manager of	System role manager to be attested.
system roles to be attested	For more information, see Finding attestors from attestation object managers on page 65.
RM - Role manager for attesting	Manager of role to be attested if secondary memberships in roles are attested.
memberships	For more information, see Finding attestors from attestation object managers on page 65.
RR - Role manager	Manager of role to be attested.
for attesting roles	For more information, see Finding attestors from attestation object managers on page 65.
SO - Target system manager of the	Target system manager of system entitlement or user account to be attested.
permission for attestation	For more information, see Determining attestors from persons responsible for the attestation objects on page 66.
WC - Waiting for further approval	- For more information, see Waiting for further approval on page 72.



Finding attestors using the attestation policy

Use the AS approval procedure if you want to fix attestors for any object to an attestation policy. This approval procedure finds all employees that are assigned to the attestation procedure as approvers.

Use this procedure to allow any objects to be attested by any of the specified employees. These employees must be assigned to the attestation policy as approvers. The attestor can also be entered when you create attestation policies in the Web Portal. For detailed information, see *One Identity Manager Web Portal User Guide*.

Related topics

• Assigning approvers on page 30

Finding attestors using the role of the employee to be attested

Installed modules: Business Roles Module (for approval procedure AO).

If you want to attest company resource assignments to employees or their requests, use the AD, AL, AO, or AP approval procedures. The attestors found are members of the **Attestor** application role.

Attestation objects are employees (table: Person) or request recipients (table: PersonWantsOrg). These approval procedures determine the role (department, location, business role, cost center) for each attestation object to which the attestation object is primarily assigned. If the primarily assigned role is not directly assigned an attestor, the approval procedure finds the the attestator's parents roles. If still no attestor can be determined, the attestation case is presented to the attestor of the associated role class for approval.

- NOTE: When attestors are found using the AO approval procedure and when "bottom-up" inheritance is defined for business roles, note the following:
 - If there is no attestor given for the primary business role, attestors are taken from the child business role.

Related topics

• Default approval procedures on page 58

Finding attestors using attestation objects

Use the AR, AY or AT approval procedures if you want to attest the validity of compliance rules, rule violations, company policies, policy violations, or of departments, locations,



cost centers, or business roles. The AT procedure is also suitable for attesting assignments to IT Shop structures (shops, shopping centers or shelves). Use the AA or AN approval procedures to attest system entitlement or system role assignments to departments, locations, cost centers, business roles or IT Shop structures. The attestors found are members of the **Attestor** application role.

	Attestation base objects	Available in Module		
AR	Rules (ComplianceRule)	Compliance Rules		
	Rule violations (PersonInNonCompliance)	Module		
AY	Company policies (QERPolicy)	Company Policies		
	Policy violations (QERPolicyHasObject)	Module		
AT	Departments (Department)			
	IT Shop Structures (ITShopOrg)			
	Locations (Locality)			
	Business roles (0rg)			
	Cost centers (ProfitCenter)			
	IT Shop Templates (ITShopSrc)			
AA, AN	System entitlement or target system group assignments to roles (<basetree>HasUNSGroupB,</basetree>	Target System Base Module		
	<pre><basetree>HasADSGroup, <basetree>HasEBSResp,)</basetree></basetree></pre>			
	System role assignments to roles (<basetree>HasESet)</basetree>			

These approval procedures determine the attestors to which the attestation object is assigned. The AA approval procedure finds the attestor using the role (departments, locations, business roles, cost centers) or IT Shop structures (IT Shop templates). The AN approval procedure finds the attestor using the service item assigned to the system entitlement or target system group.

Furthermore, the following also applies to the AT and AA approval procedures: If an attestor is not directly assigned to the attestation object, the approval procedure finds the attestor of the parent roles/IT Shop structures. If still no attestor can be determined, the attestation case is presented to the attestor of the associated role class for approval.

- NOTE: If the attestation base object is a business role or a business role assignment and bottom-up inheritance is defined for the associated role classes, the following applies:
 - If there is no attestor assigned to the attestation object, the approval procedure finds attestors from the attestors of subordinate roles.

Related topics

• Default approval procedures on page 58



Finding attestors from attestation object managers

If you want to have employees, user accounts, roles, system roles, role memberships, assignments of system roles or entitlements for employees, roles or IT Shop structures attested through their managers, use the CM, DM, LM, MO, RM, RR, or RE approval procedures.

Approval procedure	Attestation base objects	Available in Module
СМ	Employees (Person)	
	Employees: memberships in roles and organizations (PersonInBaseTree)	
DM	Employees (Person)	
	Employees: department memberships (PersonInDepartment)	
LM	Employees (Person)	
	Employees: location memberships (PersonInLocality)	
MO	Employees (Person)	Business
	Employees: business role memberships (PersonInOrg)	Roles Module
PM	Employees (Person)	
	Employees: cost center memberships (PersonInProfitCenter)	
RE	System roles (ESet)	System
	Employees: system role assignments (PersonHasESet)	Roles Module
	Departments: system role assignments(DepartmentHasESet)	rioddic
	Business roles: system role assignments (OrgHasESet)	
	IT Shop structures: system role assignments (ITShopOrgHasESet)	
	IT Shop templates: system role assignments (ITShopSrcOrgHasESet)	
	Cost centers: system role assignments (ProfitCenterHasESet)	
	Locations: system role assignments (LocalityHasESet)	
RM	Employees: department memberships (PersonInDepartment)	
	Employees: IT Shop structure memberships (PersonInITShopOrg)	
	Employees: location memberships (PersonInLocality)	



Approval procedure	Attestation base objects	Available in Module
	Employees: business role memberships (PersonInOrg)	
	Employees: cost center memberships (PersonInProfitCenter)	
RR	Departments (Department)	
	IT Shop Structures (ITShopOrg)	
	Locations (Locality)	
	Business roles (0rg)	
	Cost centers (ProfitCenter)	
	IT Shop Templates (ITShopSrc)	
	All system entitlement or system role assignments to roles; for example Roles and organizations: Active Directory group assignments (BaseTreeHasADSGroup) or Locations: EBS entitlement assignments (LocalityHasEBSResp)	

These approval procedures find the manager associated with every attestation object. In the RE approval procedure, the system role manager is determined as attestor; in the RM and RR approval procedures, the role/IT Shop structure manager is determined. The approval procedures CM, DM, LM, MO and PM find the department manager and deputy manager of the role in which the attesting employee is a member.

Determining attestors from persons responsible for the attestation objects

If you want to attest system entitlements and the user accounts assigned to them, use the ED, EM, EN, EO, or SO approval policies. Use the approval procedures AM, MD or SO to attest user accounts.

Attestation objects are user accounts or system entitlements and the user accounts assigned to them as well as system roles that have system entitlements or system roles assigned to them. The approval procedures determine the following attestors:

	Attestation base objects	Attestors	Available in Module
AM	User accounts (UNSAccount)	Employee's department manager to whom the user account is connected.	Target System Base Module



	Attestation base objects	Attestors	Available in Module
ED	User accounts: system entitlement assignments (UNSAccountInUNSGroup)	Employee's department manager (and deputy manager) to whom the user account is connected. The primary department assigned in this case.	Target System Base Module
EM	User accounts: system entitlement assignments (UNSAccountInUNSGroup)	Employee's department manager to whom the user account is connected.	Target System Base Module
EN	User accounts: system entitlement assignments (UNSAccountInUNSGroup) System entitlements (UNSGroup)	Target system manager of the target system area to which the system entitlement belongs.	Target System Base Module
EO	System roles: assignments (ESetHasEntitlement) All user account assignments to system entitlements; for example User accounts: system entitlement assignments (UNSAccountInUNSGroup) or SAP user accounts: assignments to roles (SAPUserInSAPRole) All system entitlement or system role assignments to roles; for example Roles and organizations: Active Directory group assignments (BaseTreeHasADSGroup) or Locations: EBS entitlement assignments (LocalityHasEBSResp)	Product owner of the service item to which the system entitlement or system role is assigned.	Target System Base Module or System Roles Module
MD	User accounts (UNSAccount)	Employee's department manager (and deputy manager) to whom the user account is connected. The primary department assigned in this case.	Target System Base Module
SO	User accounts: system entitlement assignments (UNSAccountInUNSGroup) User accounts (UNSAccount)	Target system manager for the target system to which the system entitle- ment or user account	Target System Base Module



Attestation base objects	Attestors	Available in Module
System entitlements: assignments to	belongs.	

Finding attestors using a specified role

system entitlements (UNSGroupInUNSGroup)

If the attestors for any object are specified in a certain role, use the approval procedure OR or OM. You can allow any objects to be attested by employees from any role using these approval procedures. In the approval step, specify the role by means of which the attestors are to be determined. The approval procedures determine the following attestors:

	Selectable Roles	Attestors
OM	Departments (Department)	Manager and deputy manager of the role specified in the approval step.
	Cost centers (ProfitCenter)	
	Locations (Locality)	
	Business roles (0rg)	
OR	Departments (Department)	All secondary members of the role specified in the approval step.
	Cost centers (ProfitCenter)	
	Locations (Locality)	
	Business roles (0rg)	
	Application roles (AERole)	

Defining product owners as attestors

Use the approval procedure OA to determine whether product owners can be attestors. The following objects can be attested with this procedure:

- Service items
- System entitlements
- System entitlement assignments to user accounts or system entitlements
- System role assignments to employees

Prerequisites:



- A service item must be assigned to the system entitlements and system roles.
- An application role for product owners must be assigned to the service item.

All employees who are assigned this application role are determined as attestors.

Determining owners of a privileged object as attestors

Installed modules: Privileged Account Governance Module

Use the approval procedure OP if you want to allow privileged objects in a Privileged Account Management system, for example PAM assets or PAM directory accounts, to be attested by their owners. The owners attest the possible user accord to these privileged objects. The owners of the privileged objects must have the **Privileged Account**Governance | Asset and account owners application role or a child application role.

Finding attestors from additional Active Directory group owners

Installed modules: Active Roles Module

If the Active Directory group is attested, the attestor can be determined through additional owners of this Active Directory group. Use the PA approval procedure for this purpose. This finds all employees that are:

- A member in the assigned Active Directory group through their Active Directory user account
- Linked to the assigned Active Directory user account
- NOTE: Only use the PA approval procedure if the configuration parameter TargetSystem | ADS | ARS_SSM is enabled. The column Additional owners is only available in this case.

Determining attestors from owners of the attestation objects

When you assign new owners to devices or system entitlements in the Web Portal, the new owner should agree with this assignment. An attestation with the approval procedure PO is carried out for this purpose.



Calculated approval

1 NOTE: Only one approval step can be defined with the CD approval procedure per approval level.

If you want to make attestation dependent on specific conditions, use the CD approval procedure. This procedure does not determine an attestor. One Identity Manager makes the decision depending on the condition that is formulated in the approval step.

You can use the procedure for any attestation base objects. You create a condition in the approval step. If the condition returns a result, the approval step is approved through the One Identity Manager. If the condition does not return a result, the approval step is denied by the One Identity Manager. If there are no further approval steps, the approval procedure is either finally granted or denied.

To enter a condition for the CD approval procedure

- Edit the approval step properties.
 For more information, see Editing approval levels on page 50.
- 2. In the **Condition** input field, enter a valid WHERE clause for database queries. You can enter the SQL query directly or with a wizard. In the condition, you reference the actual attestation case using the variable <code>@UID_AttestationCase</code>.

Example of a simple approval workflow with the CD approval procedure:

External employees should be attestation by their managers. If no manager is assigned, the members of a designated application role must attest the employees.

You can find all external employees, who have managers assigned to them by using the approval procedure CD and the following condition.

```
EXISTS
```

```
(SELECT 1 FROM
      (SELECT xobjectkey FROM Person WHERE (IsExternal = 1)
      AND (EXISTS
      (SELECT 1 FROM
            (SELECT UID_Person FROM Person WHERE 1 = 1) as X
      WHERE X.UID_Person = Person.UID_PersonHead) )) as X
WHERE X.xobjectkey = AttestationCase.ObjectKeyBase)
```

If the condition is fulfilled, the external employee's manager can attest the employee. To do this, add an approval step in the positive approval path with the CM approval procedure.

If the condition is not fulfilled, the employee is attested by the member of a designated application role. To do this, add an approval step in the negative approval path with the OR approval procedure and assign the application role.



Approvals to be made externally

Use external approvals (approval procedure EX) if an attestation needs to be approved as soon as a defined event from outside One Identity Manager takes place. You can also use this procedure to allow any number of objects to be attested by employees who do not have access to One Identity Manager.

Specify an event in the approval step that triggers an external approval. The event triggers a process that initiates the external approval for the attestation case and evaluates the result of the approval decision. The approval process waits for the external decision to be passed to One Identity Manager. Define the subsequent approval steps depending on the result of the external approval.

To use an approval procedure

- 1. Define your own processes that:
 - Trigger an external approval
 - Analyze the results of the external approval
 - Grant or deny approval in the subsequent external approval step in One Identity Manager
- 2. Define an event, which starts the process for external approval. Enter the result in **Result** in the approval step.

If the external event occurs, the approval step status in One Identity Manager has to be changed. Use the process task CallMethod with the MakeDecision method for this. Pass the following parameters to the process task:

```
MethodName: Value = "MakeDecision"
ObjectType: Value = "AttestationCase"
Param1: Value = "sa"
Param2: Value = <approval> ("true" = granted; "false" = denied)
Param3: Value = <reason for approval decision>
Param4: Value = <standard reason>
Param5: Value = <number approval steps> (PWODecisionStep.SubLevelNumber)
WhereClause: Value = "UID AttestationCase = '"& $UID AttestationCase$ &"'"
```

Use these parameters to specify which attestation case is to be approved by external approval (WhereClause). Parameter Param1 specifies the attestor. Attestor is always the **sa** system user. Parameter Param2 is passed to approval. If the attestation was granted, the value **True** must be transferred. If the attestation was denied, the value **False** must be transferred. Use parameter Param3 to pass a reason text fro the approval decision; use Param4 to pass a predefined standard reason. If more than one external approval steps have been defined in an approval level, use Param5 to pass the approval step count. This ensures the approval is aligned with the correct approval step.

Use the Process Editor to define and edit processes.



Example

All compliance rules should be checked and attested by an external assessor. The attestation object data should be made available as a PDF on an external share. The assessor should save the result of the attestation in a text file on the external share. Use this approval procedure to make external approvals and define:

- A "P1" process that saves a PDF report with data about the attestation object data and the attestation procedure on an external share
- An "E1" event that starts the "P1" process
 In the approval step, enter "E1" in the Event field, and enter P1 in the process as the trigger for the external decision.
- A process "P2" process that checks the share for new text files, evaluates the content, and calls the One Identity Manager CallMethod task the method MakeDecision method
- An "E2" event that starts the "P2" process
- A schedule that starts the events "E2" on a regular basis

For detailed information about creating processes, see the *One Identity Manager Configuration Guide*. For detailed information about setting up schedules, see the *One Identity Manager Operational Guide*.

Detailed information about this topic

• Properties of an approval step on page 51

Waiting for further approval

NOTE: Only one approval step can be defined with the approval procedure WC per approval level.

If you want to ensure that a specific data state exists in One Identity Manager before an attestation case is finally approved, then use the WC approval procedure. Use a condition to specify which prerequisites have to be fulfilled so that attestation can take place. The condition is evaluated as a function call, which must accept the attestation case UID as a parameter (AttestationCase.UID_AttestationCase). You use this UID to reference the attestation object. The function must define three return values as integer values. One of the following actions is carried out depending on the function's return value:

Table 24: Return value for deferred approval

Return value	Action
Return value > 0	The condition is fulfilled. Deferred approval has completed successfully. The next approval step (in case of success) is carried out.



Return value	Action
Return value = 0	The condition is not yet fulfilled. Approval is rolled back and is retested the next time DBQueue Processor runs.
Return value < 0	The condition is not fulfilled. Deferred approval has failed. The next approval step (in case of failure) is carried out.

To use an approval procedure

- 1. Create a database function which tests the condition for the attestation.
- 2. Create an approval step with the approval procedure WC. Enter the function call in **Condition**.

Syntax: dbo.<function name>

- 3. Specify an approval step in the case of success. Use the approval procedure with which One Identity Manager can determine the attestors.
- 4. Specify an approval step in the case of failure.

Setting up approval procedures

You can create your own approval procedures if the default approval procedures for finding the responsible attestors do not meet your requirements. The condition through which the attestors are determined is formulated as a database query. Several queries may be combined into one condition.

To set up an approval procedure

- 1. In Manager, select the category **Attestation | Basic configuration data | Approval procedures**.
- 2. Select an approval procedure in the result list and run **Change master data**.
 - OR -

Click in the result list.

- 3. Edit the approval procedure master data.
- 4. Save the changes.

To edit the condition

- In Manager, select the category Attestation | Basic configuration data | Approval procedures.
- 2. Select an approval procedure from the result list.
- 3. Select Change queries for approver selection.



Detailed information about this topic

- General master data for an approval procedure on page 74
- · Queries for finding attestors on page 74

General master data for an approval procedure

Enter the following master data for an approval procedure.

Table 25: General master data for an approval procedure

Property	Description
Approval procedure	Descriptor for the approval procedure (maximum two characters).
Description	Approval procedure identifier.
DBQueue Processor task	Approvals can either be made automatically through a DBQueue Processor calculation task or by specified approvers. Assign a custom DBQueue Processor task if the approval procedure should make an automatic approval decision. You cannot assign a DBQueue Processor task if a query is entered for determining the attestors.
Max. number approvers	Maximum number of attestors to be determined by the approval procedure. Specify how many employees must really make approval decisions in the approval steps used by this approval procedure.
Sort order	Value for sorting approval procedures in the menu.
	Specify the value 10 to display this approval procedure at the top of the menu when you set up an approval step.

Related topics

Properties of an approval step on page 51

Queries for finding attestors

The condition through which the attestors are determined is formulated as a database query. Several queries may be combined into one condition. This adds, to the group of attestors, all employees determined by single queries.



To edit the condition

- 1. In Manager, select the category **Attestation | Basic configuration data | Approval procedures**.
- 2. Select an approval procedure from the result list.
- 3. Select Change queries for approver selection.

To create single queries

1. Click Add.

This inserts a new row in the table.

- 2. Mark this row. Enter the query properties.
- 3. Add more queries if required.
- 4. Save the changes.

To edit a single query

- 1. Select the query you want to edit in the table. Edit the query's properties.
- 2. Save the changes.

To remove single queries

- 1. Select the query you want to remove in the table.
- 2. Click Delete.
- 3. Save the changes.

Table 26: Query properties

Property	Description
Approver selection	Query identifier which determines the attestors
Query	Database query for determining the attestors
	The database query must be formulated as a select statement. The column selected by the database query must return a UID_Person. Every query must return a value for UID_PWORulerOrigin. The query returns one or more employees to whom the attestation case is presented for approval. If the query fails to return a result, the attestation procedure is aborted.
	A query contains exactly one select statement. To combine several select statements, create several queries.
	If a DBQueue Processor task is assigned, you cannot enter a query to determine attestors.

You can, for example, determine predefined attestors with the query (example 1). The attestor can also be found dynamically depending on the attestation case to approve. To do



this, within the database query, use the @UID_AttestationCase variable to access the attestation case (example 2).

Example 1

The attestation cases should be approved by a specific attestor.

```
Query: select UID_Person, null as UID_PWORulerOrigin from Person where InternalName='Bloggs, Jan'
```

Example 2

All active compliance rules should be attested by the respective rule supervisor.

```
Query: select pia.UID_Person, null as UID_PWORulerOrigin from AttestationCase ac join ComplianceRule cr on cr.XObjectKey = ac.ObjectKeyBase and cr.IsWorkingCopy = '0'

join PersonInBaseTree pia on pia.UID_Org = cr.UID_OrgResponsible and pia.XOrigin > 0

where ac.UID AttestationCase = @UID AttestationCase
```

Taking delegation into account

To include delegation when determining attestors, use the query to also determine the employees to whom a responsibility has been delegated. If the managers of hierarchical roles are to make the attestation decision, determine the attestors from the HelperHeadOrg table. This table groups all hierarchical role managers, their deputy managers and employees to whom a responsibility has been delegated. If the members of business or application roles are to make the approval decision, determine the approvers from the PersonInBaseTree table. This table groups all hierarchical role members and employees to whom a responsibility has been delegated.

Determine the UID_PWORulerOrigin in order to notify delegators when the recipient of the delegation has made a decision on an attestation case and thus allow the Web Portal to show if the attestor was originally delegated.

To determine the UID_PWORulerOrigin of the delegation

• Determine the UID_PersonWantsOrg of the delegation and copy this value as UID_PWORulerOrigin to the query. Use the table function dbo.QER_ FGIPWORulerOrigin to do this.

```
select dbo.QER_FGIPWORulerOrigin(XObjectKey) as UID_PWORulerOrigin
```

Modified guery from example 2:

```
select pia.UID_Person, dbo.QER_FGIPWORulerOrigin(pia.XObjectKey) as UID_
PWORulerOrigin from AttestationCase ac
```

```
join ComplianceRule cr on cr.XObjectKey = ac.ObjectKeyBase and
```



```
cr.IsWorkingCopy = '0'
join PersonInBaseTree pia on pia.UID_Org = cr.UID_OrgResponsible and
pia.XOrigin > 0
where ac.UID AttestationCase = @UID AttestationCase
```

Additional tasks for approval procedures

After you have entered the master data, you can run the following tasks.

Overview of the approval procedure

To obtain an overview of an approval procedure

- 1. In Manager, select the category **Attestation | Basic configuration data | Approval procedures**.
- 2. Select an approval procedure from the result list.
- 3. Select **Approval procedure overview** in the task view.

Specifying permitted approval procedures for tables

You can only assign selected approval policies to attestation procedures. The approval policies permitted depend on the approval procedures applied in the approval policies and on the table that forms the attestation base object for an attestation procedure. You must specify which tables are permitted for use with custom approval procedures.

To specify the tables that permit this approval procedure

- 1. In Manager, select the category **Attestation | Basic configuration data | Approval procedures**.
- 2. Select an approval procedure from the result list.
- 3. Select the **Assign tables** task.

In **Add assignments**, assign the tables to which the approval procedure can be assigned.

TIP: In Remove assignments, you can remove the assignment of tables.

To remove an assignment

- Select the table and double-click .
- 4. Save the changes.



You can see which tables allow an approval procedure on the approval procedure overview form.

Related topics

- Assigning Approval Policies on page 16
- Overview of the approval procedure on page 77

Copying an approval procedure

For example, you can copy default approval procedures in order to customize them.

To copy an approval procedure

- 1. In Manager, select the category **Attestation | Basic configuration data | Approval procedures**.
- 2. Select an approval procedure in the result list. Select **Change master data**.
- 3. Select Create copy in the task view.
- 4. Confirm the security prompt with Yes.
- Enter the short name for the copy.
 The short name for an approval procedure consists of a maximum of two characters.
- 6. Click **OK** to start copying.
 - OR -

Click **Cancel** to cancel copying.

Deleting approval procedures

To delete an approval procedure

- 1. Remove all assignments to approval steps.
 - a. Check on the approval procedure overview form which approval steps are assigned to the approval procedure.
 - b. Switch to the approval workflow and assign another approval procedure to the approval step.
- 2. In Manager, select **Attestation | Basic configuration data | Approval procedures**.
- 3. Select an approval procedure from the result list.
- 4. Click .
- 5. Confirm the security prompt with **Yes**.



Related topics

Overview of the approval procedure on page 77

Determining the responsible attestors

The DBQueue Processor calculates which employee is authorized as approver in which approval level. Once an attestation is triggered, the attestors are determined for every approval step of the workflow to be processed. Changes to responsibilities may lead to an employee no longer being authorized as approver for an attestation that is not yet finally approved. In this case, the attestors must be recalculated. The following changes can trigger recalculation of pending attestations:

- Approval policy, workflow, step or procedure changes.
- An authorized approver loses their responsibility in One Identity Manager, for example, if a change is made to the department manager, attestation policy approver or target system manager.
- An employee obtains responsibilities in One Identity Manager and therefore is authorized as an approver, for example as the manager of the employee to be attested.
- An employee authorized as an approver is deactivated.

Once an employee's responsibilities have changed in One Identity Manager, a task for recalculating the attestors is queued in the DBQueue. All approval steps of the pending attestation cases are also recalculated by default. Approval steps that have already been approved remain approved, even if their attestor has changed. Recalculating attestors may take a long time depending on the configuration of the system environment and the amount of data to be processed. To optimize this processing time, you can specify the approval steps for which the attestors are to be recalculated.

To configure recalculation of the attestors

• In Designer, set the configuration parameter **QER | Attestation | ReducedApproverCalculation** and select one of the following options as the value.

Table 27: Options for recalculating attestors

Option	Description
No	All approval steps are recalculated. This behavior also applies if the configuration parameter is not set.
	Advantage: All valid attestors are displayed in the approval process. The rest of the approval sequence is transparent.
	Disadvantage: Recalculating attestors may take a long time.
CurrentLevel	Only the attestors for the approval level that is currently to be edited



Option

Description

are recalculated. Once an approval level has been approved, the attestors are determined for the next approval level.

Advantage: The number of approval levels to calculate is lower. Calculating the attestors may be faster.



TIP: Use this option if performance problems occur in your environment in connection with the recalculation of attestors.

Disadvantage: The originally calculated attestors are still displayed in the approval sequence for each subsequent approval step, even though they may no longer have approval authorization. The rest of the approval sequence is not correctly represented.

NoRecalc

No recalculation of attestors. The previous attestors remain authorized to approve the current approval level. Once an approval level has been approved, the attestors are determined for the next approval level.

Advantage: The number of approval levels to calculate is lower. Calculating the attestors may be faster.



TIP: Use this option if performance problems occur in your environment in connection with the recalculation of attestors, even though the **CurrentLevel** option is used..

Disadvantage: The originally calculated attestors are still displayed in the approval sequence for each subsequent approval step, even though they may no longer have approval authorization. The rest of the approval sequence is not correctly represented. Employees that are no longer authorized can approve the current approval level.

In the worst-case scenario, the only attestors originally calculated here now have no access to One Identity Manager, for example, because they have left the company. The approval level cannot be approved.

To see approval steps of this type through

- Define a timeout and timeout behavior when you set up the approval workflows on the approval steps.
 - OR -
- When setting up the attestation, assign members to the chief approval team. These members can access pending attestation cases at any time.

Detailed information about this topic

- Properties of an approval step on page 51
- Chief approval team on page 23



Related topics

Modifying approval workflows for pending attestation cases on page 96

Setting up multi-factor authentication for attestation

You can set up additional authentication for particularly security critical attestations, which requires every attestor to enter a security code for attesting. Define which attestation policies require this authentication in your attestation policies.

Use One Identity Manager One Identity Starling Two-Factor Authentication for multi-factor authentication. The authentication information required is defined in the configuration parameters under **QER | Person | Starling** or **QER | Person | Defender**. For detailed information about setting up multi-factor authentication, see the *One Identity Manager Authorization and Authentication Guide*.

To be able to use multi-factor authentication

- 1. Set up multi-factor authentication as described in the *One Identity Manager Authorization and Authentication Guide*.
- 2. In Manager, select the attestation policies for which the multi-factor authentication will be used.
- Enable the Approval by multi-factor authentication option.
 Multi-factor authentication cannot be used for default attestation policies.

Once the **Approval by multi-factor authentication** option is set on an attestation policy, a security code is requested in each approval step of the approval process. This means that every employee who is determined to be an attestor for this attestation policy, must have a Starling 2FA token.

1 IMPORTANT: An attestation cannot be sent by email if multi-factor authentication is configured for the attestation policy. Attestation emails for such attestations produce an error message.

For detailed information about multi-factor authentication, see the *One Identity Manager Web Portal User Guide*.

Related topics

- General master data for attestation policies on page 26
- Attestation by mail on page 110



Prevent attestation by employee awaiting attestation

The attestation object can also be determined as the attestor in an attestation case. which means the employees to be attested can attest themselves. To prevent this, set the configuration parameter **QER | Attestation | PersonToAttestNoDecide**.

NOTE:

- Changing the configuration parameter only affects new attestation cases. Attestors are not recalculated for existing attestation cases.
- The configuration parameter setting also applies for fallback approvers; it does not apply to the chief approval team.
- If the **Approval by affected employee** option is set on an approval step, this configuration parameter has no effect.

To prevent employees from attesting themselves

• In Designer, set the **QER | Attestation | PersonToAttestNoDecide** configuration parameter.

This configuration parameter affects all attestation cases in which employees included in the attestation object or in object relations, are attestors at the same time. the following employees are removed from the group of attestors.

- Employees included in AttestationCase.ObjectKeyBase
- Employees included in AttestationCase.UID_ObjectKey1, ObjectKey2 or ObjectKey3
- Employees' main identities
- All subidentities of these main identities

If the configuration parameter is not set or if **Approval by affected employee** is enabled for the approval step, these employees can attest themselves.

Related topics

Properties of an approval step on page 51

Managing attestation cases

During attestation, you may find it necessary to assign someone else as default attestor responsible for the attestation because, for example, the actual attestor is absent. You may require additional information about an attestation object. The One Identity Manager offers different possibilities to intervene in an open attestation case.



Getting more information

An attestor has the option to gather more information about an attestation case. This ability does not, however, replace the granting or denying approval of an attestation case. There is no addition approval step required in the approval workflow to obtain the information.

Attestors can request information from any employee. The attestation case is put on hold while the query is pending. Once the employee requested has supplied the required information and the attestors have made an decision on the approval step, hold status is revoked. Attestors can recall a pending query at any time. The request is taken off hold. The query and answer are logged in the approval sequence and made available to the attestors.

NOTE: Hold status is revoked if the attestor who asked a question is removed as an approver. The queried employee must not answer. Attestation process will proceed.

Email notification to the employees involved can be sent using unanswered inquiries.

For detailed information about queries, see the *One Identity Manager Web Portal User Guide*

Detailed information about this topic

• Email notification: Notifications with questions on page 108

Appointing other attestors

Once an approval level in the approval workflow has been reached, the attestors at this level can appoint another employee to handle the approval. To do this, you have the options described below.

· Rerouting approvals

The attestor appoints another approval level to carry out attestations. To do this, set up a connection to the approval level in the approval workflow to which an approval decision can be rerouted.

- Appointing additional attestors
 - . The attestor appoints another employee to carry out the attestation. The other attestor must make an approval decision in addition to the known attestors. To do this, enable the option **Additional approver possible** in the approval step.

The additional attestor can reject the approval and return the attestation case to the original attestor. The original attestor is informed about this by email. The original attestor can appoint another additional attestor.

Delegate approval

The attestor appoints another employee with the attestation. This employee is added to the current approval step as the attestor. This employee then makes the approval



decision instead of the attestor who made the delegation. To do this, enable the option **Approval can be delegated** in the approval step.

The current attestor can reject the approval and return the attestation case to the original attestor. The original attestor can withdraw the delegation and delegate a different employee, for example, if the other attestor is not available.

Email notifications can be sent to the original attestors and the others.

Detailed information about this topic

- Connecting approval levels on page 55
- Editing approval levels on page 50
- Properties of an approval step on page 51

Related topics

- Email notification: Delegating attestations on page 107
- Email notification: Rejecting approvals on page 107
- Email notification: Notifications from additional attestors on page 108

Escalating an attestation case


Approval steps can be automatically escalated once the specified timeout is exceeded. The attestation case is presented again to another approval body. The attestation case can subsequently be processed again in the normal approval workflow.

To configure escalation of an approval step

- 1. Open the approval workflow in the Workflow Editor.
- 2. Add an additional approval level with one approval step for escalation.
- 3. Connect the approval step that is going to be escalated when the time period is exceeded with the new approval step. Use the connection point for escalation to do this.



Figure 3: Example of an Approval Workflow with Escalation



4. Configure the behavior for the approval step to be escalated when it times out.

Table 28: Properties for escalation on timeout

Property Meaning

TimeOut (working hours)

Number of working hours to elapse after which the approval step is automatically granted or denied approval.

The timeout is check every 30 minutes, by default. To change this interval, modify the **Checks reminder interval and timeout of attestation cases** schedule.

The working hours of the respective approver are taken into account when the time is calculated.

NOTE: Ensure that a state and/or county is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about employees' calculating working hours, see the One Identity Manager Identity Management Base Module Administration Guide.

If more than one approver was found, the an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.

If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.

If an approver is queried, the approval decision must be made within



Property	Meaning
	the defined timeout anyway. The time point for automatic approval is not recalculated.
Timeout	Action, which is executed if the timeout expires.
behavior	 Escalation: The attestation case is escalated. The escalation approval level is called.

In the event of an escalation, email notifications can be sent to the new approvers and other employees.

Related topics

Email notification: Demanding attestation

• Email notification: Escalation of attestation cases on page 106

Attestors cannot be established

You can specify a fallback approver if attestation cases cannot be approved because no attestors are available. An attestation case is then always assigned to the fallback approver for attestation if no attestor can be found in an approval step in the specified approval procedure.

To specify fallback approvers, define application roles and assign these to an approval step. Different attestation groups in the approval steps may also require different fallback approvers. Specify different application role for this, to which you can assign employees who can be determined as fallback approvers in the approval process. For more detailed information, see the *One Identity Manager Authorization and Authentication Guide*.



To specify fallback approvers for an approval step

Enter the following data for the approval step.

Table 29: Approval step properties for fallback approvers

Property Meaning

Fallback approver

Application role whose members are authorized to approve attestation cases if an attestor cannot be determined through the approval procedure. Assign an application from the menu.

To create a new application role, click . Enter the application role name and assign a parent application role. For detailed information, see the *One Identity Manager Authorization and Authentication Guide*.



NOTE: The number of approvers is not applied to the fallback approvers. The approval step is considered approved the moment as soon as one fallback approver has approved the request.

Attestation sequence with fallback approvers

- 1. No attestor can be found for an approval step in an approval process. The attestation is assigned to all members of the fallback approver application role.
- 2. Once a fallback approver has approved an attestation case, it is presented to the attestors at the next approval level.
 - NOTE: You can specify in the approval step how many attestors are required for approval in this step. This limit is **not** valid for the chief approval team. The approval step is considered to be approved as soon as **one** fallback approver has approved the attestation.
- 3. The attestation case is aborted if no fallback approver can be found.

Fallback approvers can make approval decisions on attestation cases for all manual approval steps. Fallback approvals are not permitted for approval steps using the CD, EX and WC approval procedures.

Related topics

- Editing approval levels on page 50
- Selecting attestors on page 57
- Attestation through chief approval team on page 90

Automatic approval on timeout

Attestation cases can be automatically granted or denied approval once a specified time period has been exceeded.



To configure automatic approval if the timeout expires

Enter the following data for the approval step.

Table 30: Properties for automatic approval on timeout

Property Meaning

TimeOut (working hours)

Number of working hours to elapse after which the approval step is automatically granted or denied approval.

The timeout is check every 30 minutes, by default. To change this interval, modify the **Checks reminder interval and timeout of attestation cases** schedule.

The working hours of the respective approver are taken into account when the time is calculated.



NOTE: Ensure that a state and/or county is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about employees' calculating working hours, see the *One Identity Manager Identity Management Base Module Administration Guide*.

If more than one approver was found, the an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.

If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.

If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is not recalculated.

Timeout behavior

Action, which is executed if the timeout expires.

- **Approved**: The attestation case is approved in this approval step. The next approval level is called.
- **Deny**: The attestation case is denied in this approval step. The approval level for denying is called.

When the approval decision for an attestation case is made automatically, other people can be notified by email.

Related topics

- Email notification: Granting or denying attestation cases on page 103
- Editing approval levels on page 50



Aborting an attestation case on timeout

Attestation cases can be automatically aborted once a specified time period has been exceeded. The abort takes place when either a single approval step or the entire approval process has exceeded the timeout.

To configure an abort after the timeout of a single approval step has been exceeded

• Enter the following data for the approval step.

Table 31: Properties of the approval step for abort on timeout

Property Meaning

TimeOut (working hours)

Number of working hours to elapse after which the approval step is automatically granted or denied approval.

The timeout is check every 30 minutes, by default. To change this interval, modify the **Checks reminder interval and timeout of attestation cases** schedule.

The working hours of the respective approver are taken into account when the time is calculated.



NOTE: Ensure that a state and/or county is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about employees' calculating working hours, see the *One Identity Manager Identity Management Base Module Administration Guide*.

If more than one approver was found, the an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.

If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.

If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is not recalculated.

Timeout behavior

Action, which is executed if the timeout expires.

 Abort: the approval step and, therefore, the attestation case, are canceled.



To configure abort on timeout for the entire approval process

• Enter the following data for the approval workflow.

Table 32: Properties of the approval workflow for abort on timeout

Property	Meaning
System abort (days)	Number of days to elapse after which the approval workflow, and therefore the system, automatically ends the entire attestation procedure.

When an attestation case is aborted, other people can be notified by email.

Related topics

- Email notification: Aborting attestation cases
- Editing approval levels on page 50
- Setting up approval workflows on page 49

Attestation through chief approval team

Sometimes, approval decisions cannot be made for attestation cases because an attestor is not available or does not have access to One Identity Manager tools. To complete these attestations, you can define a chief approval team whose members are authorized to intervene in the approval process at any time.

The chief approval team is authorized to approve, deny, or abort attestations in special cases or to appoint other attestors.

IMPORTANT:

- The four-eye principle can be broken like this because chief approval team members can make approval decisions for attestation cases at any time. Specify, on a custom basis, in which special cases the chief approval team may intervene in the approval process.
- The chief approval team is authorized to attest its own members. The
 configuration parameter setting QER | Attestation |
 PersonToAttestNoDecide does not apply to the chief approval team.
- In the approval step, you can specify how many attestors must make a decision on this approval step. This limit is not valid for the chief approval team. The approval decision is considered to be made as soon as one member of the chief approval team has decided on the attestation.

The chief approval team can approve attestations for all manual approval steps. Following applies:



- Chief approval team decisions are not permitted for approval steps using the CD, EX and WC approval procedures.
- If a member of the chief approval team is also named as a regular attestor for an approval step, he or she can only make an approval decision for this step as a regular attestor.
- The chief approval team can also make an approval decision if a regular attestor has submitted a query and the attestation is in hold status.

To add members to the chief approval team

- 1. In Manager, select the category **Attestation | Basic configuration data | Chief approval team**.
- 2. Select **Assign employees** in the task view.

In **Add assignments**, assign the employees who are authorized to approve all attestations.

TIP: In the **Remove assignments** area, you can remove the assignment of employees.

To remove an assignment

- Select the employee and double-click

 ✓.
- 3. Save the changes.

Related topics

Chief approval team on page 23



Attestation sequence

Once attestation is automatically or manually started, One Identity Manager creates an attestation case for each attestation object. Attestation cases record the entire attestation sequence. Each attestation step in the attestation case can be audit-proof reconstructed.

You can view the attestation cases in the navigation view under the **Attestation runs** | <attestation policy> menu item. This is where you can monitor the status of the attestation cases. Attestation cases that were not yet subject to approval are grouped under **Pending attestations**. You can see the attestation cases that have been closed by attestors or One Identity Manager grouped under **Completed attestations**.

NOTE: Attestation cases are edited in the Web Portal. For detailed information, see One Identity Manager Web Portal User Guide.

Attestation is complete when the attestation case has been granted or denied approval. You specify how to deal with granted or denied attestations on a company basis.

TIP: One Identity Manager provides various default attestation procedures for different data situations and default attestation procedures. If you use these default attestation procedures, you can configure how you deal with denied attestations.

For more information, see Default attestation and withdrawal of entitlements on page 114.

Starting attestation

There are two ways for you to add attestation cases in the One Identity Manager. You can trigger attestation through a scheduled task or start selected objects individually.

Prerequisite

• The attestation policy for this attestation is set.

To start attestation using a scheduled task

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list and run **Change master data**.



- 3. Enable the schedule entered in Calculation schedule.
 - a. In the navigation view, select **Basic configuration data | Schedules**.
 - b. Select the schedule in the result list and run **Change master data**.
 - c. Set Enabled.
 - d. Save the changes.

To start attestation for the selected objects

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list. Select **Change master data**.
- Select Run attestation cases for single objects....This opens a separate window.
- 4. In the **Attestation** column, select every object for which attestation is to be run.
- 5. Click Run.

Attestation cases are generated for the selected attestation objects. As soon as DBQueue Processor has processed the task, you will see the newly created attestation cases in the navigation view under **Attestation runs** | **<attestation policy>** | **Attestation runs** | **<year>** | **<month>** | **<day>** | **Pending attestations**.

- 6. Click Close.
- NOTE: Under certain circumstances, old, closed attestation cases are deleted from the One Identity Manager database when new attestation cases are added.

For more detailed information about configuring schedules, see the *One Identity Manager Operational Guide*.

Detailed information about this topic

- General master data for attestation policies on page 26
- Schedules on page 17

Related topics

- Running attestation for single objects on page 32
- Determining the responsible attestors on page 79
- Deleting attestation cases on page 98

Additional tasks for attestation cases

Once you have started attestation for an attestation policy, you can monitor the attestation case in One Identity Manager. The task view contains different forms with which you can



Attestation case overview

The overview form supplies you with the most important information about an attestation case. Here you can see the time by which an attestation case will be processed, depending on the processing time. One Identity Manager does not stipulate which actions are carried out if processing times out. Define your own custom actions or evaluations to deal with this situation.

To obtain an overview of an attestation case

- 1. In Manager, select the category **Attestation | Attestation runs | <attestation policy> | Attestation runs | <year> | <month> | <day>.**
- 2. Select **Pending attestations** or **Completed attestations**.
- 3. Select an attestation case from the result list.
- 4. Select Attestation case overview.

Approval sequence

For pending attestation cases, see the current status of the approval process. The approval sequence is shown as soon as the DBQueue Processor has determined the attestors for the first approval step. in the approval workflow, you can view the approval sequence, the results of each approval step, and the attestors found. If the approval procedure could not find an attestor, the attestation case is canceled by the system.

To display the approval sequence of a pending attestation case

- 1. In Manager, select Attestation | Attestation runs | <attestation policy> | Attestation runs | <year> | <month> | <day> | Pending attestations.
- 2. Select an attestation case from the result list.
- 3. Select Approval sequence.

Each approval level of an approval workflow is represented by a special control. The attestors responsible for a particular approval step are shown in a tooltip. Pending attestation questions are also shown in tooltips. These elements are colored. The color code reflects the current status of the approval level.

Table 33: Meaning of the colors in an approval sequence (in order of decreasing importance)

Color	Meaning
Blue	This approval level is currently being processed.



Color	Meaning
Green	This approval level has been granted approval.
Red	This approval level has been denied approval.
Yellow	This approval level has been deferred due to a question.
Gray	This approval level has not (yet) been reached.

Attestation history

The attestation history displays each step of an attestation case. Here you can follow all the approvals in the approval process in a chronological sequence. The attestation history is displayed for pending and closed attestations.

To display an attestation case in the attestation history

- 1. In Manager, select the category **Attestation | Attestation runs | <attestation policy> | Attestation runs | <year> | <month> | <day>.**
- 2. Select Pending attestations or Completed attestations.
- 3. Select an attestation case from the result list.
- 4. Select the **Attestation history** report.

These elements are colored. The color code reflects the status of the approval steps.

Table 34: Meaning of colors in the attestation history

Color	Meaning
Yellow	Attestation case set up.
Green	Attestor has approved.
Red	Attestor has denied.
	Attestation has been escalated.
	Approver has recalled the approval decision
Gray	Attestation has been aborted.
	Case has been assigned to an extra attestor.
	Additional attestor has withdrawn approval decision.
	Approval has been delegated
	New attestor has withdrawn the delegation.
Orange	Attestor has a question.
	The query has been answered



Color	Meaning
	Query was aborted due to change of approver
Blue	Approver has rerouted approval
	The approval step was reset automatically.

Modifying approval workflows for pending attestation cases

When approval workflows are changed, a decision must be made as to whether these changes should be applied to pending attestation cases. Configuration parameters are used to define the desired procedure.

Scenario: Another approval workflow was stored with the approval policy

The newly stored workflow is only used in new requests. If changes have been made to the approval workflow in an approval policy, any pending approval procedures are continued by default with the original workflow. The newly stored workflow is only used in new attestation cases. You can configure different behavior.

To specify how to handle pending attestation cases

- In Designer, enable the configuration parameter QER | Attestation |
 OnWorkflowAssign and select one of the following values.
 - CONTINUE: Ongoing approval processes are continued with the originally applicable workflow. The newly stored workflow is only used in new attestation cases.

This behavior also applies if the configuration parameter is not set.

- **RESET**: In ongoing approval processes, all approval decisions already taken are reset. The approval processes are restarted with the newly stored workflow. The attestation cases are run through the approval process again.
- ABORT: Ongoing approval processes are aborted. All pending attestation cases are closed. The next automatic or manual start of the attestation uses the new approval workflow.

A working copy of the originally applicable workflow is saved. The working copy is retained as long as it is used in ongoing approval processes. All unused working copies are regularly deleted using the **Maintenance approval workflows** schedule.

Scenario: A change was made to an approval workflow in use

If changes have been made to an approval workflow that is being used in pending attestation cases, any pending approval processes are continued by default with the



original workflow. The changes to the approval workflow are only implemented for new attestation cases. You can configure different behavior.

To specify how to handle pending attestation cases

- In Designer, enable the configuration parameter QER | Attestation |
 OnWorkflowUpdate and select one of the following values.
 - **CONTINUE**: Ongoing approval processes are continued with the originally applicable approval workflow. The changes to the approval workflow are only implemented for new attestation cases.
 - This behavior also applies if the configuration parameter is not set.
 - **RESET**: In ongoing approval processes, all approval decisions already taken are reset. The approval processes are restarted with the changed approval workflow. The attestation cases are run through the approval process again.
 - ABORT: Ongoing approval processes are aborted. All pending attestation cases are closed. The next automatic or manual start of the attestation uses the changed approval workflow.

A working copy of the approval workflow is saved, which contains the original version. This working copy is retained as long as it is used in ongoing approval processes. All unused working copies are regularly deleted using the **Maintenance approval workflows** schedule.

Related topics

• Determining the responsible attestors on page 79

Closing attestation cases for deactivated employees

Pending attestation cases must still be processed even if they have permanently deactivated in the meantime. This is not required very often because the affected employee may have, for example, left the company. In this case, you can use the option to close an employee's pending attestation cases automatically, if the employee is permanently disabled.

To close attestation cases automatically

 In Designer, set the configuration parameter QER | Attestation | AutoCloseInactivePerson.

The configuration parameter only applies if the employee to be attested is deactivated after the attestation case was created.

The configuration parameter does not apply if the employee is temporarily deactivated.



TIP: Write a corresponding condition for finding the attestation object on the attestation policies to prevent attestation cases being created for deactivated employees. For more information, see General master data for attestation policies on page 26.

Deleting attestation cases

The AttestationCase table expands very quickly when attestation is performed regularly. To limit the number of attestation cases in the One Identity Manager database, you can delete obsolete, closed attestation cases from the database. The attestation case properties are logged and then the attestation cases are deleted. The same number of attestation cases remain in the database as are specified in the attestation policy. For more detailed information about logging data changes tags, see the One Identity Manager Configuration Guide.

NOTE: Ensure that the logged request procedures are archived for audit reasons. For more detailed information about the archiving process, see the One Identity Manager Data Archiving Administration Guide.

Prerequisites

- The Common | ProcessState | PropertyLog configuration parameter is enabled.
- The attestation policy is enabled.

To delete attestation cases automatically

- 1. Set the Log changes when deleting option on at least three columns in the **AttestationCase** table.
 - a. In Designer, select **Database schema | Tables | AttestationCase**.
 - b. Select **Show table definition** in the task view.
 - Opens the Schema Editor.
 - c. Select a column in the Schema Editor.
 - d. In the edit view of the schema editor, select the **More** tab.
 - e. Set the option Log changes when deleting.
 - f. Repeat steps (c) to (e) for all columns that are to be recorded on deletion. There must be at least three.
 - g. Click on **Commit to database** and save the changes.
 - The changes take effect as soon as the DBQueue Processor has performed the calculation tasks.
- 2. Set the Log changes when deleting option on at least three columns in the **AttestationHistory** table.



- a. In Designer, select **Database schema | Tables | AttestationHistory**.
- b. Repeat the steps 1(b) to 1(h) for the AttestationHistory table.
- 3. Enter the number of obsolete cases in the attestation policies.
 - a. In the Manager, select **Attestation | Attestation policies**.
 - b. Select the attestation policy in the result list whose attestation cases should be deleted.
 - c. Select Change master data.
 - d. In the **Obsolete tasks limit** field, enter a value **greater than 0**.
 - e. Save the changes.
- 1 TIP: If you want to prevent attestation cases being deleted for certain attestation policies, enter the value **0** for the obsolete task limit for these attestation policies.

Attestation cases are deleted once

- A new attestation is started for an attestation policy.
 - OR -
- An attestation policy is disabled.

One Identity Manager tests how many closed attestation cases exists in the database for each attestation object of this attestation policy. If the number is more than the number of obsolete attestation cases:

- The attestation case properties and their approval sequence are recorded All columns are recorded, which are marked for logging on deletion.
- The attestation cases are deleted
 The same number of attestation cases remain in the database as are specified in the obsolete tasks limit.
- NOTE: Closed attestation cases are also deleted in the case of disabled attestation policies if the configuration parameter **Common | ProcessState | PropertyLog** is not set. In this case, the deleted attestation cases are not logged.

Related topics

General master data for attestation policies on page 26

Notifications in the attestation process

In an attestation process, various email notifications can be sent to attestors and other employees. The notification procedure uses mail templates to create notifications. The mail text in a mail template is defined in several languages. This ensures that the language of



the recipient is taken into account when the email is generated. Mail templates are supplied in the default installation with which you can configure the notification procedure.

Messages are not sent to the chief approval team by default. Fallback approvers are only notified if not enough approvers could be found for an approval step.

To use notification in the request process

- 1. Ensure that the email notification system is configured in One Identity Manager. For more detailed information, see the *One Identity Manager Installation Guide*.
- 2. Enable the **QER | Attestation | DefaultSenderAddress** configuration parameter in Designer and enter the sender address used to send the email notifications.
- 3. Ensure that all employees have a default email address. Notifications are sent to this address. For more detailed information, see the *One Identity Manager Identity Management Base Module Administration Guide*.
- 4. Ensure that a language can be determined for all employees. Only then can they receive email notifications in their own language. For more detailed information, see the *One Identity Manager Identity Management Base Module Administration Guide*.
- 5. Configure the notification procedure.

Related topics

Custom mail templates for notifications on page 35

Demanding attestation

When a new attestation case is made, the attestor is notified by mail. Demands for attestation can be configured separately for each approval step.

Prerequisite

The configuration parameter QER | Attestation | MailTemplateIdents |
 RequestApproverByCollection is disabled.

To set up the notification procedure

- On the **Mail templates** tab of the approval step, enter the following data:
 - Mail template request: Attestation approval required
 - TIP: To allow approval by email, select the **Attestation approval required** (by email) mail template.
- NOTE: You can schedule demands for attestation to send a general notification if there are attestations pending. This replaces single demands for attestation at each approval step.



Related topics

- Email notification: Scheduling attestation demands on page 103
- Attestation by mail on page 110
- Editing approval steps on page 51

Reminding attestors

If an attestor has not made a decision by the time the reminder timeout expires, notification can be sent by email as a reminder. The attestors work time applies to the time calculation.

Prerequisite

• The configuration parameter **QER** | **Attestation** | **MailTemplateIdents** | **RequestApproverByCollection** is disabled.



To set up the notification procedure

Enter the following data for the approval step.

Table 35: Properties of the approval step for notification

Property Meaning

interval (hours)

Reminder Number of working hours to elapse after which the attestor is notified by mail that there are still pending attestation cases for attestation.

> The reminder interval is set to 30 minutes, by default. To change this interval, modify the Checks reminder interval and timeout of attestation cases schedule.



NOTE: Ensure that a state and/or county is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about employees' calculating working hours, see the One Identity Manager Identity Management Base Module Administration Guide.

If more than one attestor was found, each attestor will be notified. The same applies if an additional attestor has been assigned.


If an attestor delegated the approval, the time point for reminding the delegation recipient is recalculated. The delegation recipient and all the other attestors are notified. The original attestor is not notified.

If an attestor has made an inquiry, the time point for reminding the queried employee is recalculated. As long as the inquiry has not been answered, only this employee is notified.

Mail template reminder Select the **Attestation - Remind approver** mail template.



TIP: To allow approval by email, select the **Attestation** remind approver (by email) mail template.



Related topics

- Email notification: Scheduling attestation demands on page 103
- Attestation by mail on page 110
- Editing approval steps on page 51



Scheduling attestation demands

Attestors can be regularly notified of attestation cases that are pending. These regular notifications replace the individual prompts and attestation reminders that are configured in the approval step.

To send regular notifications about pending attestations

1. Enable the **QER | Attestation | MailTemplateIdents | RequestApproverByCollection** configuration parameter in Designer.

By default, a notification is sent with the **Attestation - pending requests for approver** mail template.

- 1 TIP: To use something other than the default mail template for these notifications, change the value of the configuration parameter.
- 2. In Designer, configure and enable the **Inform approver about pending attestations** schedule.

For detailed information, see One Identity Manager Operational Guide.

Reminding attestors about attestation objects

The hierarchical role manager and those responsible for system entitlements or system roles can view all pending attestation cases for this object in the Web Portal. If necessary, they can send reminders to attestors of selected attestation objects.

To send notification about a specific attestation object

- In Designer, set the configuration parameter QER | Attestation |
 MailTemplateIdents | RemindApproverByObject.
 - By default, notification is sent using the **Attestation remind approver of all open object attestations** template.
- TIP: To use something other than the default mail template for these notifications, change the value of the configuration parameter.

To send notifications user the Web Portal. For detailed information, see *One Identity Manager Web Portal User Guide*.

Granting or denying attestation cases

When an attestation case is granted approval or denied it, other employees receive notification. Notification may occur after approval or denial of a single approval step or



once the entire approval process is complete. You can specify the recipient of the notification as required by the company.

Attestation cases can be automatically granted or denied approval once a specified time period has been exceeded. Notification is sent in the same way in this case.

To set up the notification procedure

- 1. Create custom mail templates for sending notification if attestation cases have been granted or denied approval.
- 2. Create company specific processes for notifications.
- 3. If notification should be sent immediately after an approval decision is made for a single approval step, enter the following data on the **Mail templates** tab of the approval step.

Table 36: Properties of the approval step for notification

Property	Meaning
Mail template approved	Mail template to be used for email notification when an approval step is approved.
Mail template denied	Mail template to be used for email notification when an approval step is denied.

- OR -

If notification should be sent after the entire approval procedure is complete, enter the following data in the approval policy.

Table 37: Properties of an approval policy for notifications

Property	Meaning
Mail template approved	Mail template to be used for email notifications when an attestation case is approved.
Mail template denied	Mail template to be used for email notifications when an attestation case is denied.

Detailed information about this topic

- Custom mail templates for notifications on page 35
- Custom notification processes on page 41
- Editing approval steps on page 51
- Approval policies for attestations on page 43



Notifying delegates

If required, a delegator can receive notifications if the recipient of the delegation has made an approval decision in an attestation case. A notification is sent once an employee has been determined as an attestor due to delegation and has made an approval decision for the attestation case.

To send a notification when the employee who was delegated an approval approves or denies the attestation.

- In Designer, set the **QER | ITShop | Delegation | MailTemplateIdents | InformDelegatorAboutDecisionAttestation** configuration parameter.
 - By default, a notification is sent with the **Delegation inform delegator about decided attestation** mail template.
- TIP: Change the value of the configuration parameter in order to use custom mail templates for these mails.

Delegations are taken into account in the following default approval procedures.

Table 38: Delegation relevant default approval procedures

Delegation of	Approval procedure
Department responsibilities	DM, ED
Cost center responsibilities	PM
Location responsibilities	LM
Business role responsibilities	MO, OM, RM, RR
Employee responsibilities	CM, EM
Memberships in business roles	OR
Memberships in application roles	AA, AD, AL, AN, AO, AP, AR, AS, AT, AY, EN, EO, OA, SO

Example

Jon Blogs is responsible for the business role R1. He delegates his responsibility for the business role to Clara Harris. Clara Harris is herself responsible for business role R2.

A member of business role R1 is to be attested. Jon Bloggs is established as an attestor through the **OM - Manager of a specific role** approval process. The attestation case is assigned to Clara Harris for approval through delegation. Jon



Blogs is notified as soon as Clara Harris has made her approval decision for the attestation case.

A member of business role R2 is to be attested. Clara Harris is established as an attestor through the **OM - Manager of a specific role** approval process. No notification is sent because Clara Harris does not make the approval decision due to delegation.

For more detailed information about delegating responsibilities, see the *One Identity Manager IT Shop Administration Guide*.

Related topics

- Default approval procedures on page 58
- Notifications from additional attestors on page 108

Aborting attestation cases

Email notifications can be sent to other employees when an attestation case is aborted. You can specify the recipient of the notification as required by the company.

To set up the notification procedure

- 1. Create custom mail templates for sending notification if attestation cases have been aborted.
- 2. Create company specific processes for notifications.
- 3. Enter the following data for the approval policy:

Mail template aborted: Mail template to be used for email notifications when an attestation case is aborted.

Detailed information about this topic

- Custom mail templates for notifications on page 35
- Custom notification processes on page 41

Escalation of attestation cases

Email notifications can be sent to the attestation policy's owner when an attestation case is escalated.



To set up the notification procedure

- On the Mail templates tab of the approval step, enter the following data:
 Mail template escalation: Attestation Escalation
- 2. Assign an owner to the attestation policies.

Related topics

- Escalating an attestation case on page 84
- General master data for attestation policies on page 26
- Editing approval steps on page 51

Delegating attestations

If, in an approval step, other attestors can be authorized to make the approval decision, the additional attestors can be prompted to approve by email. The same applies if the attestation can be delegated.

To set up the notification procedure

- On the Mail templates tab of the approval step, enter the following data:
 Mail template delegation: Attestation Delegated/additional approval
 - TIP: To enable approval by e-mail, select the **Attestation delegated/additional approval (by email)** mail template.

Related topics

- Attestation by mail on page 110
- Appointing other attestors on page 83
- Editing approval steps on page 51

Rejecting approvals

The original attestor must be notified if an additional attestor or employee to whom an attestation has been delegated refuses the approval decision.

To set up the notification procedure

On the Mail templates tab of the approval step, enter the following data:
 Mail template rejection: Attestation - Reject approval



TIP: If you allow approval by email, select the mail template **Attestation** - reject approval (by mail).

Related topics

- Attestation by mail on page 110
- Appointing other attestors on page 83
- Editing approval steps on page 51

Notifications with questions

Employees can be notified when a question about an attestation is asked. Similarly, the attestors can also be notified as soon as the question is answered.

To send a notification when an attestor asks a question

• In Designer, enable the **QER | Attestation | MailTemplateIdents | QueryFromApprover** configuration parameter.

A notification is sent by default with the **Attestation - question** mail template.

To send a notification to the attestor when the queried employee answers a question

• In Designer, set the **QER | Attestation | MailTemplateIdents | AnswerToApprover** configuration parameter.

A notification is sent by default with the **Attestation - answer** mail template.

1 TIP: Change the value of the configuration parameter in order to use custom mail templates for these mails.

Notifications from additional attestors

The original attestor can be notified when an additional attestor or an employee who has been delegated an attestation has granted or denied the attestation. This mail is send the moment the approval step has been decided.

To send a notification when the additional attestor approves or rejects the attestation

• In Designer, enable the **QER | Attestation | MailTemplateIdents | InformAddingPerson** configuration parameter.

A notification is sent by default with the **attestation - approval of added step** mail template.



To send a notification when the employee who was delegated an approval approves or denies the attestation.

• In Designer, enable the **QER | Attestation | MailTemplateIdents | InformDelegatingPerson** configuration parameter.

A notification is sent by default with the **attestation - approval of delegated step** mail template.

TIP: Change the value of the configuration parameter in order to use custom mail templates for these mails.

Link for verifying new external users

If a new user logs in to the Web Portal or new external employees need to be certified, they receive an email containing a link to the Password Reset Portal. Using the link, employees verify their contact email address, set a password and password questions.

To send notification with a verification link

• In the Designer, set the **QER | Attestation | MailTemplateIdents | NewExternalUserVerification** configuration parameter.

By default, notification is sent using the **Attestation - new external user verification link** mail template.

1 TIP: To use something other than the default mail template for these notifications, change the value of the configuration parameter.

Detailed information about this topic

- User attestation and recertification on page 123
- Self-registration of new users in the Web Portal on page 126
- Adding new employees using a manager or employee administrator on page 128

Default mail templates

One Identity Manager supplies mail templates by default. These mail templates are available in English and German. If you require the mail body in other languages, you can add mail definitions for these languages to the default mail template.

To edit a default mail template

• In Manager, select the **Attestation | Basic configuration data | Mail templates** | **Predefined** category.



Related topics

• Custom mail templates for notifications on page 35

Attestation by mail

To provide attestors who are temporarily unable to access One Identity Manager tools with the option of making attestation case decisions, you can set up attestation by email. In this process, attestors are notified by email when an attestation case is pending their approval. Approvers can use the links in the email to make approval decisions without having to connect to the Web Portal. This generates an email that contains the approval decision and in which attestors can state the reasons for their approval decision. This email is sent to a central Microsoft Exchange mailbox. The One Identity Manager checks this mailbox regularly, evaluates the incoming emails and updates the status of the attestation cases correspondingly.

1 IMPORTANT: An attestation cannot be sent by email if multi-factor authentication is configured for the attestation policy. Attestation emails for such attestations produce an error message.

Prerequisites

- 1. The Microsoft Exchange environment is configured with
 - Microsoft ExchangeClient Access Server version 2007, Service Pack 1 or higher
 - Microsoft Exchange Web Service .NET API Version 1.2.1, 32-bit
- 2. The user account used by One Identity Manager Service to register with the Microsoft Exchange environment requires full access to the mailbox given in the configuration parameter **QER | Attestation | MailApproval | Inbox**.
- 3. The configuration parameter **QER | Attestation | MailTemplateIdents | RequestApproverByCollection** is disabled.

To set up attestation by email

- In Designer, enable the configuration parameter QER | Attestation | MailApproval | Inbox and enter the mailbox to which the approval mails are to be sent.
- 2. Set up mailbox access.
 - a. By default, One Identity Manager uses the One Identity Manager Service user account to log in to the Microsoft Exchange Server and access the mailbox.
 - OR -
 - b. You enter a separate user account for logging in to the Microsoft Exchange Server for mailbox access. Enabled the following configuration parameters to do this.



Table 39: Configuration parameters for logging in to Microsoft Exchange Server

Configuration parameter	Meaning
QER Attestation MailApproval Account	Name of the user account.
QER Attestation MailApproval Domain	User account's user account.
QER Attestation MailApproval Password	Password of the user account.

3. In Designer, enable the configuration parameter **QER | Attestation | MailTemplateIdents | ITShopApproval**.

The mail template used to create the attestation mail is stored with this configuration parameter. You can use the default mail template or add a custom mail template.

- TIP: To use a company-specific mail template for attestation mails, change the value of the configuration parameter. In this case, also change the VI_MailApproval_ProcessMail script.
- 4. Assign the following mail templates to the approval steps:

Table 40: Mail templates for approval by mail

Property	Mail template
Mail template request	Attestation - approval required (by mail)
Mail template reminder	Attestation - remind approver (by mail)
Mail template delegation	Attestation - delegated/additional approval (by mail)
Mail template rejection	Attestation - reject approval (by mail)

5. In Designer, configure and enable the schedule **Processes attestation mail** approvals.

Based on this schedule, One Identity Manager regularly checks the mailbox for new attestation mails. Based on this schedule, the regularly checks the mailbox every 15 minutes. You can change how frequently it checks, by altering the interval in the schedule as required.

To clean up a mail box

In Designer, enable the configuration parameter QER | Attestation |
 MailApproval | DeleteMode and select one of the following values.



Table 41: Mailbox cleanup

Value	Method
HardDelete	The processed e-mail is immediately deleted.
MoveToDeletedItems	The processed email is moved to the Deleted objects mailbox folder.
SoftDelete	The processed email is moved to the Active Directoryrecycling bin and can be restored if necessary.

NOTE: If you use the MoveToDeletedItems or SoftDelete cleanup method, you should empty the **Deleted objects** folder and the Active Directory recycling bin on a regular basis.

Related topics

- Processing attestation mails on page 112
- Custom mail templates for notifications on page 35
- Demanding attestation on page 100
- Reminding attestors on page 101
- Delegating attestations on page 107
- Rejecting approvals on page 107
- Setting up multi-factor authentication for attestation on page 81

Processing attestation mails

The schedule **Processes attestation mail approvals** starts the process VI_Attestation_Process Approval Inbox. This process runs the VI_MailApproval_ProcessInBox script, which searches the mailbox for new attestation mails and updates the attestation cases in the One Identity Manager database. The contents of the attestation mail are processed at the same time.

- NOTE: The validity of the email certificate is checked with the script VID_ ValidateCertificate. You can customize this script to suit your security requirements. Take into account that this script is also used for attestations by email.
 - If an self-signed root certification authority is used, the user account under which the One Identity Manager Service is running, must trust the root certificate.
- TIP: VI_MailApproval_ProcessInBox finds the Exchange Web Service URL which uses AutoDiscover through the given mailbox as default. This assumes that the AutoDiscover service is running.
 - If this is not possible, enter the URL in the configuration parameter QER\Attestation\MailApproval\ExchangeURI.



Attestation mails are processed with the VI_MailApproval_ProcessMail script. The script finds the relevant approval decision, sets the **Approved** option if approval is granted, and stores the reason for the approval decision with the attestation cases. The attestor is found through the sender address. Then the attestation mail is removed from the mailbox depending on the selected cleanup method.

NOTE: If you use a custom mail template for the attestation mail, check the script and modify it as required. Take into account that this script is also used for approval decisions for IT Shop requests by email.



Default attestation and withdrawal of entitlements

One Identity Manager provide various default attestation procedures for different data situations and default attestation procedures.

Data situations for default attestations:

- System entitlements owned by an employee
- System entitlements assigned to system entitlements
- System entitlements assigned to hierarchical roles
- System roles assigned to an employee
- Company resources assigned to system roles
- System roles assigned to hierarchical roles
- Business and application role memberships
- Employee master data for a new One Identity Manager user
- Employee master data for an existing One Identity Manager user

The attestation polices required for attesting employee master data are also supplied by default. You can also use the default supplied attestation policies without modifying them. The prerequisites and the attestation sequence for employee data are described in User attestation and recertification.

You can set up attestation policies easily in Web Portal using default attestation procedures for other data situations. You can also use the default attestation policies supplied without customizing them. Furthermore, you can configure how to deal with denied attestations that are based on these default attestation procedures. If your specific data situation allows, denied entitlements can be removed by the One Identity Manager following the attestation.

To remove denied permissions automatically

- In Designer, set the configuration parameter QER | Attestation |
 AutoRemovalScope and the configuration subparameters.
- 2. If the entitlements were obtained through IT Shop, specify whether these requests should be unsubscribed or canceled. To do this, enable the configuration parameter



QER | Attestation | AutoRemovalScope | PWOMethodName and select a value.

- Abort: Requests are aborted. In this case, they do not go through a
 cancelation workflow. The requested entitlements are withdrawn without
 additional checks.
- **Unsubscribe**: Requests are unsubscribed. They go through the cancelation workflow defined in the approval policies. Withdrawal of the entitlement can thus be subjected to an additional check.
 - If the cancelation is denied, the entitlement is not withdrawn even though the attestation has been denied.

If the configuration parameter is not set, the requests are aborted.

1 IMPORTANT: If role memberships or system roles are removed from an employee they lose the unapproved entitlement. They also lose all other company resources inherited through this role. These may be other system entitlements or account definitions. If necessary, system entitlements are removed and company resources are deleted from the employee.

Check whether your data situation allows automatic withdrawal of entitlements before you enable configuration parameters under **QER | Attestation | AutoRemovalScope**.

Automatic removal of entitlements is triggered by an additional approval step with the EX approval procedure in the default approval workflows.

Attestation sequence with subsequence withdrawal of denied entitlements:

- 1. Attestation is carried out using a default attestation procedure.
- 2. The attestor denies attestation. The approval step is not granted approval and approval is passed on the next approval level with the EX approval procedure.
- 3. The approval step triggers the event AUTOREMOVE. This runs the process VI_Attestation_AttestationCase_AutoRemoveMembership.
- 4. The process runs the script VI_AttestationCase_RemoveMembership. This removes the affected entitlement depending on which configuration parameters are set.
- 5. The script sets the approval step status to **Denied**. This means the entire attestation case is finally denied.
- 6. Tasks to recalculate inheritance are entered in the DBQueue.

Detailed information about this topic

- System entitlements attestation on page 116
- System role attestation on page 118
- Application role attestation on page 121
- Business role attestation on page 121



System entitlements attestation

Installed modules: Target System Base Module

When you use the **System entitlement memberships attestation** default attestation policy or have set up attestation policies with the **System entitlement memberships attestation** default attestation procedure, you can configure automatic removal of system entitlements through the **QER | Attestation | AutoRemovalScope | GroupMembership** configuration parameter. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the system entitlement.

Table 42: Effect of configuration parameters when attestation denied

Configuration parameter	Effect when set
QER Attestation AutoRemovalScope GroupMembership RemoveDirect	Direct membership of the user account in the system entitlement, is removed.
QER Attestation AutoRemovalScope GroupMembership RemovePrimaryRole	If membership in the system entitlement was inherited through a primary role, the role is withdrawn from the employee. This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope GroupMembership RemoveRequestedRole	If membership of the system entitlement was inherited through a requested role, the role request is canceled or unsubscribed. This removes all indirect assignments obtained by the employee through this role. Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 114.
QER Attestation AutoRemovalScope GroupMembership RemoveDelegatedRole	If membership in the system entitlement was inherited through a delegated role, delegation of this role is canceled or unsubscribed. This removes all indirect assignments obtained by the employee through this role. Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 114.
QER Attestation	If membership of the system entitlement was requested



Configuration parameter	Effect when set	
AutoRemovalScope	through the IT Shop, the request is canceled or unsubscribed.	
GroupMembership RemoveRequested	Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 114.	
QER Attestation AutoRemovalScope	System roles incorporating the system entitlements are withdrawn from the employee.	
GroupMembership RemoveSystemRole	This removes all indirect assignments obtained by the employee through this system role.	
	This configuration parameter is only available if the System Roles Module is installed.	
QER Attestation AutoRemovalScope	The system entitlement assignment to hierarchical roles is removed and	
GroupMembership RemoveDirectRole	therefore removes the system entitlement assignment to all user accounts whose associated employees inherit assignments from these roles.	
	IMPORTANT: Employees whose attestation has been approved can lose the system entitlement through this.	
	Check the side-effects of this configuration parameter in your situation before you set it.	

When you use the **Attestation of assignments to system entitlements** default attestation policy or have set up attestation policies with the **Attestation of assignments to system entitlements** default attestation procedure, you can configure automatic removal of system entitlements through the **QER | Attestation | AutoRemovalScope | UNSGroupInUNSGroup** configuration parameter.

Table 43: Effect of configuration parameters when attestation denied

Configuration parameter	Effect when set
QER Attestation AutoRemovalScope UNSGroupInUNSGroup RemoveDirect	Assignment of the system entitlement to a system entitlement is removed.

You can configure automatic withdrawal of system entitlement assignments to hierarchical roles, if you use the following default attestation policies or procedures:

- Attestation of system entitlement assignments to department
- Attestation of system entitlement assignments to cost centers
- Attestation of system entitlement assignments to locations
- Attestation of system entitlement assignments to business roles

Enabled the following configuration parameters to do this.



Table 44: Effect of configuration parameters when attestation denied

Configuration parameter	Effect when set
QER Attestation AutoRe- movalScope Depart- mentHasUNSGroup RemoveDirect	The assignment of the system entitlement to a department is removed and
	therefore the system entitlement is removed from all employees that inherit assignments from this department.
QER Attestation AutoRe- movalScope ProfitCen-	The assignment of the system entitlement to a cost center is removed and
terHasUNSGroup RemoveDirect	therefore the system entitlement is removed from all employees that inherit assignments from this cost center.
QER Attestation AutoRe- movalScope LocalityHasUNSGroup	The assignment of the system entitlement to a location is removed and
RemoveDirect	therefore the system entitlement is removed from all employees that inherit assignments from this location.
QER Attestation AutoRe- movalScope OrgHasUNSGroup	The assignment of a system entitlement to a business role is removed and
RemoveDirect	therefore the system entitlement is removed from all employees that inherit assignments from this business role.

System role attestation

Installed modules: System Roles Module

If you use the **System role membership attestation** default attestation policy or have set up attestation policies with the **System entitlement memberships attestation** default attestation procedure, you can configure automatic removal of system roles through the **QER | Attestation | AutoRemovalScope | ESetAssignment** configuration parameter. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the system role.

Table 45: Effect of configuration parameters when attestation denied

Configuration parameter	Effect when set
QER Attestation	Direct membership in the system role is removed.
AutoRemovalScope	This removes all indirect assignments obtained by the



Configuration parameter	Effect when set
ESetAssignment RemoveDirect	employee through this system role.
QER Attestation AutoRemovalScope	If the system role was inherited through a primary role, the role is withdrawn.
ESetAssignment RemovePrimaryRole	This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope	If the system role was inherited through a requested role, the role request is canceled or unsubscribed.
ESetAssignment RemoveRequestedRole	This removes all indirect assignments obtained by the employee through this role.
	Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 114.
QER Attestation AutoRemovalScope ESetAssignment RemoveDelegatedRole	If the system role was inherited through a delegated role, the delegation of this role is canceled or unsubscribed.
	This removes all indirect assignments obtained by the employee through this role.
	Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 114.
QER Attestation AutoRemovalScope ESetAssignment RemoveRequested	If the system role was requested through the IT Shop, the request is canceled or unsubscribed.
	This removes all indirect assignments obtained by the employee through this system role.
	Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 114.
QER Attestation AutoRemovalScope ESetAssignment RemoveDirectRole	The system role assignment to hierarchical roles is removed.
	This removes the system role assignment to all employees, which inherits assignments from these roles.
	IMPORTANT: Employees whose attestation has been approved can lose the system role through this.
	Check the side-effects of this configuration parameter in your situation before you set it.



If you use the **System role entitlement assignment attestation** default attestation policy or have set up attestation policies with the **System role entitlement assignment attestation** default attestation procedure, you can configure automatic removal of the assignments through the **QER | Attestation | AutoRemovalScope | ESetHasEntitlement** configuration parameter.

Table 46: Effect of configuration parameters when attestation denied

Configuration parameter	Effect when set
QER Attestation AutoRemovalScope ESetHasEntitlement RemoveDirect	Assignment of the company resource to a system role is removed.

You can configure automatic withdrawal of system role assignments to hierarchical roles, if you use the following default attestation policies or procedures:

- Department system role assignment attestation
- Cost center system role assignment attestation
- Location system role assignment attestation
- Business role system role assignment attestation

Enabled the following configuration parameters to do this.

Table 47: Effect of configuration parameters when attestation denied

Configuration parameter	Effect when set
QER Attestation AutoRe- movalScope DepartmentHasESet RemoveDirect	The assignment of the system role to a department is removed and
	therefore the system role is removed from all employees that inherit assignments from this department.
QER Attestation AutoRe- movalScope ProfitCenterHasESet RemoveDirect	The assignment of the system role to a cost center is removed and
	therefore the system role is removed from all employees that inherit assignments from this cost center.
QER Attestation AutoRe- movalScope LocalityHasESet	The assignment of the system role to a location is removed and
RemoveDirect	therefore the system role is removed from all employees that inherit assignments from this location.
QER Attestation AutoRe- movalScope OrgHasESet	The assignment of the system role to a business role is removed and
RemoveDirect	therefore the system role is removed from all employees that inherit assignments from this business role.



Application role attestation

When you use the **Application role membership attestation** default attestation policy or have set up attestation policies with the **Application role membership attestation** default attestation procedure, you can configure automatic removal of application roles through the **QER | Attestation | AutoRemovalScope | AERoleMembership** configuration parameter. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the application role.

Table 48: Effect of configuration parameters when attestation denied

Configuration parameter	Effect when set
QER Attestation AutoRemovalScope AERoleMembership RemoveDirectRole	The employee's secondary membership is removed from the application role.
	This removes all indirect assignments obtained by the employee through this application role. Membership in dynamic roles is not removed in this process.
QER Attestation AutoRemovalScope AERoleMembership RemoveRequestedRole	If the employee requested the application role through the IT Shop, the request is canceled or unsubscribed.
	This removes all indirect assignments obtained by the employee through this application role.
	Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 114.
QER Attestation AutoRemovalScope AERoleMembership RemoveDelegatedRole	If the application role was delegated to the employee, delegation is canceled or unsubscribed.
	This removes all indirect assignments obtained by the employee through this application role.
	Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 114.

Business role attestation

Installed modules: Business Roles Module



When you use the **Business role membership attestation** default attestation policy and have set up attestation policies with the **Business role membership attestation** default attestation procedure, you can configure automatic removal of business roles through the configuration parameter **QER | Attestation | AutoRemovalScope | RoleMembership**. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the business role.

Table 49: Effect of configuration parameters when attestation denied

Configuration parameter	Effect when set
QER Attestation AutoRemovalScope RoleMembership RemoveDirectRole	The employee's secondary membership in the business role is removed.
	This removes all indirect assignments obtained by the employee through this business role. Membership in dynamic roles is not removed by this.
QER Attestation AutoRemovalScope	If the employee requested the business role through the IT Shop, the request is canceled or unsubscribed.
RoleMembership RemoveRequestedRole	This removes all indirect assignments obtained by the employee through this business role.
	Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 114.
QER Attestation AutoRemovalScope RoleMembership RemoveDelegatedRole	If the business role was delegated to the employee, delegation is canceled or unsubscribed.
	This removes all indirect assignments obtained by the employee through this business role.
	Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 114.



User attestation and recertification

Use the One Identity Manager attestation functionality to regularly check and authorize employees' master data, target system entitlements and assignments. In addition, One Identity Manager provides default procedures for managers to quickly attest and certify the master data of newly added One Identity Manager users in the One Identity Manager database. This functionality can be used, for example, if external employees, such as contract workers, should be provided with temporary access to the One Identity Manager. The sequence is different for internal and external employees.

Regular recertification can be run through scheduled tasks.

In the context of an attestation, a manager can check and update the master data for the user to be certified, if necessary. Use the Web Portal for attestation.

Detailed information about this topic

- Configuring user attestation and recertification on page 124
- Attesting new users on page 125
- Recertifying existing users on page 134

One Identity Manager users for attesting and recertifying users

The following user are involved in attestation and recertification of employees.

Table 50: Users

User	Tasks
Employee administrators	Employee administrators must be assigned to the application role Identity Management Employees Administrators.
	Users with this application role:
	Can edit master data for all employees



User	Tasks
	Can assign a manager.
	 Can assign company resources to employees.
	 Check and authorize employee master data.
	 Create and edit risk index functions.
	 Edit password policies for employee passwords
	 Delete employee's security keys (Webauthn)
Manager	 Check employee master data of the user to be certified.
	 Update employee master data as required.
	 Assign another manager if required.
	Attests the master data.
Attestors for external users	Attestors for external users must be assigned to the application role Identity & Access Governance Attestation Attestors for external users .
	Users with this application role:
	Attests new, external employees.
Administrators for attestation	Administrators must be assigned to the Identity & Access Governance Attestation Administrators application role.
cases	Users with this application role:
	 Modify the attestation policies if necessary.
	 Create more schedules if required.
Web Portal users	 Log on to the Web Portal and enter their master data,

Configuring user attestation and recertification

To use the attestation and recertification function for new internal users

- 1. In Designer, set the configuration parameter **QER | Attestation | UserApproval**.
- 2. Assign at least one employee to the **Identity Management | Employees | Administrators** application role.

All employees with this application role can assign a manager to the employee being attested during the attestation process.



To use the attestation and recertification function for new external users

- 1. In the Designer, set the following configuration parameters:
 - QER | Attestation | ApproveNewExternalUsers: Select the value 1.
 - QER | WebPortal | PasswordResetURL: Enter the URL for the Password Reset Portal.
 - QER | Attestation | MailTemplateIdents |
 NewExternalUserVerification: Mail template sending verification links.
 - **QER | Attestation | NewExternalUserTimeoutInHours**: For new external users, specify the duration of the verification link in hours.

The default is 4 hours. If logging in to the Password Reset Portal fails because the timeout has expired, the user can ask for a new verification link to be sent. To change the duration of the verification link, change the value in the configuration parameter.

• **QER | Attestation | NewExternalUserFinalTimeoutInHours**: Specify the duration in hours, within which self-registration must be successfully completed.

If the user does not complete registration with 24 hours, the attestation case quits. To register anyway, the user must log in again to the Web Portal from the beginning. To change the checkout duration of registration, change the value of the configuration parameter.

2. Assign at least one employee to the **Identity & Access Governance | Attestation | Attestor for external users** application role.

Detailed information about this topic

- Self-registration of new users in the Web Portal on page 126
- Adding new employees using a manager or employee administrator on page 128
- Importing new employee master data on page 130
- The recertification sequence on page 135
- Link for verifying new external users on page 109

Attesting new users

Attestation of new users is divided into three use cases by One Identity Manager:

- 1. Registration of new external users logging in to the Web Portal.
- 2. Adding new employees in the Manager or using a manager in the Web Portal.
- 3. Adding a new employee by importing employee master data.

The result of attestation is the same in all three cases.



• Certified, enabled employees that can access all entitlements assigned to them in One Identity Manager and the connected target systems.

Company resources are inherited. Account definitions are assigned to internal employees.

- OR -
- Denied and permanently deactivated employees.

Disable employees cannot log onto One Identity Manager tools. Company resources are not inherited. Account definitions are not automatically assigned. User accounts associated with the employee are also locked or deleted. You can customize the behavior to meet your requirements.

Self-registration of new users in the Web Portal

Users who are not yet registered have the option to register themselves to use the Web Portal. These users can log in to the Web Portal once a manager has attested the user's master data and the set the user's password. This adds an external employee to the One Identity Manager database.

Attestation sequence:

1. The user logs in to the Web Portal for the first time and enters the required properties.

A new employee object is added to the One Identity Manager database with properties:

Table 51: Properties of a newly added employee

Property	Value
Certification status	New
External	Set
Contact email address	Email address to send the verification link to.
Permanently disabled	Set
No inheritance	Set

2. Attestation is started automatically.

Attestation policy used: **New user certification**

NOTE: The attestation only starts automatically if the **QER | Attestation | UserApproval** configuration parameter is set. Otherwise the new user remains disabled permanently until a manager changes the employee master data manually.



- 3. Attestors are found.
 - Effective approval policy: Certification of users
- 4. If the QER | Attestation | ApproveNewExternalUsers configuration parameter is set and the value is 1, attestation of members of the Identity & Access Governance | Attestation | Attestors for external users is submitted.
 - a. If an attestor for external users denies the attestation, the attestation case is closed. The employee object's properties are updated in the database.

Table 52: Properties of an external employee with denied attestation

Property	Value	Explanation
Certification status	Denied	
External	Set	
Permanently disabled	Set	The user cannot log in to the Web Portal.
No inheritance	Set	Company resources are not inherited.

- b. If an attestor for external users approves attestation, an email with a verification link is sent to the new user.
- NOTE: If the **QER | Attestation | ApproveNewExternalUsers** configuration parameter is not set or the value is **0**, an email with a verification link is sent immediately to the new user.
- 5. Once the user has followed the link and a password and a password question have been set, the attestation case is approved. The employee object's properties are updated in the database.

Table 53: Properties of an external employee with approved attestation

Property	Value	Explanation
Certification status	Certified	
External	Set	
Permanently disabled	Not set	The user can log on to Web Portal.
No inheritance	Not set	Company resources are inherited.

The default is 4 hours. If logging in to the Password Reset Portal fails because the timeout has expired, the user can ask for a new verification link to be sent.

If the user does not complete registration with 24 hours, the attestation case quits. To register anyway, the user must log in again to the Web Portal from the beginning.



Related topics

Configuring user attestation and recertification on page 124

Adding new employees using a manager or employee administrator

You can also attest new users if new employees are added in the Manager or if a manager in the Web Portal adds a new employees. Specify the required behavior with the configuration parameter **QER | Attestation | UserApproval | InitialApprovalState**. This configuration parameter has the default value **0**. This gives each new employee the certification status **Certified**. Automatic attestation is not carried out.

To automatically attest new users

• In Designer, enable the **QER | Attestation | UserApproval | InitialApprovalState** configuration parameter and set the value to **1**.

All employees added to the database from this point on are given the certification status **New**. This means automatic attestation of these employees is carried out.

The sequence is different for internal and external employees.

Attestation sequence:

1. Enter the new user's master data and assign a manager to them.

For detailed information about adding employees, see the *One Identity Manager Identity Management Base Module Administration Guide* and the *One Identity Manager Web Portal User Guide*.

The certification status corresponds to the value of the configuration parameter **QER** | **Attestation** | **UserApproval** | **InitialApprovalState**. If the configuration parameter has the value **1**, certification status is set to **New**.

By default, the employee is active and can log in immediately to One Identity Manager.

- If new users are not allowed to log in to One Identity Manager until their master data has been attested, run the task **Disable employee** permanently.
- 2. Once the employee master data has been saved, attestation starts.

Attestation policy used: **New user certification**

3. Attestors are found.

Effective approval policy: Certification of users

4. If the **External** option is set for the employee:

Attestation takes place as described in the Self-registration of new users in the Web Portal section, steps 4 to 5.



- 5. If the **External** option is set for the employee:
 - a. One Identity Manager checks whether you have assigned a manager to the employee.
 - If you have assigned a manager to the employee, the case is immediately passed on to them for approval.
 - If you have not assigned a manager to the employee, the case is assigned to the employee administrators for approval.
 - b. An employee administrator checks your master data and also assigns a manager to you.
 - The employee administrator assigns a manager and approves attestation. The attestation case is assigned to the manager for approval.
 - If the employee administrator does not assign a manager and approves attestation, the attestation case is closed. The employee object's properties are updated in the database.

Table 54: Properties of an employee with approved attestation

Property	Value	Explanation
Certification status	Certified	
External	Not set	
Disabled permanently	Not set	
No inheritance	Not set	Company resources are inherited.

• If an employee administrator denies attestation approval, the attestation case is closed. Your employee properties are updated in the database.

Table 55: Properties of an employee with rejected attestation

Property	Value	Explanation
Ceritifcation status	Rejected	
External	Not set	
Permanently disabled	Set	
No inheritance	Set	Company resources are not inherited.
		User accounts are not created automatically.

c. The manager can deny attestation approval if he is not the manager in charge of the employee.



- The manager can assign another person as manager. The attestation case is immediately assigned to this manager.
- If the manager does not know who your manager is, approval is returned to the employee administrators. These can
 - Assign another manager
 - Not assign another manager and grant attestation approval
 - Deny attestation approval
- d. If the manager approves attestation, the attestation case is closed. Your employee properties are updated in the database.

Table 56: Properties of an employee with approved attestation

Property	Value	Explanation
Certification status	Certified	
External	Not set	
Disabled permanently	Not set	
No inheritance	Not set	Company resources are inherited.

NOTE: Only employee administrators can ultimately deny attestation approval. If a manager denies attestation, the case is returned to the employee administrators for approval in any case.

Related topics

• Configuring user attestation and recertification on page 124

Importing new employee master data

You can request attestation of new employees if the master data is imported from other systems into the One Identity Manager database. To ensure that new employees are automatically attested, you must set the employee's certification status to **New** (Person.ApprovalState = '1'). There are two possible ways to do this:

1. The configuration parameter **QER | Attestation | UserApproval | InitialApprovalState** is evaluated for certification status. If the configuration parameter has the value **1**, certification status is set to **New**.

Prerequisite: The import does not alter the Person. Approval State property.



1 NOTE: The configuration parameter QER | Attestation | UserApproval | InitialApprovalStatehas the value 0 by default. This gives each new employee the certification status Certified. Automatic attestation is not carried out.

If you want to attest new employees immediately, change the value of the configuration parameter to $\mathbf{1}$.

- 2. The import sets the property Person. ApprovalState explicitly.
 - The import sets ApprovalState='1' (New).
 Employees are automatically attested by their manager.
 - The import sets ApprovalState='0' (Certified).
 Imported employee master data has already been authorized. It should not be attested again.
 - The import sets ApprovalState='3' (Denied).
 The employee is disabled permanently and is not attested.

Attestation of new users is triggered when:

- the configuration parameter **QER | Attestation | UserApproval** is enabled
- new employee master data was imported into the One Identity Manager database
- the certification status for new employees is set to New
- No **Import data source** is stored with the employee.

If the **External** option is not set for an employee, attestation takes place as described in the Adding new employees using a manager or employee administrator section, step 5.

If the **External** option is set for the employee, attestation takes place as described in the Self-registration of new users in the Web Portal section, steps 4 to 5.

The **New user certification** attestation policy is run.

Related topics

Configuring user attestation and recertification on page 124

Scheduled attestations

Users are also attested when the certification status for an employee is set to **New** at a later date (manually or through import). The schedule **Daily** is assigned to the **New user certification** attestation policy for this purpose. Attestation of new users is started when the time set in the schedule is reached. This process determines all employees with the certification status **New** and for whom no attestation cases are pending.

You can assign a custom schedule to the attestation policy if required.



Detailed information about this topic

• Schedules on page 17

Limiting attestation objects for certification

IMPORTANT: In order to customize the default **New user certification** attestation policy, you must make changes to One Identity Manager objects. Always use a custom copy of the respective object to make changes.

It may be necessary to limit attestation of new users to a certain group of employees, for example, if only employees in a specific departments should be attested. To do this, you can extend the condition attached to the attestation policy. Create a custom attestation policy for this.

The following objects must be changed so that attestation of new users can be carried out with this attestation policy. Always create a copy of the respective object to do this.

- Attestation policy New user certification
- Process VI_Attestation_Person_new_AttestationCase_for_Certification
- Process VI_Attestation_AttestationCase_Person_Approval_Granted
- Process VI_Attestation_AttestationCase_Person_Approval_Dismissed
- IMPORTANT: In order for attestation to run correctly in the Web Portal, the default **Certification of users** attestation procedure and the default **Certification of users** approval policy must be assigned to the attestation policy.

The default attestation procedure, the default approval policy, and the default **Certification of users** approval workflow must not be changed.



To customize default attestation of new users

1. Copy the **Certification of users** attestation policy and customize it.

Table 57: Attestation policy properties

Property	Value
Attestation procedure	Certification of users
Approval policies	Certification of users
Editing conditions	Copy the default condition without modification so that the correct attestation object is selected.
	To limit the number of attestation objects, you can add additional partial conditions to the database query.

2. In Designer, create a copy of the VI_Attestation_Person_new_AttestationCase_for_ Certification process from the Person base object and customize the copy.

Table 58: Process properties with changes

Р	rocess step	Parameter	Change
at	reate ttestation nstance	WhereClause	Replace the UID of the New user certification attestation policy with the UID of the new attestation policy.

3. In the Designer, copy the process VI_Attestation_AttestationCase_Person_Approval_ Granted process of the AttestationCase base object and customize the copy.

Table 59: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the New user certification attestation policy
Generating condition	with the UID of the new attestation policy.

4. In Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Dismissed process of the AttestationCase base object and customize the copy.



Table 60: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the New user certification attestation policy
Generating condition	with the UID of the new attestation policy.

For detailed information about editing processes, see the *One Identity Manager Configuration Guide*.

Detailed information about this topic

- General master data for attestation policies on page 26
- Creating a copy on page 33

Recertifying existing users

IMPORTANT: Access to connected target systems may possibly be denied to One Identity Manager users as a result of recertification. You can configure this behavior to meet your company's requirements. Read the following section thoroughly before you use the recertification function.

One Identity Manager provides an attestation policy for performing cyclical attestation of existing users allowing companies to regularly test and authorize employee master data stored in the One Identity Manager database. Cyclical attestation is triggered through a scheduled task. This resets the certification status for all employees stored in the database. One Identity Manager uses the same procedure for this as for attesting new users. The case is referred to as recertification.

Result of recertification

- Certified, enabled employees that can access all entitlements assigned to them in One Identity Manager and the connected target systems.
 - Company resources are inherited. Account definitions are assigned to internal employees.
 - OR -
- Denied and permanently deactivated employees.
 - Disable employees cannot log onto One Identity Manager tools. Company resources are not inherited. Account definitions are not automatically assigned. User accounts associated with the employee are also locked or deleted. You can customize the behavior to meet your requirements.



Preparing for recertification

To set up regular user attestation

- 1. In the Designer, set the required configuration parameters.
- 2. Create a schedule and assign it to the **User recertification** attestation policy. By doing this, you replace the schedule assigned by default.
 - Enable the schedule.

Detailed information about this topic

Configuring user attestation and recertification on page 124

Related topics

- General master data for attestation policies on page 26
- Schedules on page 17

The recertification sequence

One Identity Manager uses the same method for recertification as for certification of new users. User recertification is triggered when:

- the configuration parameter **QER | Attestation | UserApproval** is enabled
- no Import data source is stored with the employee or the Import data source is not E-Business Suite and
- the execution time in the schedule stored for the **User recertification** attestation policy has been reached.

Internal employees are attested by their manager. If an employee is not assigned a manager, the employee administrator assigns an initial manager for them. Only employee administrators can ultimately deny recertification. If a manager denies recertification, the case is returned to the employee administrators for approval in any case.

External employees are attested by members of the **Identity & Access Governance | Attestation | Attestors for external users** application role.

If the **External** option is not set for an employee, attestation takes place as described in the Adding new employees using a manager or employee administrator section, step 5.

If the **External** option is set for the employee, attestation takes place as described in the Self-registration of new users in the Web Portal section, steps 4 to 5.

The attestors are determined using the **Certification of users** approval policy.



Limiting attestation objects for recertification

IMPORTANT: In order to customize the default attestation policy **User recertification**, you must make changes to One Identity Manager objects. Always use a custom copy of the relevant object to make these changes.

All employees saved in the database are recertified using the **User recertification** attestation policy supplied in the One Identity Manager. It may be necessary to limit recertification of new users to a certain group of employees, for example, if only employees in a specific departments should be attested. To do this, you can extend the condition attached to the attestation policy. Create a custom attestation policy for this.

The following objects must be changed so that recertification of users can be carried out with this attestation policy. Always create a copy of the respective object to do this.

- User recertification attestation policy
- Process VI Attestation AttestationCase Person Approval Granted
- Process VI Attestation AttestationCase Person Approval Dismissed
- IMPORTANT: In order for recertification to run correctly in the Web Portal, the default **Certification of users** attestation procedure and the default **Certification of users** approval policy must be assigned to the attestation policy.

The default attestation procedure, the default approval policy, and the default **Certification of users** approval workflow must not be changed.

To customize default recertification of users

1. Copy the **User recertification** attestation policy and customize it.

Table 61: Attestation policy properties

Property	Value
Attestation procedure	Certification of users
Approval policies	Certification of users
Editing conditions	Copy the default condition without modification so that the correct attestation object is selected.
	To limit the number of attestation objects, you can add additional partial conditions to the database query.

2. In the Designer, copy the process VI_Attestation_AttestationCase_Person_Approval_ Granted process of the AttestationCase base object and customize the copy.



Table 62: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the User recertification attestation policy
Generating condition	with the UID of the new attestation policy.

3. In Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Dismissed process of the AttestationCase base object and customize the copy.

Table 63: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the User recertification attestation policy
Generating condition	with the UID of the new attestation policy.

For detailed information about editing processes, see the *One Identity Manager Configuration Guide*.

Detailed information about this topic

- General master data for attestation policies on page 26
- Creating a copy on page 33



Mitigating controls

Violation of regulatory requirements can harbor different risks for companies. To evaluate these risks, you can apply risk indexes to attestation policies. These risk indexes provide information about the risk involved for the company if this particular policy is violated. Once the risks have been identified and evaluated, mitigating controls can be implemented.

Mitigating controls are independent on One Identity Manager's functionality. They are not monitored through One Identity Manager.

Mitigating controls describe controls that are implemented if an attestation rule was violated. The attestation can be approved after the next attestation run, once controls have been applied.

To edit mitigating controls

• In Designer, set the configuration parameter **QER | CalculateRiskIndex** and compile the database.

For more detailed information about risk assessment, see the *One Identity Manager Risk Assessment Administration Guide*.

General master data for mitigating controls

To edit mitigating controls

- 1. In Manager, select Risk index functions | Mitigating controls.
- 2. Select a mitigating control in the result list and run **Change master data**.
 - OR -
 - Click in the result list.
- 3. Edit the mitigating control master data.
- 4. Save the changes.

Enter the following master data for mitigating controls.



Table 64: General master data for a mitigating control

Property	Description
Measure	Unique identifier for the mitigating control.
Significance reduction	When the mitigating control is implemented, this value is used to reduce the risk of denied attestation cases. Enter a number between 0 and 1.
Description	Detailed description of the mitigating control.
Functional area	Functional area in which the mitigating control may be applied.
D	B. J. J. Lilliam W. J.

Department Department in which the mitigating control may be applied.

Additional tasks for mitigating controls

After you have entered the master data, you can run the following tasks.

Mitigating controls overview

You can see the most important information about a mitigating control on the overview form.

To obtain an overview of a mitigating control

- 1. In Manager, select Risk index functions | Mitigating controls.
- 2. Select the mitigating control in the result list.
- 3. Select Mitigating control overview.

Assigning attestation policies

Use this task to specify for which attestation policies the mitigating control is valid.

To assign attestation policies to mitigating controls

- 1. In Manager, select **Risk index functions | Mitigating control**.
- 2. Select the mitigating control in the result list.
- 3. Select **Assign attestation polices** in the task view.



Assign the attestation policies in **Add assignments**.

TIP: In **Remove assignments**, you can remove the assignment of attestation policies.

To remove an assignment

- Select the approval policy and double-click

 ✓.
- 4. Save the changes.

Calculating mitigation

The significance reduction of a mitigating control supplies the value by which the risk index of an attestation policy is reduced when the control is implemented. One Identity Manager calculates a reduced risk index based on the risk index and the significance reduction. One Identity Manager supplies default functions for calculating reduced risk indexes. These functions cannot be edited with One Identity Manager tools.

The reduced risk index is calculated from the company policy and the significance reduced sum of all assigned mitigating controls.

Risk index (reduced) = Risk index - sum significance reductions

If the significance reduction sum is greater than the risk index, the reduced risk index is set to **0**.



Appendix: Configuration parameters for attestation

The following configuration parameters are additionally available in One Identity Manager after the module has been installed. Some general configuration parameters are relevant for attestation. The following table contains a summary of all applicable configuration parameters for attestation.

Table 65: Overview of configuration parameters

Configuration parameter	Description
QER Attestation	Preprocessor relevant configuration parameter for controlling the model parts for attestation. Changes to the parameter require recompiling the database.
	If the parameter is enabled you can use the attestation function.
QER Attestation AllowAllReportTypes	This configuration parameter specifies whether all report formats are permitted for attestation policies. By default, only PDF is allowed because it is the only audit secure format.
QER Attestation ApproveNewEx- ternalUsers	This configuration parameter specifies whether new external users must be attested before the are enabled.
QER Attestation AutoCloseInactivePerson	If this configuration parameter is set, pending attestation cases for an employee are closed, when this employees is permanently deactivated.
QER Attestation AutoRemovalScope	General configuration parameter for defining automatic withdrawal of member-ships/assignments if attestation approval is not granted.
QER Attestation	Determines default behavior for automatic



Configuration parameter	Description
AutoRemovalScope AERoleMembership	removal of application role memberships if attestation approval is not granted.
QER Attestation AutoRemovalScope AERoleMembership RemoveDelegatedRole	If this configuration parameter is set, it ends the application role delegation if attestation approval is not granted.
QER Attestation AutoRemovalScope AERoleMembership RemoveDirectRole	If this configuration parameter is set, the employee's membership of the application role is removed when attestation approval is not granted.
QER Attestation AutoRemovalScope AERoleMembership RemoveRequestedRole	If this configuration parameter is set, the request for membership of the application role is aborted if attestation approval is not granted.
QER Attestation AutoRe- movalScope DepartmentHasESet	Determines default behavior for automatic removal of system role assignments to departments if attestation approval has been denied.
QER Attestation AutoRe- movalScope DepartmentHasESet RemoveDirect	If this configuration parameter is set, system role to department assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope Depart- mentHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to departments if attestation approval has been denied.
QER Attestation AutoRe- movalScope Depart- mentHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to department assignments are removed if attestation approval is not granted.
QER Attestation AutoRemovalScope ESetAssignment	Determines default behavior for automatic removal of system role memberships if attestation approval is not granted.
QER Attestation AutoRemovalScope ESetAssignment RemoveDelegatedRole	If this configuration parameter is set, it ends the role delegation through which the employee obtained the system role if attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope ESetAssignment RemoveDirect	If this configuration parameter is set, the direct user account membership in the system role will be removed if attestation approval is not



Configuration parameter	Description
	granted.
	This removes all indirect assignments obtained by the employee through the system role.
QER Attestation AutoRemovalScope ESetAssignment RemoveDirectRole	If this configuration parameter is set, the system role assignment to roles (organizations and business roles) is removed if attestation approval is not granted. This removes the system entitlement assignment to all user accounts whose associated employees are members of these roles.
	1 IMPORTANT: Employees whose attestation has been approved can lose the system role through this.
QER Attestation AutoRemovalScope ESetAssignment RemovePrimaryRole	If this configuration parameter is set, the primary role assignment through which the employee obtained the system role is removed from the employee when attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope ESetAssignment RemoveRequested	If this configuration parameter is set, the requested system role is canceled if attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through the system role.
QER Attestation AutoRemovalScope ESetAssignment RemoveRequestedRole	If this configuration parameter is set, the request for the role through which the employee obtained the system role is canceled if attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRe- movalScope ESetHasEntitlement	Determines default behavior for automatic removal of system role assignments after attestation approval has been denied.
QER Attestation AutoRe- movalScope ESetHasEntitlement RemoveDirect	If this configuration parameter is set, company resource assignments to system roles are removed when attestation approval is denied.
QER Attestation AutoRemovalScope	Determines default behavior for automatic removing of united namespace system entitle-



Configuration parameter	Description
GroupMembership	ments if attestation approval is not granted.
QER Attestation AutoRemovalScope GroupMembership RemoveDelegatedRole	If this configuration parameter is set, it ends the role delegation through which the employee obtained the system entitlement if attestation approval is not granted. This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope GroupMembership RemoveDirect	If this configuration parameter is set, the direct user account membership in the system entitlement will be removed if attestation approval is not granted.
QER Attestation AutoRemovalScope GroupMembership RemoveDirectRole	If this configuration parameter is set, the system entitlement assignment to roles (organizations and business roles) is removed if attestation approval is not granted. This removes the system entitlement assignment to all user accounts whose associated employees are members of these roles. IMPORTANT: Employees whose attestation has been approved can lose the system entitlement through this.
QER Attestation AutoRemovalScope GroupMembership RemovePrimaryRole	If this configuration parameter is set, the primary role assignment through which the employee obtained the system entitlement is removed from the employee when attestation approval is not granted. This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope GroupMembership RemoveRequested	If this configuration parameter is set, the requested system entitlement is canceled if attestation approval is not granted.
QER Attestation AutoRemovalScope GroupMembership RemoveRequestedRole	If this configuration parameter is set, the request for the role through which the employee obtained the system entitlement is canceled when attest- ation approval is not granted.
	This removes all indirect assignments obtained by the employee through this role.
QER Attestation	If this configuration parameter is set, the system



Configuration parameter	Description
AutoRemovalScope GroupMembership RemoveSystemRole	role assignment through which the employee obtained the system entitlement is removed from the employee when attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through this system role.
	NOTE: This configuration parameter is only available if the System Roles Module is installed.
QER Attestation AutoRe- movalScope LocalityHasESet	Determines default behavior for automatic removal of system role assignments to locations if attestation approval has been denied.
QER Attestation AutoRe- movalScope LocalityHasESet RemoveDirect	If this configuration parameter is set, system role to location assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope LocalityHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to locations if attestation approval has been denied.
QER Attestation AutoRe- movalScope LocalityHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to location assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope OrgHasESet	Determines default behavior for automatic removal of system role assignments to business roles if attestation approval has been denied.
QER Attestation AutoRe- movalScope OrgHasESet RemoveDirect	If this configuration parameter is set, system role to business role assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope OrgHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to business roles if attestation approval has been denied.
QER Attestation AutoRe- movalScope OrgHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to business role assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope ProfitCenterHasESet	Determines default behavior for automatic removal of system role assignments to system roles if attestation approval has been denied.
QER Attestation AutoRe-	If this configuration parameter is set, system



Configuration parameter	Description
movalScope ProfitCenterHasESet RemoveDirect	role to cost center assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope ProfitCen- terHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to system roles if attestation approval has been denied.
QER Attestation AutoRe- movalScope ProfitCen- terHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to cost center assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope PWOMethodName	Method to be executed on requests if the requested assignment is to be deleted when attestation approval is not granted.
	The requests can be unsubscribed (Unsubscribe) or aborted (Abort). If the configuration parameter is not set, the requests are aborted by default.
QER Attestation AutoRemovalScope RoleMembership	Determines default behavior for automatic removal of business role memberships if attestation approval is not granted.
QER Attestation AutoRemovalScope RoleMembership	If this configuration parameter is set, it ends the business role delegation if attestation approval is not granted.
RemoveDelegatedRole	This removes all indirect assignments the employee obtained through this business role.
QER Attestation AutoRemovalScope RoleMembership RemoveDirectRole	If this configuration parameter is set, the employee secondary membership in the business role will be removed if attestation approval is not granted.
	This removes all indirect assignments the employee obtained through this business role.
QER Attestation AutoRemovalScope RoleMembership	If this configuration parameter is set, the request for membership of the business role is canceled if attestation approval is not granted.
RemoveRequestedRole	This removes all indirect assignments the employee obtained through this business role.
QER Attestation AutoRemovalScope UNSGroupInUNSGroup	Specifies the default behavior for removing assignments from system entitlements to system entitlement is attestation approval is not granted.



Configuration parameter	Description
QER Attestation AutoRemovalScope UNSGroupInUNSGroup RemoveDirect	If this configuration parameter is set, the system entitlement assignment to a system entitlement is removed when attestation approval is not granted.
QER Attestation DefaultSenderAddress	This configuration parameter contains the sender email address for messages automatically generated for attestation.
QER Attestation MailApproval Account	Name of the user account for authenticating the mailbox used for attestation by mail.
QER Attestation MailApproval DeleteMode	Specifies the way emails are deleted from the inbox.
QER Attestation MailApproval Domain	Domain of the user account for authenticating the mailbox used for attestation by mail.
QER Attestation MailApproval ExchangeURI	Specifies the Microsoft Exchange Web Service URL. AutoDiscover mode is used to find the URL if it is not given.
QER Attestation MailApproval Inbox	Microsoft Exchange mailbox. Approval mails for attestation by mail are sent to this mailbox.
QER Attestation MailApproval Password	User account password for authenticating the mailbox used for attestation by mail.
QER Attestation MailTemplateIdents AnswerToApprover	This mail template is used to send a notification with an answer to a question from an approver.
QER Attestation MailTemplateIdents AttestationApproval	Mail template used for attestation by mail.
QER Attestation MailTemplateIdents InformAddingPerson	This mail template is used to notify approvers that an approval decision has been made for the step they added.
QER Attestation MailTemplateIdents InformDelegatingPerson	This mail template is used to notify approvers that an approval decision has been made for the step they delegated.
QER Attestation MailTemplateIdents NewEx- ternalUserVerification	Mail template for sending a message with a verification link to a new external user.
QER Attestation MailTemplateIdents QueryFromApprover	This mail template is used to send a notification with a question from an approver to an employee.



Configuration parameter	Description
QER Attestation MailTemplateIdents RequestApproverByCollection	This mail template is used for generating an email when there are pending attestation for an approver. If this configuration parameter is not set, a Mail template request or Mail template reminder can be entered for single approval steps. This template is then sent for each individual attestation case. If this configuration parameter is set, single mails are not sent.
QER Attestation NewEx- ternalUserFinalTimeoutInHours	Number of hours given for new external users to register (default: 24 hrs).
QER Attestation NewEx- ternalUserTimeoutInHours	Number of hours that the access code and verification link for new external users are valid (default: 4 hrs).
QER Attestation OnWorkflowAssign	This configuration parameter specifies how pending attestation cases are handled when a new approval workflow is assigned to the approval policy.
QER Attestation OnWorkflowUpdate	This configuration parameter specifies how pending attestations are handled when the approval workflow is changed.
QER Attestation PersonToAttestNoDecide	This configuration parameter specifies whether employees to be attested are allowed to approve this attestation case. If the parameter is set, an attestation case cannot be approved by employees, which are contained in the attestation object (AttestationCase.ObjectKeyBase) or in the objects identifiers 1-3 (AttestationCase.UID_ObjectKey1, ObjectKey2 or ObjectKey3). If the parameter is not set, these employee are allowed to make approval decisions for this attestation case.
QER Attestation ReducedApproverCalculation	This configuration parameter specifies, which approval steps are recalculated if modifications require attestors to be redetermined.
QER Attestation UserApproval	Supports attestation procedures for regularly checking and confirming One Identity Manager users through their Manager.
QER Attestation UserApproval InitialApprovalState	Certification status for new employees. If an employee is added with the certification status 1 = new, data attestation by the employee's



Configuration parameter	Description
	manager is started.
QER CalculateRiskIndex	Preprocessor relevant configuration parameter controlling system components for calculating an employee's risk index. Changes to the parameter require recompiling the database. If the parameter is enabled, values for the risk
	index can be entered and calculated.
QER Employee Defender	This configuration parameter specifies whether Starling Two-Factor Authentication is supported.
QER Employee Defender ApiEndpoint	This configuration parameter contains the URL of the Starling 2FA API end point used to register new users.
QER Employee Defender ApiKey	This configuration parameter contains your company's subscription key for accessing the Starling Two-Factor Authentication interface.
QER Person Defender DisableForceParameter	This configuration parameter specifies whether Starling 2FA is forced to send the OTP by SMS or phone call if one of these options is selected for multi-factor authentication. If the configuration parameter is set, Starling 2FA can disallow the request and the user must request the OPT through Starling 2FA.
QER WebPortal BaseURL	Web Portal URL This address is used in mail templates to add hyperlinks to the Web Portal.
QER WebPortal PasswordResetURL	URL for the Password Reset Portal. This address is used to navigate.
Common MailNotification DefaultCulture	This configuration parameter contains the default language for email notifications if no language can be determined for the recipient.
Common MailNotification Signature	Data for the signature in email automatically generated from mail templates.
Common MailNotification Signature Caption	Signature under the salutation.
Common MailNotification Signature Company	Company name.
Common MailNotification Signature Link	Link to company website.
Common MailNotification	User account name for authentication on an



Configuration parameter	Description
SMTPAccount	SMTP server.
Common MailNotification SMTPDomain	User account domain for authentication on the SMTP server.
Common MailNotification SMTPPassword	User account password for authentication on the SMTP server.
Common MailNotification SMTPPort	Port for SMTP services on the SMTP server (default: 25).
Common MailNotification SMTPRelay	SMTP server for sending notifications.
Common MailNotification SMTPUseDefaultCredentials	If this configuration parameter is set, the One Identity Manager Service credentials are used for authentication on the SMTP server. If this configuration parameter is not set, the login data stored in the configuration parameters Common MailNotification SMTPDomain and Common MailNotification SMTPAccount or Common MailNotification SMTPPassword is used.
Common ProcessState PropertyLog	When this configuration parameter is set, changes to individual values are logged and shown in the process view.



One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales or other inquiries, visit https://www.oneidentity.com/company/contact-us.aspx or call +1-800-306-9329.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at https://support.oneidentity.com/.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to-videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- · Chat with support engineers online
- View services to assist you with your product



Index

A	members of a certain role 68
application role	overview form 77
chief approval team 23, 79	owner of a privileged object 69
approval 55	permitted for tables 77
approval by mail 110	product owners 66
approval level 50	proposed owner 69
connect 55	query 74
approval policies 26, 43	recipient's location attestor 63
default 44	recipient's manager 65
user certification 126, 128	recipient's cost center attestor 63
verify 45	recipient's department attestor 63
approval procedure 58	recipient's primary role attestor 63
add 73	role manager 65
approvals made externally 71	specific role Manager 68
approver for attestation policy 63 attestation compliance rule	target system manager of the permis- sion for attestation 66
attestor 63	target system managers 66
attestation organization attestor 63	waiting for further approval 72
attestor for attestation company policy 63	approval process 43 approval reason 24
calculated approval 70	approval step 50-51
condition 74	edit 51
copy 78	approval workflow 46, 94
custom 73	change 96
delete 78	copy 56
department manager 66	default 57
department manager of account's person 66	delete 56
employee manager 66	edit 49 overview form 56
escalation 84	
manager of account's person 66	user certification 126, 128
manager of system roles to be attested 65	



approver	close attestations 92
notification 107	closed 98
select 58	create 32, 92
attestation 8	delegate approval 83
employee 123	delete 26, 98
new employee 125	escalate 84
new user 125	notification 99
approver 126, 128	overview form 94
customize 132	pending attestation 92
imported employee master	processing time 94
data 130	query 83
prepare 128	record 98
prepare import 130	reject approval 83
sequence 126, 128	reroute approval 83
start schedule 131	timeout 84, 87, 89
remove application role automatically 121	attestation object 26, 32-33
remove business role	also attestor 82
automatically 121	attestation policy
remove entitlement	assign approver 30
automatically 114	assign compliance framework 30
remove system entitlement automat- ically 116	assign mitigating control 31
remove system role	calculation schedule
automatically 118	assign 26
start 32, 92	copy 33
for selected objects 92	create 25
user 123	create in Web Portal 114
user certification	default 29, 114
attestation policy 29	delete 34
attestation procedure 15	disable 26, 34
attestation case 92	edit 25
abort 89	mitigating control 31
additional attestors 83	new user certification 126, 128, 130
approval sequence 94	customize 132
approve automatically 87	obsolete attestation cases 98
attestation history 95	overview form 30



owner 26	overview form 20
processing time 26	recertification 135
report 26	start immediately 21
risk index 26, 28	certification
show condition 33	see attestation 123
attestation procedure	certification status
assign approval policy 16	employee 125
default 15, 114	chief approval team 23, 79
group 10	compliance framework 22
overview form 16	assign attestation policy 23
set up 12	manager 22
attestation type 12	overview form 22
assign attestation procedure 12	
default 11	D
overview form 11	default attestation policy 114
attestors 94	default attestation procedure 114
approval by email 110	default mail template 109
approve own attestation case 82	delegation
notification 101, 103, 107-108	approval notification 105
recalculate 79	deny 55
restrict 82	delly 33
select 58	_
	E
В	email notification
base object 12	set up 99
mail template 35	employee
basic data 10	attestation 123
busic data 10	certification status 126
	initial 128, 130
C	certified 125, 134
calculation schedule 17	no inheritance 125, 134
assign attestation policy 21	not set 125, 134
default schedule 19	set 125, 134
default schedule attestation check 17	escalation 55
new user certification 131	notification 106



F	on delegation 105
fallback approver 86	query 108
	recipient 99
	refuse approval 107
L	reject approval 107
login	reminder 101, 103
verification link 109	sender 99
	verification link 109
M	
mail template	R
base object 35, 37	reason 24
hyperlink 38	recertification 8, 123
mitigating control 138	attestation policy
assign attestation policy 32, 139	customize 136
create 32	calculation schedule 135
log 138	customize 136
overview form 139	employee 134
significance reduction 138	prepare 135
multi-factor authentication 81	sequence 135
	user 134
N	report 12
notification	create 15
abort 106	default 15
additional attestors 108	reroute 55
approval 103	risk assessment
attestors 103	attestation policy 28
default mail template 109	risk index
demand 100, 107	calculate 140
deny 103	reduced
deny approval 107	calculate 140
escalation 106	
external user 109	S
mail template 35, 99	scheduled 92
	security code 81



significance reduction 138 standard reason 24 Starling 2FA 81 Starling Two-Factor Authentication 81

т

timeout 55

U

user certification
approval policies 44
approval workflow 57
calculation schedule 19

W

Workflow Editor open 46

