



One Identity Manager 8.0.5

Administration Guide for Connecting Unix-Based Target Systems

Copyright 2020 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC .

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.
Attn: LEGAL Dept
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our Web site (<http://www.OneIdentity.com>) for regional and international office information.




Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal. All other trademarks are the property of their respective owners.

Legend

-  **WARNING:** A WARNING icon indicates a potential for property damage, personal injury, or death.
-  **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.
-  **IMPORTANT, NOTE, TIP, MOBILE, or VIDEO:** An information icon indicates supporting information.

Contents

| | |
|---|-----------|
| Managing Unix-Based Systems | 7 |
| Architecture Overview | 7 |
| One Identity Manager Users for Managing a Unix-Base Target System | 8 |
| Setting Up Synchronization with a Unix-Based Target System | 11 |
| Users and Permissions for Synchronizing with a Unix-Based Target System | 12 |
| Setting Up the Synchronization Server | 13 |
| Creating a Synchronization Project for initial Synchronization of a Unix Host | 16 |
| Information Required for Setting up a Synchronization Project | 17 |
| Setting Up an Initial Synchronization Project | 19 |
| Show Synchronization Results | 23 |
| Configuring the Log's Retention Time | 24 |
| Customizing Synchronization Configuration | 24 |
| Configuring Unix Host Synchronization | 25 |
| Configuring Synchronization of Several Unix Hosts | 26 |
| Updating Schemas | 26 |
| Post-Processing Outstanding Objects | 27 |
| Configuring Memberships Provisioning | 29 |
| Help for Analyzing Synchronization Issues | 30 |
| Deactivating Synchronization | 31 |
| Base Data for Unix-Based Target Systems | 32 |
| Setting Up Account Definitions | 33 |
| Creating an Account Definition | 34 |
| Master Data for an Account Definition | 34 |
| Setting Up Manage Levels | 36 |
| Creating a Formatting Rule for IT Operating Data | 39 |
| Determining IT Operating Data | 40 |
| Modifying IT Operating Data | 42 |
| Assigning Account Definitions to Employees | 43 |
| Assigning Account Definitions to Departments, Cost Centers and Locations | 44 |
| Assigning Account Definitions to Business Roles | 44 |
| Assigning Account Definitions to all Employees | 45 |

| | |
|---|-----------|
| Assigning Account Definitions Directly to Employees | 46 |
| Assigning Account Definitions to System Roles | 46 |
| Adding Account Definitions in the IT Shop | 47 |
| Assigning Account Definitions to a Target System | 48 |
| Deleting an Account Definition | 49 |
| Password Policies | 51 |
| Predefined Password Policies | 51 |
| Editing Password Policies | 52 |
| General Master Data for a Password Policy | 52 |
| Policy Settings | 53 |
| Character Sets for Passwords | 54 |
| Custom Scripts for Password Requirements | 55 |
| Script for Checking a Password | 55 |
| Script for Generating a Password | 56 |
| Restricted Passwords | 57 |
| Testing a Password | 58 |
| Testing Generating a Password | 58 |
| Assigning a Password Policy | 58 |
| Initial Password for New Unix User Accounts | 60 |
| Email Notifications about Login Data | 61 |
| Target System Managers | 63 |
| Editing a Server | 65 |
| Master Data for a Job Server | 66 |
| Server Functions of a Job Server | 68 |
| Unix Host | 70 |
| General Master Data for Unix Hosts | 70 |
| Specifying Categories for Inheriting Permissions | 72 |
| How to Edit a Synchronization Project | 73 |
| Overview of the Unix Host | 73 |
| Displaying Unix Login Shells | 73 |
| Unix User Accounts | 75 |
| Linking User Accounts to Employees | 75 |
| Supported User Account Types | 76 |
| Properties for Mapping User Accounts | 76 |

| | |
|--|-----------|
| Default User Accounts | 77 |
| Administrative User Accounts | 78 |
| Privileged User Accounts | 79 |
| Entering Master Data for Unix User Accounts | 80 |
| General Master Data of a Unix User Account | 81 |
| User Account Master Data for AIX Systems | 84 |
| User Account Limits | 84 |
| User Account Password Data | 85 |
| Security Relevant User Account Master Data | 87 |
| Master Data of a User Account's Encrypted File System | 88 |
| Additional Tasks for Managing Unix User Accounts | 89 |
| Overview of Unix User Accounts | 89 |
| Changing the Manage Level of a Unix User Account | 90 |
| Assigning Unix Groups Directly to Unix User Accounts | 90 |
| Assigning Extended Properties to a Unix User Account | 91 |
| Automatic Assignment of Employees to Unix User Accounts | 91 |
| Editing Search Criteria for Automatic Employee Assignment | 93 |
| Disabling User Accounts for AIX Systems | 96 |
| Deleting and Restoring Unix User Accounts | 97 |
| Unix Groups | 99 |
| Entering Master Data for Unix Groups | 99 |
| General Master Data for an Unix Group | 99 |
| Assigning Unix Groups to Unix User Accounts | 100 |
| Assigning Unix Groups to Departments, Cost Centers and Locations | 101 |
| Assigning Unix Groups to Business Roles | 102 |
| Assigning Unix User Accounts directly to an Unix Group | 103 |
| Adding Unix Groups to System Roles | 104 |
| Adding Unix Groups to the IT Shop | 104 |
| Removing a Unix Group from an IT Shop Shelf | 105 |
| Removing a Unix Group from all IT Shop Shelves | 106 |
| Additional Tasks for Managing Unix Groups | 106 |
| Overview of Unix Groups | 106 |
| Adding Unix Groups to Unix Groups | 106 |
| Effectiveness of Group Memberships | 107 |
| Unix Group Inheritance Based on Categories | 109 |

| | |
|---|------------|
| Assigning Extended Properties to an Unix Group | 111 |
| Deleting Unix Groups | 111 |
| Reports about Unix Objects | 112 |
| Overview of all Assignments | 113 |
| Appendix: Configuration Parameters for Managing Unix | 115 |
| Appendix: Default Project Template for Unix-Based Target Systems | 118 |
| About us | 119 |
| Contacting us | 119 |
| Technical support resources | 119 |
| Index | 120 |

Managing Unix-Based Systems

One Identity Manager offers simplified user account administration for Unix. One Identity Manager concentrates on setting up and editing user accounts and providing the required permissions. To equip users with the required permissions, groups are mapped in One Identity Manager. This makes it possible to use Identity and Access Governance processes such as attesting, Identity Audit, user account management and system entitlements, IT Shop or report subscriptions for Unix based target systems.

One Identity Manager provides company employees with the necessary user accounts. For this, you can use different mechanisms to connect employees to their user accounts. You can also manage user accounts independently of employees and therefore set up administrator user accounts.

Additional information about the Unix core directory is loaded into the One Identity Manager database by data synchronization. There are only limited possibilities for customizing this information in One Identity Manager due to the complex dependencies and far reaching effects of changes.

One Identity Manager supports most Unix and Linux derivatives. For more information, see the specifications for [One Identity Authentication Services](#).

Architecture Overview

The following servers are used for managing an Unix system in One Identity Manager:


- Unix Host

Unix host, which holds the directory. This host is a selected live host with a good network connection to the synchronization server. The synchronization server connects to this host in order to access Unix objects.

- Synchronization server

The synchronization server for synchronizing the One Identity Manager database with the Unix system. The One Identity Manager Service with the machine role "Unix" is installed on this server. The machine role "Unix" contains the Unix connector and the AIX connector. The Unix connector is used for synchronization and provisioning Unix-based objects. The AIX connector is implemented for synchronizing and provisioning IBM AIX systems objects. The connectors communicate directly with the Unix host.

Figure 1: Architecture for synchronization



One Identity Manager Users for Managing a Unix-Base Target System

The following users are used for setting up and managing Unix-based target systems.

Table 1: Users

| User | Task |
|------------------------------|--|
| Target system administrators | <p>Target system administrators must be assigned to the application role Target system Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Administrate application roles for individual target systems types. • Specify the target system manager. • Set up other application roles for target system managers if required. • Specify which application roles are conflicting for target system managers • Authorize other employee to be target system administrators. |

| User | Task |
|-------------------------------------|--|
| Target system managers | <ul style="list-style-type: none"> • Do not assume any administrative tasks within the target system. <p>Target system managers must be assigned to the application role Target systems Unix or a sub application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Assume administrative tasks for the target system. • Create, change or delete target system objects, like user accounts or groups. • Edit password policies for the target system. • Prepare groups for adding to the IT Shop. • Configure synchronization in the Synchronization Editor and defines the mapping for comparing target systems and One Identity Manager. • Edit the synchronization's target system types and outstanding objects. • Authorize other employees within their area of responsibility as target system managers and create child application roles if required. |
| One Identity Manager administrators | <ul style="list-style-type: none"> • Create customized permissions groups for application roles for role-based login to administration tools in the Designer, as required. • Create system users and permissions groups for non-role based login to administration tools, as required. • Enable or disable additional configuration parameters in the Designer, as required. • Create custom processes in the Designer, as required. • Create and configures schedules, as required. • Create and configure password policies, as required. |
| Administrators for the IT Shop | <p>Administrators must be assigned to the application role Request & Fulfillment IT Shop Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Assign to IT Shop structures. |
| Administrators for organizations | <p>Administrators must be assigned to the application role Identity Management Organizations Administrators.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Assign to departments, cost centers and locations. |

User**Task**

Business roles administrators

Administrators must be assigned to the application role
Identity Management | Business roles | Administrators.

Users with this application role:

- Assign to business roles.

Setting Up Synchronization with a Unix-Based Target System

One Identity Manager supports most Unix and Linux derivatives. For more information, see the specifications for [One Identity Authentication Services](#).

To load Unix-based objects into the One Identity Manager database for the first time

1. Prepare a user account with sufficient permissions for synchronizing in the Unix-based target system.
2. The One Identity Manager components for managing Unix-based target systems are available if the configuration parameter "TargetSystem\Unix" is set.
 - Check whether the configuration parameter is set in the Designer. Otherwise, set the configuration parameter and compile the database.
 - Other configuration parameters are installed when the module is installed. Check the configuration parameters and modify them as necessary to suit your requirements.
3. Install and configure a synchronization server and declare the server as Job server in One Identity Manager.
4. Create a synchronization project with the Synchronization Editor.

Related Topics

- [Users and Permissions for Synchronizing with a Unix-Based Target System](#) on page 12
- [Setting Up the Synchronization Server](#) on page 13
- [Creating a Synchronization Project for initial Synchronization of a Unix Host](#) on page 16
- [Deactivating Synchronization](#) on page 31
- [Customizing Synchronization Configuration](#) on page 24
- [Appendix: Configuration Parameters for Managing Unix](#) on page 115
- [Appendix: Default Project Template for Unix-Based Target Systems](#) on page 118

Users and Permissions for Synchronizing with a Unix-Based Target System

The following users are involved in synchronizing One Identity Manager with a Unix-based target system.

Table 2: Users for Synchronization

| User | Permissions |
|---|---|
| User for accessing the Unix host | <p>You must provide a user account with the following permissions for full synchronization of a Unix-based target system with the supplied One Identity Manager default configuration.</p> <ul style="list-style-type: none">• Permissions for establishing a Secure Shell (SSH) connection to the host.• Administration permission for executing write operation in the Unix objects. |
| One Identity Manager Service user account | <p>The user account for the One Identity Manager Service requires access rights to carry out operations at file level (issuing user rights, adding directories and files to be edited).</p> <ul style="list-style-type: none">• The user account must belong to the group "Domain Users".• The user account must have the extended access right "Log on as a service".• The user account requires access rights to the internal web service. <p>NOTE: If the One Identity Manager Service runs under the network service (NT Authority\NetworkService), you can issue access rights for the internal web service with the following command line call:</p> <pre>netsh http add urlacl url=http://<IP address>:<port number>/ user="NT AUTHORITY\NETWORKSERVICE"</pre> <p>The user account needs full access to the One Identity Manager Service installation directory in order to automatically update the One Identity Manager.</p> <p>In the default installation the One Identity Manager is installed under:</p> <ul style="list-style-type: none">• %ProgramFiles(x86)%\One Identity (on 32-bit operating systems)• %ProgramFiles%\One Identity (on 64-bit operating systems) |

| User | Permissions |
|--|---|
| User for accessing the One Identity Manager database | The default system user "Synchronization" is available to run synchronization over an application server. |

Setting Up the Synchronization Server

To set up synchronization with a Unix-based target system, a server must be available with the following software installed on it:

- Windows operating system
 - Following versions are supported:
 - Windows Server 2008 (non-Itanium based 64-bit) Service Pack 2 or later
 - Windows Server 2008 R2 (non-Itanium based 64-bit) Service Pack 1 or later
 - Windows Server 2012
 - Windows Server 2012 R2
 - Windows Server 2016
- Microsoft .NET Framework Version 4.5.2 or later
 - ① **NOTE:** Microsoft .NET Framework version 4.6.0 is not supported.
 - ① **NOTE:** Take the target system manufacturer's recommendations into account.
- Windows Installer
- One Identity Manager Service, Unix connector
 - Install One Identity Manager components with the installation wizard.
 1. Select the option **Select installation modules with existing database.**
 2. Select the machine role **Server | Job server | Unix.**

All One Identity Manager Service actions are executed against the target system environment on the synchronization server. Data entries required for synchronization and administration with the One Identity Manager database, are processed by the synchronization server. The synchronization server must be declared as a Job server in One Identity Manager.

- ① **NOTE:** If several target system environments of the same type are synchronized under the same synchronization server, it is useful to set up a job server for each target system on performance grounds. This avoids unnecessary swapping of connection to target systems because a job server only has to process tasks of the same type (re-use of existing connections).

Use the Server Installer to install the One Identity Manager Service. This program executes the following steps.

- Setting up a Job server.
- Specifying machine roles and server function for the Job server.
- Remote installation of One Identity Manager Service components corresponding to the machine roles.
- Configures the One Identity Manager Service.
- Starts the One Identity Manager Service.

NOTE: The program executes remote installation of the One Identity Manager Service. Local installation of the service is not possible with this program. Remote installation is only supported within a domain or a trusted domain.

To install and configure the One Identity Manager Service remotely on a server

1. Start the program Server Installer on your administrative workstation.
2. Enter valid data for connecting to One Identity Manager on the **Database connection** page and click **Next**.
3. Specify on which server you want to install the One Identity Manager Service on the **Server properties** page.
 - a. Select a job server in the **Server** menu.
- OR -
Click **Add** to add a new job server.
 - b. Enter the following data for the Job server.

Table 3: Job Servers Properties

| Property | Description |
|------------------|--|
| Server | Name of the Job servers. |
| Queue | Name of queue to handle the process steps. Each One Identity Manager Service within the network must have a unique queue identifier. The process steps are requested by the job queue using exactly this queue name. The queue identifier is entered in the One Identity Manager Service configuration file. |
| Full server name | Full name of the server in DNS syntax. Example: <name of server>.<fully qualified domain name> |

NOTE: Use the **Advanced** option to edit other Job server properties. You can use the Designer to change properties at a later date.

- Specify which job server roles to include in One Identity Manager on the **Machine role** page. Installation packages to be installed on the Job server are found depending on the selected machine role.

Select at least the following roles:

- Unix

- Specify the server's functions in One Identity Manager on the **Server functions** page. One Identity Manager processes are handled depending on the server function.

The server's functions depend on which machine roles you have selected. You can limit the server's functionality further here.

Select at least one of the following server functions:

- Unix connector
- AIX connector

- Check the One Identity Manager Service configuration on the **Service settings** page.

NOTE: The initial service configuration is already predefined. If further changes need to be made to the configuration, you can do this later with the Designer. For more detailed information about configuring the service, see One Identity Manager Configuration Guide.

- To configure remote installations, click **Next**.
 - Confirm the security prompt with **Yes**.
 - Select the directory with the install files on the **Select installation source** page.
 - Select the file with the private key on the page **Select private key file**.
- NOTE:** This page is only displayed when the database is encrypted.
- Enter the service's installation data on the **Service access** page.

Table 4: Installation Data

| Data | Description |
|-----------------|--|
| Computer | <p>Server on which to install and start the service from.</p> <p>To select a server</p> <ul style="list-style-type: none"> • Enter the server name. - OR - • Select a entry from the list. |
| Service account | <p>One Identity Manager Service user account data.</p> <p>To enter a user account for the One Identity Manager Service</p> |

| Data | Description |
|----------------------|---|
| Installation account | <ul style="list-style-type: none"> • Set the option Local system account. This starts the One Identity Manager Service under the account "NT AUTHORITY\SYSTEM". - OR - • Enter user account, password and password confirmation. <p>Data for the administrative user account to install the service. To enter an administrative user account for installation</p> <ul style="list-style-type: none"> • Enable Advanced. • Enable the option Current user. This uses the user account of the current user. - OR - • Enter user account, password and password confirmation. |

12. Click **Next** to start installing the service.

Installation of the service occurs automatically and may take some time.

13. Click **Finish** on the last page of the Server Installer.

NOTE: The is entered with the name "One Identity Manager Service" in the server's service administration.

Creating a Synchronization Project for initial Synchronization of a Unix Host

Use the Synchronization Editor to configure synchronization between the One Identity Manager database and the Unix-based target system. The following describes the steps for initial configuration of a synchronization project.

After the initial configuration, you can customize and configure workflows within the synchronization project. Use the workflow wizard in the Synchronization Editor for this. The Synchronization Editor also provides different configuration options for a synchronization project.

For more detailed information about setting up synchronization, see the One Identity Manager Target System Synchronization Reference Guide.

Detailed information about this topic

- [Information Required for Setting up a Synchronization Project](#) on page 17
- [Setting Up an Initial Synchronization Project](#) on page 19

- [Appendix: Default Project Template for Unix-Based Target Systems](#) on page 118

Information Required for Setting up a Synchronization Project

Have the following information available for setting up a synchronization project.

Table 5: Information Required for Setting up a Synchronization Project

| Data | Explanation |
|---|--|
| Server name or IP address of the host | Full name or IP address of the host for connecting to the synchronization server to provide access to Unix objects. |
| Host communications port | Communications port for establishing a Secure Shell (SSH) connection to the host. The default port is TCP port 22. |
| User account and password for logging onto the host | User account and password for logging onto the host. This user account is used to access the host by SSH. The user account requires permissions for establishing an SSH connection. |
| Method, user name and password for escalating permissions | <p>Executing commands requires an administrative context. Make a user account available with sufficient permissions. This user account is used to perform write operations on the Unix objects.</p> <p>Available methods are:</p> <ul style="list-style-type: none"> • Default The user that logs in on the host already has administrative permissions. • Sudo The user for logging in on the host can execute administrative tasks with another user's permissions, for example "root". This is configured in the sudoer file on the host. • su This method uses the su command for changing the context. Another user with administrative permissions is required. |
| Synchronization server of the Unix-based target system | <p>All One Identity Manager Service actions are executed against the target system environment on the synchronization server. Data entries required for synchronization and administration with the One Identity Manager database, are processed by the synchronization server.</p> <p>The One Identity Manager Service with the Unix connector must be installed on the synchronization server.</p> |

| Data | Explanation |
|------|---|
| | The synchronization server must be declared as a Job server in One Identity Manager. Use the following properties when you set up the Job server. |

Table 6: Additional Properties for the Job Server

| Property | Value |
|-----------------|---------------------------------|
| Server Function | Unix connector AIX connector |
| Machine role | Server/Job server/Unix |

| | |
|---|--|
| One Identity Manager Database Connection Data | <p data-bbox="443 680 608 710">SQL Server:</p> <ul data-bbox="491 734 1193 909" style="list-style-type: none"> <li data-bbox="491 734 743 763">• Database server <li data-bbox="491 786 647 815">• Database <li data-bbox="491 837 906 866">• Database user and password <li data-bbox="491 889 1193 909">• Specifies whether Windows authentication is used. <p data-bbox="523 931 1382 1025">This type of authentication is not recommended. If you decide to use it anyway, ensure that your environment supports Windows authentication.</p> <p data-bbox="443 1048 539 1077">Oracle:</p> <ul data-bbox="491 1102 1382 1453" style="list-style-type: none"> <li data-bbox="491 1102 1326 1211">• Species whether access is direct or through the Oracle client Which connection data is required, depends on how this option is set. <li data-bbox="491 1234 743 1263">• Database server <li data-bbox="491 1285 794 1314">• Oracle instance port <li data-bbox="491 1337 707 1366">• Service name <li data-bbox="491 1388 995 1417">• Oracle database user and password <li data-bbox="491 1440 1169 1460">• Data source (TNS alias name from TNSNames.ora) |
|---|--|

| | |
|--------------------------|--|
| Remote connection server | <p data-bbox="443 1476 1382 1776">To configure synchronization with a target system, One Identity Manager must load the data from the target system. One Identity Manager communicates directly with target system to do this. Sometimes direct access from the workstation on which the Synchronization Editor is installed is not possible, because of the firewall configuration, for example, or because the workstation does not fulfill the necessary hardware and software requirements. If direct access to the workstation is not possible, you can set up a remote connection.</p> |
|--------------------------|--|

| Data | Explanation |
|------|---|
| | <p>The remote connection server and the workstation must be in the same Active Directory domain.</p> <p>Remote connection server configuration:</p> <ul style="list-style-type: none"> • One Identity Manager Service is started • RemoteConnectPlugin is installed • Unix connector or AIX connector is installed <p>The remote connection server must be declared as a Job server in One Identity Manager. The Job server name is required.</p> <p>TIP: The remote connection server requires the same configuration (with respect to the installed software) as the synchronization server. Use the synchronization as remote connection server at the same time, by simply installing the RemoteConnectPlugin as well.</p> <p>For more detailed information about setting up a remote connection, see the One Identity Manager Target System Synchronization Reference Guide.</p> |

Related Topics

- [Users and Permissions for Synchronizing with a Unix-Based Target System](#) on page 12
- [Setting Up the Synchronization Server](#) on page 13

Setting Up an Initial Synchronization Project

TIP: NOTE: The following sequence describes how you configure a synchronization project if the Synchronization Editor is both:

- In default mode
- Started from the launchpad

Additional settings can be made if the project wizard is run in expert mode or is started directly from the Synchronization Editor. Follow the project wizard instructions through these steps.

To set up an initial synchronization project for a Unix-based target system

1. Start the Launchpad and log on to the One Identity Manager database.
 - 1 **NOTE:** If synchronization is executed by an application server, connect the database through the application server.
2. Select the entry **Unix target system type**. Click **Run**.

This starts the Synchronization Editor's project wizard.
3. Specify how the One Identity Manager can access the target system on the **System access** page.
 - If you have access from the workstation from which you started the Synchronization Editor, do not set anything.
 - If you do not have access from the workstation from which you started the Synchronization Editor, you can set up a remote connection.

In this case, set the option **Connect using remote connection server** and select, under **Job server**, the server you want to use for the connection.
4. Enter the connection data for the Unix host on the **General connection settings** page.
 - a. Enter the server name or host's IP address in **Server or IP**.
 - b. Enter the communications port for establishing the SSH connection in **Port**. The default communications port is the TCP port 22.
 - c. Enter the user account and password for SSH login on the host.
 - d. Click **Test** to test the connection. The system tries to connect to the host.
5. Click **Test** in the **Verify connection** pane to test the connection to the host.
6. Select the method to use for obtaining administrative permissions on the page **Change to administrative context**.
 - Select the method "Default" if the user already possesses administrative permissions.
 - Select the method "Sudo" if the current user logged in on the host can run administrative tasks as an administrative user. Enter the alternative user, for example "root", in **User**.
 - Select the method "su", if administrative tasks should be executed using a different user. Enter the login data of the other user in **User** and **Password**. The default user is "root".
7. Verify the One Identity Manager database connection data on the **One Identity Manager connection** page. The data is loaded from the connected database. Reenter the password.
 - 1 **NOTE:** Reenter all the connection data if you are not working with an encrypted One Identity Manager database and no synchronization project has been saved yet in the database. This page is not shown if a synchronization project already exists.


8. The wizard loads the target system schema. This may take a few minutes depending on the type of target system access and the size of the target system.
9. Specify how system access should work on the page **Restrict target system access**. You have the following options:

Table 7: Specifying Target System Access

| Option | Meaning |
|---|---|
| Read-only access to target system. | <p>Specifies whether a synchronization workflow should be set up to initially load the target system into the One Identity Manager database.</p> <p>The synchronization workflow has the following characteristics:</p> <ul style="list-style-type: none"> • Synchronization is in the direction of "One Identity Manager". • Processing methods in the synchronization steps are only defined in synchronization direction "One Identity Manager". |
| Changes are also made to the target system. | <p>Specifies whether a provisioning workflow should be set up in addition to the synchronization workflow to initially load the target system.</p> <p>The provisioning workflow displays the following characteristics:</p> <ul style="list-style-type: none"> • Synchronization in the direction of the "target system" • Processing methods are only defined in the synchronization steps in synchronization direction "target system". • Synchronization steps are only created for such schema classes whose schema types have write access. |

10. Select the synchronization server to execute synchronization on the **Synchronization server** page.

If the synchronization server is not declare as a job server in the One Identity Manager database yet, you can add a new job server.

- Click  to add a new job server.
- Enter a name for the job server and the full server name conforming to DNS syntax.
- Click **OK**.

The synchronization server is declared as job server for the target system in the One Identity Manager database.

NOTE: Ensure that this server is set up as the synchronization server after saving the synchronization project.

11. Click **Finish** to complete the project wizard.

This creates and allocates a default schedule for regular synchronization. Enable the schedule for regular synchronization.

The synchronization project is created, saved and enabled immediately.

- ① **NOTE:** If the synchronization project is not going to be executed immediately, disable the option **Activate and save the new synchronization project automatically**.

In this case, save the synchronization project manually before closing the Synchronization Editor.

- ① **NOTE:** The target system connection data is saved in a variable set, which you can change in the Synchronization Editor under **Configuration | Variables** if necessary.

To configure the content of the synchronization log

1. To configure the synchronization log for target system connection, select the category **Configuration | Target system**.
2. To configure the synchronization log for the database connection, select the category **Configuration | One Identity Manager connection**.
3. Select **General** view and click **Configure....**
4. Select the **Synchronization log** view and set **Create synchronization log**.
5. Enable the data to be logged.

- ① **NOTE:** Certain content create a lot of log data.

The synchronization log should only contain the data necessary for error analysis and other evaluations.

6. Click **OK**.

To synchronize on a regular basis

1. Select the category **Configuration | Start up configurations**.
2. Select a start up configuration in the document view and click **Edit schedule....**
3. Edit the schedule properties.
4. To enable the schedule, click **Activate**.
5. Click **OK**.

To start initial synchronization manually

1. Select the category **Configuration | Start up configurations**.
2. Select a start up configuration in the document view and click **Execute**.
3. Confirm the security prompt with **Yes**.

- NOTE:** Following synchronization, employees are automatically created for user accounts in the default installation. If there are no account definitions for the host at the time of synchronization, user accounts are linked to employees. However, account definitions are not assigned. The user accounts are, therefore, in a "Linked" state.

To select user accounts through account definitions

1. Create an account definition.
2. Assign an account definition to the host.
3. Assign the account definition and manage level to the user accounts in a "linked" state.
 - a. Select the category **Unix | User accounts | Linked but not configured | <host>**.
 - b. Select the task **Assign account definition to linked accounts**.


Related Topics

- [Show Synchronization Results](#) on page 23
- [Customizing Synchronization Configuration](#) on page 24
- [Setting Up Account Definitions](#) on page 33
- [Automatic Assignment of Employees to Unix User Accounts](#) on page 91

Show Synchronization Results

Synchronization results are summarized in the synchronization log. You can specify the extent of the synchronization log for each system connection individually. One Identity Manager provides several reports in which the synchronization results are organized under different criteria.

To display a synchronization log


1. Open the synchronization project in the Synchronization Editor.
2. Select the category **Logs**.
3. Click  in the navigation view toolbar.

Logs for all completed synchronization runs are displayed in the navigation view.
4. Select a log by double-clicking on it.

An analysis of the synchronization is shown as a report. You can save the report.

To display a provisioning log.

1. Open the synchronization project in the Synchronization Editor.
2. Select the category **Logs**.

3. Click  in the navigation view toolbar.
Logs for all completed provisioning processes are displayed in the navigation view.
4. Select a log by double-clicking on it.
An analysis of the provisioning is show as a report. You can save the report.

The log is marked in color in the navigation view. This mark shows you the execution status of the synchronization/provisioning.

Configuring the Log's Retention Time

Synchronization logs are stored for a fixed length of time.

To modify the retention period for synchronization logs

- In the Designer, set the "DPR\Journal\LifeTime" configuration parameter and enter the maximum retention time.

Customizing Synchronization Configuration

You have used the Synchronization Editor to set up a synchronization project for initial synchronization of an Unix host. You can use this synchronization project to load Unix objects into the One Identity Manager database. If you manage user accounts and their authorizations with One Identity Manager, changes are provisioned in the Unix-based target system.

You must customize the synchronization configuration in order to compare the database with the Unix-based target system regularly and to synchronize changes.

- Create a workflow with the direction of synchronization "target system" to use One Identity Manager as the master system for synchronization.
- You can use variables to create generally applicable synchronization configurations which contain the necessary information about the synchronization objects when synchronization starts. Variables can be implemented in base objects, schema classes or processing methods, for example.
- Use variables to set up a synchronization project which can be used for several different hosts. Store a connection parameter as a variable for logging onto the hosts.
- To specify which Unix objects and database object are included in synchronization, edit the scope of the target system connection and the One Identity Manager database connection. To prevent data inconsistencies, define the same scope in both systems. If no scope is defined, all objects will be synchronized.

- Update the schema in the synchronization project, if the One Identity Manager schema or target system schema has changed. Then you can add the changes to the mapping.

IMPORTANT: As long as synchronization is running, you must not start another synchronization for the same target system. This applies especially, if the same synchronization objects would be processed.

- The moment another synchronization is started with the same start up configuration, the running synchronization process is stopped and given the status, "Frozen". An error message is written to the One Identity Manager Service log file.
- If another synchronization is started with another start up configuration, that addresses same target system, it may lead to synchronization error or loss of data. Specify One Identity Manager behavior in this case, in the start up configuration. Group start up configurations with the same start up behavior.

For more detailed information about configuring synchronization, see the One Identity Manager Target System Synchronization Reference Guide.

Detailed information about this topic

- [Configuring Unix Host Synchronization](#) on page 25
- [Configuring Synchronization of Several Unix Hosts](#) on page 26
- [Updating Schemas](#) on page 26

Configuring Unix Host Synchronization

The synchronization project for initial synchronization provides a workflow for initial loading of target system objects (initial synchronization) and one for provisioning object modifications from the One Identity Manager database to the target system (provisioning). You also require a workflow with synchronization in the direction of the "target system" to use One Identity Manager as the master system for synchronization.

To create a synchronization configuration for synchronizing a Unix host

1. Open the synchronization project in the Synchronization Editor.
2. Check whether existing mappings can be used for synchronizing the . Create new maps if required.
3. Create a new workflow with the workflow wizard.
This adds a workflow for synchronizing in the direction of the target system.
4. Create a new start up configuration. Use the new workflow to do this.
5. Save the changes.
6. Run a consistency check.

Detailed information about this topic

- [Configuring Synchronization of Several Unix Hosts](#) on page 26

Configuring Synchronization of Several Unix Hosts

Prerequisites

- The target system schema of both hosts are identical.
- All virtual schema properties used in the mapping must exist in the extended schema of both hosts.

To customize a synchronization project for synchronizing another host

1. Prepare a user account with sufficient permissions for synchronizing in the other host.
2. Open the synchronization project in the Synchronization Editor.
3. Create a new base object for the other hosts. Use the wizards to attach a base object.
 - Select the Unix or AIX connector in the wizard and enter the connection parameters. The connection parameters are saved in a special variable set.
A start up configuration is created, which uses the new variable set.
4. Change other elements of the synchronization configuration as required.
5. Save the changes.
6. Run a consistency check.

Related Topics

- [Configuring Unix Host Synchronization](#) on page 25

Updating Schemas

All the schema data (schema types and schema properties) of the target system schema and the One Identity Manager schema are available when you are editing a synchronization project. Only a part of this data is really needed for configuring synchronization. If a synchronization project is finished, the schema is compressed to remove unnecessary data from the synchronization project. This can speed up loading the synchronization project. Deleted schema data can be added to the synchronization configuration again at a later point.

If the target system schema or the One Identity Manager schema has changed, these changes must also be added to the synchronization configuration. Then the changes can be added to the schema property mapping.

To include schema data that have been deleted through compressing and schema modifications in the synchronization project, update each schema in the synchronization project. This may be necessary if:

- A schema was changed by:
 - Changes to a target system schema
 - Customizations to the One Identity Manager schema
 - A One Identity Manager update migration
- A schema in the synchronization project was shrunk by:
 - Activating the synchronization project
 - Synchronization project initial save
 - Compressing a schema

To update a system connection schema

1. Open the synchronization project in the Synchronization Editor.
2. Select the category **Configuration | Target system**.
- OR -
Select the category **Configuration | One Identity Manager connection**.
3. Select the view **General** and click **Update schema**.
4. Confirm the security prompt with **Yes**.
This reloads the schema data.

To edit a mapping

1. Open the synchronization project in the Synchronization Editor.
2. Select the category **Mappings**.
3. Select a mapping in the navigation view.
Opens the Mapping Editor. For more detailed information about editing mappings, see One Identity Manager Target System Synchronization Reference Guide.

NOTE: The synchronization is deactivated if the schema of an activated synchronization project is updated. Reactivate the synchronization project to synchronize.

Post-Processing Outstanding Objects

Objects, which do not exist in the target system, can be marked as outstanding in One Identity Manager by synchronizing. This prevents objects being deleted because of an

incorrect data situation or an incorrect synchronization configuration.

Objects marked as outstanding:

- Cannot be edited in One Identity Manager.
- Are ignored by subsequent synchronization.
- Must be post-processed separately in One Identity Manager.

Start target system synchronization to do this.

To post-process outstanding objects




1. Select the category **Unix | Target system synchronization: Unix**.
All tables assigned to the target system type Unix as synchronization tables are displayed in the navigation view.
2. Select the table whose outstanding objects you want to edit in the navigation view.
This opens the target system synchronization form. All objects are shown here that are marked as outstanding.

TIP:

To display object properties of an outstanding object

- a. Select the object on the target system synchronization form.
 - b. Open the context menu and click **Show object**.
3. Select the objects you want to rework. Multi-select is possible.
 4. Click one of the following icons in the form toolbar to execute the respective method.

Table 8: Methods for handling outstanding objects

| Icon | Method | Description |
|---|---------|--|
|  | Delete | The object is immediately deleted in the One Identity Manager. Deferred deletion is not taken into account. The "outstanding" label is removed from the object. Indirect memberships cannot be deleted. |
|  | Publish | The object is added in the target system. The "outstanding" label is removed from the object. The method triggers the event "HandleOutstanding". This runs a target system specific process that triggers the provisioning process for the object. Prerequisites: <ul style="list-style-type: none">• The table containing the object can be published.• The target system connector has write access to the target system. |
|  | Reset | The "outstanding" label is removed from the object. |

5. Confirm the security prompt with **Yes**.

NOTE: By default, the selected objects are processed in parallel, which speeds up execution of the selected method. If an error occurs during processing, the action is stopped and all changes are discarded.

Bulk processing of objects must be disabled if errors are to be localized, which means the objects are processed sequentially. Failed objects are named in the error message. All changes that were made up until the error occurred are saved.

To disable bulk processing

- Deactivate  in the form toolbar.

You must customize synchronization to synchronize custom tables.

To add custom tables to the target system synchronization.

1. Select the category **Unix | Basic configuration data | Target system types**.
2. Select the target system type Unix in the result list.
3. Select **Assign synchronization tables** in the task view.
4. Assign custom tables whose outstanding objects you want to handle in **Add assignments**.
5. Save the changes.
6. Select **Configure tables for publishing**.
7. Select custom tables whose outstanding objects can be published in the target system and set the option **Publishable**.
8. Save the changes.

NOTE: The target system connector must have write access to the target system in order to publish outstanding objects that are being post-processed. That means, the option **Connection is read only** must not be set for the target system connection.

Configuring Memberships Provisioning

Memberships, for example, user accounts in groups, are saved in assignment tables in the One Identity Manager database. During provisioning of modified memberships, changes made in the target system will probably be overwritten. This behavior can occur under the following conditions:

- Memberships are saved in the target system as an object property in list form.
- Memberships can be modified in either of the connected systems.
- A provisioning workflow and provisioning processes are set up.

If a membership in One Identity Manager changes, the complete list of members is transferred to the target system by default. Memberships, previously added to the target system are removed by this; previously deleted memberships are added again.

To prevent this, provisioning can be configured such that only the modified membership is provisioned in the target system. The corresponding behavior is configured separately for each assignment table.

To allow separate provisioning of memberships

1. Start the Manager.
2. Select the category **Unix | Basic configuration data | Target system types**.
3. Select **Configure tables for publishing**.
4. Select the assignment tables for which you want to allow separate provisioning. Multi-select is possible.
 - The option can only be set for assignment tables whose base table has a `XDateSubItem` or a `CCC_XDateSubItem`.
 - Assignment tables, which are grouped together in a virtual schema property in the mapping, must be labeled identically.
5. Click **Enable merging**.
6. Save the changes.

For each assignment table labeled like this, the changes made in the One Identity Manager are saved in a separate table. During modification provisioning, the members list in the target system is compared to the entries in this table. This means that only modified memberships are provisioned and the members list does not get entirely overwritten.

NOTE: The complete members list is updated by synchronization. During this process, objects with changes but incomplete provisioning are not handled. These objects are logged in the synchronization log.

For more detailed information about provisioning memberships, see the One Identity Manager Target System Synchronization Reference Guide.

Help for Analyzing Synchronization Issues

You can generate a report for analyzing problems which occur during synchronization, for example, insufficient performance. The report contains information such as:

- Consistency check results
- Revision filter settings
- Scope applied

- Analysis of the synchronization buffer
- Object access times in the One Identity Manager database and in the target system

To generate a synchronization analysis report

1. Open the synchronization project in the Synchronization Editor.
2. Select the menu **Help | Generate synchronization analysis report** and answer the security prompt with **Yes**.

The report may take a few minutes to generate. It is displayed in a separate window.

3. Print the report or save it in one of the available output formats.

Deactivating Synchronization

Regular synchronization cannot be started until the synchronization project and the schedule are active.

To prevent regular synchronization

- Select the start up configuration and deactivate the configured schedule.
Now you can only start synchronization manually.

An activated synchronization project can only be edited to a limited extent. The schema in the synchronization project must be updated if schema modifications are required. The synchronization project is deactivated in this case and can be edited again.

Furthermore, the synchronization project must be deactivated if synchronization should not be started by any means (not even manually).

To deactivate the loaded synchronization project

1. Select **General** on the start page.
2. Click **Deactivate project**.

Detailed information about this topic

- [Creating a Synchronization Project for initial Synchronization of a Unix Host](#) on page 16

Base Data for Unix-Based Target Systems

The following base data is relevant for managing a Unix-based target system in One Identity Manager.

- Configuration parameter

Use configuration parameters to configure the behavior of the system's basic settings. One Identity Manager provides default settings for different configuration parameters. Check the configuration parameters and modify them as necessary to suit your requirements.

Configuration parameters are defined in the One Identity Manager modules. Each One Identity Manager module can also install configuration parameters. You can find an overview of all configuration parameters in the category **Base data | General | Configuration parameters** in the Designer.

For more information, see [Appendix: Configuration Parameters for Managing Unix](#) on page 115.

- Account definitions

One Identity Manager has account definitions for automatically allocating user accounts to employees during working hours. You can create account definitions for every target system. If an employee does not have a user account in the target system, a new user account is created. This is done by assigning account definitions to an employee using the integrated inheritance mechanism followed by process handling.

For more information, see [Setting Up Account Definitions](#) on page 33.

- Password policies

One Identity Manager provides you with support for creating complex password policies, for example, for system user passwords, the employees' central password as well as passwords for individual target systems. Password policies apply not only when the user enters a password but also when random passwords are generated.

Predefined password policies are supplied with the default installation that you can use or customize if required. You can also define your own password policies.

For more information, see [Password Policies](#) on page 51.

- Initial Password for New User Accounts

You have the different options for issuing an initial password for user accounts. The central password of the assigned employee can be aligned with the user account password, a predefined, fixed password can be used or a randomly generated initial password can be issued.

For more information, see [Initial Password for New Unix User Accounts](#) on page 60.

- Email notifications about login data

When a new user account is created, the login data are sent to a specified recipient. In this case, two messages are sent with the user name and the initial password. Mail templates are used to generate the messages.

For more information, see [Email Notifications about Login Data](#) on page 61.

- Target System Types

Target system types are required for configuring target system comparisons. Tables containing outstanding objects are maintained on target system types.

For more information, see [Post-Processing Outstanding Objects](#) on page 27.

- Target System Managers

A default application role exists for the target system manager in the One Identity Manager. Assign this application to employees who are authorized to edit the Unix hosts in One Identity Manager.

Define other application roles, if you want to limit target system managers' access permissions to individual Unix hosts. The application roles must be added under the default application role.

For more information, see [Target System Managers](#) on page 63.

- Servers

Servers must know your server functionality in order to handle Unix specific processes in One Identity Manager. For example, the synchronization server.

For more information, see [Editing a Server](#) on page 65.

Setting Up Account Definitions

One Identity Manager has account definitions for automatically allocating user accounts to employees during working hours. You can create account definitions for every target system. If an employee does not have a user account in the target system, a new user account is created. This is done by assigning account definitions to an employee using the integrated inheritance mechanism followed by process handling.

The data for the user accounts in the respective target system comes from the basic employee data. The assignment of the IT operating data to the employee's user account is controlled through the primary assignment of the employee to a location, a department, a cost center, or a business role (template processing). Processing is done through


templates. There are predefined templates for determining the data required for user accounts included in the default installation. You can customize templates as required. For more details about the basics, see the One Identity Manager Target System Base Module Administration Guide.

The following steps are required to implement an account definition:

- [Creating an Account Definition](#)
- [Setting Up Manage Levels](#)
- [Creating a Formatting Rule for IT Operating Data](#)
- [Determining IT Operating Data](#)
- [Assigning Account Definitions to Employees](#)
- [Assigning Account Definitions to a Target System](#)

Creating an Account Definition

To create a new account definition

1. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
2. Select an account definition in the result list. Select **Change master data** in the task view.
- OR -
Click  in the result list toolbar.
3. Enter the account definition's master data.
4. Save the changes.

Detailed information about this topic

- [Master Data for an Account Definition](#) on page 34

Master Data for an Account Definition

Enter the following data for an account definition:

Table 9: Master Data for an Account Definition

| Property | Description |
|--------------------|--------------------------|
| Account definition | Account definition name. |

| Property | Description |
|-----------------------------------|--|
| User account table | Table in the One Identity Manager schema which maps user accounts. |
| Target System | Target system to which the account definition applies. |
| Required account definition | Required account definitions. Define the dependencies between account definitions. When this account definition is requested or assigned, the required account definition is automatically requested or assigned with it. Leave empty for Unix hosts. |
| Description | Spare text box for additional explanation. |
| Manage level (initial) | Manage level to use by default when you add new user accounts. |
| Risk index | Value for evaluating the risk of account definition assignments to employees. Enter a value between 0 and 1. This property is only visible when the configuration parameter QER\CalculateRiskIndex is set. For more detailed information, see the One Identity Manager Risk Assessment Administration Guide. |
| Service item | Service item through which you can request the account definition in the IT Shop. Assign an existing service item or add a new one. |
| IT Shop | Specifies whether the account definition can be requested through the IT Shop. The account definition can be ordered by an employee over the Web Portal and distributed using a defined approval process. The can still be directly assigned to employees and roles outside the IT Shop. |
| Only for use in IT Shop | Specifies whether the account definition can only be requested through the IT Shop. The account definition can be ordered by an employee over the Web Portal and distributed using a defined approval process. This means, the account definition cannot be directly assigned to roles outside the IT Shop. |
| Automatic assignment to employees | Specifies whether the account definition is assigned automatically to all internal employees. The account definition is assigned to every employee not marked as external, on saving. New employees automatically obtain this account definition as soon as they are added. <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-left: 20px;"> <p>i IMPORTANT: Only set this option if you can ensure that all current internal employees in the database and all pending newly added internal employees obtain a user account in this target system.</p> </div> <p>Disable this option to remove automatic assignment of the account definition to all employees. The account definition cannot be reassigned to</p> |

| Property | Description |
|---|--|
| | employees from this point on. Existing account definition assignments remain intact. |
| Retain account definition if permanently disabled | <p>Specifies the account definition assignment to permanently disabled employees.</p> <p>Option set: the account definition assignment remains in effect. The user account stays the same.</p> <p>Option not set: the account definition assignment is not in effect. The associated user account is deleted.</p> |
| Retain account definition if temporarily disabled | <p>Specifies the account definition assignment to temporarily disabled employees.</p> <p>Option set: the account definition assignment remains in effect. The user account stays the same.</p> <p>Option not set: the account definition assignment is not in effect. The associated user account is deleted.</p> |
| Retain account definition on deferred deletion | <p>Specifies the account definition assignment on deferred deletion of employees.</p> <p>Option set: the account definition assignment remains in effect. The user account stays the same.</p> <p>Option not set: the account definition assignment is not in effect. The associated user account is deleted.</p> |
| Retain account definition on security risk | <p>Specifies the account definition assignment to employees posing a security risk .</p> <p>Option set: the account definition assignment remains in effect. The user account stays the same.</p> <p>Option not set: the account definition assignment is not in effect. The associated user account is deleted.</p> |
| Resource type | Resource type for grouping account definitions. |
| Spare field 01 - spare field 10 | Additional company specific information. Use the Designer to customize display names, formats and templates for the input fields. |

Setting Up Manage Levels

Specify the manage level for an account definition for managing user accounts. The user account's manage level specifies the extent of the employee's properties that are inherited by the user account. This allows an employee to have several user accounts in one target system, for example:

- Default user account that inherits all properties from the employee
- Administrative user account that is associated to an employee but should not inherit the properties from the employee.

The One Identity Manager supplies a default configuration for manage levels:

- Unmanaged

User accounts with a manage level of "Unmanaged" become linked to an employee but do not inherit any other properties. When a new user account is added with this manage level and an employee is assigned, some of the employee's properties are transferred initially. If the employee properties are changed at a later date, the changes are not passed onto the user account.

- Full managed

User accounts with a manage level of "Full managed" inherit specific properties from the assigned employee.

NOTE: The manage levels "Full managed" and "Unmanaged" are evaluated in the templates. You can customize the supplied templates in the Designer.

You can define other manage levels depending on your requirements. You need to amend the templates to include manage level approaches.

Specify the effect of temporarily or permanently disabling, deleting or the security risk of an employee on its user accounts and group memberships for each manage level. For more detailed information about manage levels, see the One Identity Manager Target System Base Module Administration Guide.


- Employee user accounts can be locked when they are disabled, deleted or rated as a security risk so that permissions are immediately withdrawn. If the employee is reinstated at a later date, the user accounts are also reactivated.
- You can also define group membership inheritance. Inheritance can be discontinued if desired when, for example, the employee's user accounts are disabled and therefore cannot be members in groups. During this time, no inheritance processes should be calculated for this employee. Existing group memberships are deleted!

To assign manage levels to an account definition

1. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
2. Select an account definition in the result list.
3. Select **Assign manage level** in the task view.
4. Assign manage levels in **Add assignments**.
- OR -
Remove assignments to manage levels in **Remove assignments**.
5. Save the changes.

IMPORTANT: The manage level "Unmanaged" is assigned automatically when an account definition is assigned and cannot be removed.

To edit a manage level

1. Select the category **Unix | Basic configuration data | Account definitions | Manage levels**.
2. Select the manage level in the result list. Select **Change master data**.
- OR -
Click  in the result list toolbar.
3. Edit the manage level's master data.
4. Save the changes.

Related Topics

- [Master Data for a Manage Level](#) on page 38

Master Data for a Manage Level

Enter the following data for a manage level.

Table 10: Master Data for a Manage Level

| Property | Description |
|--|--|
| Manage level | Name of the manage level. |
| Description | Spare text box for additional explanation. |
| IT operating data overwrites | Specifies whether user account data formatted from IT operating data is automatically updated. Permitted values are: Never Data is not updated always Data is always updated Only initially Data is only initially determined. |
| Retain groups if temporarily disabled | Specifies whether user accounts of temporarily disabled employees retain their group memberships. |
| Lock user accounts if temporarily disabled | Specifies whether user accounts of temporarily disabled employees are locked. |
| Retain groups if permanently disabled | Specifies whether user accounts of permanently disabled employees retain group memberships. |
| Lock user accounts if permanently disabled | Specifies whether user accounts of permanently disabled employees are locked. |
| Retain groups on deferred deletion | Specifies whether user accounts of employees marked for deletion retain their group memberships. |

| Property | Description |
|--|---|
| Lock user accounts if deletion is deferred | Specifies whether user accounts of employees marked for deletion are locked. |
| Retain groups on security risk | Specifies whether user accounts of employees posing a security risk retain their group memberships. |
| Lock user accounts if security is at risk | Specifies whether user accounts of employees posing a security risk are locked. |
| Retain groups if user account disabled | Specifies whether locked user accounts retain their group memberships. |

Creating a Formatting Rule for IT Operating Data

An account definition specifies which rules are used to form the IT operating data and which default values will be used if no IT operating data can be found through the employee's primary roles.

The following IT operating data is used in the One Identity Manager default configuration for automatic creating and modifying of user accounts for an employee in the target system.

- Login shell
- Groups can be inherited
- Identity
- Privileged user account

To create a mapping rule for IT operating data

1. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
2. Select an account definition in the result list.
3. Select **Edit IT operating data mapping** in the task view and enter the following data.

Table 11: Mapping rule for IT operating data

| Property | Description |
|----------|--|
| Column | User account property for which the value is set. |
| Source | Specifies which roles to use in order to find the user account properties. You have the following options: |

| Property | Description |
|-----------------------------------|---|
| | <ul style="list-style-type: none">• Primary department• Primary location• Primary cost center• Primary business roles <p>i NOTE: Only use the primary business role if the Business Roles Module is installed.</p> <ul style="list-style-type: none">• Empty <p>If you select a role, you must specify a default value and set the option Always use default value.</p> |
| Default value | Default value of the property for an employee's user account if the value is not determined dynamically from the IT operating data. |
| Always use default value | Specifies whether user account properties are always filled with the default value. IT operating data is not determined dynamically from a role. |
| Notify when applying the standard | Specifies whether email notification to a defined mailbox is sent when the default value is used. Use the mail template "Employee - new user account with default properties created". To change the mail template, modify the configuration parameter "TargetSystem\Unix\Accounts\MailTemplateDefaultValues". |

4. Save the changes.

Related Topics

- [Determining IT Operating Data](#) on page 40

Determining IT Operating Data

In order for an employee to create user accounts with the manage level "Full managed", the necessary IT operating data must be determined. The operating data required to automatically supply an employee with IT resources is shown in the departments, locations, cost centers, and business roles. An employee is assigned to one primary location, one primary department, one primary cost center or one primary business role. The necessary IT operating data is ascertained from these assignments and used in creating the user accounts. Default values are used if valid IT operating data cannot be found over the primary roles.

You can also specify IT operating data directly for a specific account definition.

Example:

Normally, each employee in department A obtains a default user account in the host A. In addition, certain employees in department A obtain administrative user accounts in the host A.


Create an account definition A for the default user account of the host A and an account definition B for the administrative user account of host A. Specify the property "Department" in the IT operating data formatting rule for the account definitions A and B in order to determine the valid IT operating data.

Specify the effective IT operating data of department A for the host A. This IT operating data is used for standard user accounts. In addition, specify the effective account definition B IT operating data for department A. This IT operating data is used for administrative user accounts.

To specify IT operating data

1. Select the role in the category **Organizations** or **Business roles**.
2. Select **Edit IT operating data** in the task view and enter the following data.

Table 12: IT Operating Data

| Property | Description |
|----------------------------|---|
| Organization/Business role | Department, cost center, location or business role for which the IT operating data is valid. |
| Effects on | IT operating data application scope. The IT operating data can be used for a target system or a defined account definition. |
| | <p>To specify an application scope</p> <ol style="list-style-type: none"> a. Click  next to the text box. b. Select the table under Table, which maps the target system or the table TSBAccountDef for an account definition. c. Select the concrete target system or concrete account definition under Effects on. d. Click OK. |
| Column | User account property for which the value is set. Columns using the script template TSB_ITDataFromOrg in their template are listed. For more detailed information, see the One Identity Manager Target System Base Module Administration Guide. |
| Value | Concrete value which is assigned to the user account property. |

3. Save the changes.

Related Topics

- [Creating a Formatting Rule for IT Operating Data](#) on page 39

Modifying IT Operating Data

If IT operating data changes, you must transfer these changes to the existing user accounts. To do this, templates must be rerun on the affected columns. Before you can run the templates, you can check what the effect of a change to the IT operating data has on the existing user accounts. You can decide whether the change is transferred to the database in the case of each affected column in each affected database.

Prerequisites

- The IT operating data of a department, cost center, business role or a location was changed.
- OR -
- The default values in the IT operating data template were modified for an account definition.

NOTE: If the assignment of an employee to a primary department, cost center, business role or to a primary location changes, the templates are automatically executed.

To execute the template

1. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
2. Select an account definition in the result list.
3. Select **Execute templates** in the task view

This displays a list of all user account, which are created through the selected account definition and whose properties are changed by modifying the IT operating data.

Old value Current value of the object property.

New value Value applied to the object property after modifying the IT operating data.

Selection Specifies whether the modification is applied to the user account.

4. Mark all the object properties in the **selection** column that will be given the new value.
5. Click **Apply**.

The templates are applied to all selected user accounts and properties.

Assigning Account Definitions to Employees

Account definitions are assigned to company employees. Indirect assignment is the default method for assigning account definitions to employees. Account definitions are assigned to departments, cost centers, locations or roles. The employees are categorized into these departments, cost centers, locations or roles depending on their function in the company and thus obtain their account definitions. To react quickly to special requests, you can assign individual account definitions directly to employees. You can automatically assign special account definitions to all company employees. It is possible to assign account definitions to the IT Shop as requestable products. A department manager can then request user accounts from the Web Portal for his staff. It is also possible to add account definitions to system roles. These system roles can be assigned to employees through hierarchical roles or directly or added as products in the IT Shop.

In the One Identity Manager default installation, the processes are checked at the start to see if the employee already has a user account in the target system that has an account definition. If no user account exists, a new user account is created with the account definition's default manage level.

i **NOTE:** If a user account already exists and is disabled, then it is re-enabled. You have to alter the user account manage level afterwards in this case.

Prerequisites for indirect assignment of account definitions to employees

- Assignment of employees and account definitions is permitted for role classes (department, cost center, location or business role).

For detailed information about preparing role classes to be assigned, see the One Identity Manager Identity Management Base Module Administration Guide.

Detailed information about this topic

- [Assigning Account Definitions to Departments, Cost Centers and Locations](#) on page 44
- [Assigning Account Definitions to Business Roles](#) on page 44
- [Assigning Account Definitions to all Employees](#) on page 45
- [Assigning Account Definitions Directly to Employees](#) on page 46
- [Assigning Account Definitions to System Roles](#) on page 46
- [Adding Account Definitions in the IT Shop](#) on page 47

Assigning Account Definitions to Departments, Cost Centers and Locations

To add account definitions to hierarchical roles

1. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
2. Select an account definition in the result list.
3. Select **Assign organizations**.
4. Assign organizations in **Add assignments**.
 - Assign departments on the **Departments** tab.
 - Assign locations on the **Locations** tab.
 - Assign cost centers on the **Cost center** tab.

- OR -

Remove the organizations from **Remove assignments**.
5. Save the changes.

Related Topics

- [Assigning Account Definitions to Business Roles](#) on page 44
- [Assigning Account Definitions to all Employees](#) on page 45
- [Assigning Account Definitions Directly to Employees](#) on page 46
- [Assigning Account Definitions to System Roles](#) on page 46
- [Adding Account Definitions in the IT Shop](#) on page 47

Assigning Account Definitions to Business Roles

Installed Modules: Business Roles Module

To add account definitions to hierarchical roles

1. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
2. Select an account definition in the result list.
3. Select **Assign business roles** in the task view.
4. Assign business roles in **Add assignments**.
 - OR -
 - Remove business roles in **Remove assignments**.
5. Save the changes.

Related Topics

- [Assigning Account Definitions to Departments, Cost Centers and Locations](#) on page 44
- [Assigning Account Definitions to all Employees](#) on page 45
- [Assigning Account Definitions Directly to Employees](#) on page 46
- [Assigning Account Definitions to System Roles](#) on page 46
- [Adding Account Definitions in the IT Shop](#) on page 47

Assigning Account Definitions to all Employees

To assign an account definition to all employees

1. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
2. Select an account definition in the result list.
3. Select **Change master data** in the task view.
4. Set the option **Automatic assignment to employees** on the **General** tab.

! **IMPORTANT:** Only set this option if you can ensure that all current internal employees in the database and all pending newly added internal employees obtain a user account in this target system.

5. Save the changes.

The account definition is assigned to every employee that is not marked as external. New employees automatically obtain this account definition as soon as they are added. The assignment is calculated by the DBQueue Processor.

! **NOTE:** Disable the option **Automatic assignment to employees** to remove automatic assignment of the account definition to all employees. The account definition cannot be reassigned to employees from this point on. Existing assignments remain intact.

Related Topics

- [Assigning Account Definitions to Departments, Cost Centers and Locations](#) on page 44
- [Assigning Account Definitions to Business Roles](#) on page 44
- [Assigning Account Definitions Directly to Employees](#) on page 46
- [Assigning Account Definitions to System Roles](#) on page 46
- [Adding Account Definitions in the IT Shop](#) on page 47

Assigning Account Definitions Directly to Employees

To assign an account definition directly to employees

1. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
2. Select an account definition in the result list.
3. Select **Assign to employees** in the task view.
4. Assign employees in **Add assignments**.
- OR -
Remove employees from **Remove assignments**.
5. Save the changes.

Related Topics

- [Assigning Account Definitions to Departments, Cost Centers and Locations](#) on page 44
- [Assigning Account Definitions to Business Roles](#) on page 44
- [Assigning Account Definitions to all Employees](#) on page 45
- [Assigning Account Definitions to System Roles](#) on page 46
- [Adding Account Definitions in the IT Shop](#) on page 47

Assigning Account Definitions to System Roles

Installed Modules: System Roles Module

NOTE: Account definitions with the option **Only use in IT Shop** can only be assigned to system roles that also have this option set.

To add account definitions to a system role

1. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
2. Select an account definition in the result list.
3. Select **Assign system roles in the task view**.
4. Assign system roles in **Add assignments**.
- OR -
Remove assignments to system roles in **Remove assignments**.
5. Save the changes.

Related Topics

- [Assigning Account Definitions to Departments, Cost Centers and Locations](#) on page 44
- [Assigning Account Definitions to Business Roles](#) on page 44
- [Assigning Account Definitions to all Employees](#) on page 45
- [Assigning Account Definitions Directly to Employees](#) on page 46
- [Adding Account Definitions in the IT Shop](#) on page 47

Adding Account Definitions in the IT Shop

A account definition can be requested by shop customers when it is assigned to an IT Shop shelf. To ensure it can be requested, further prerequisites need to be guaranteed.

- The account definition must be labeled with the **IT Shop** option.
- The account definition must be assigned to a service item.
- If the account definition is only assigned to employees using IT Shop assignments, you must also set the option **Only for use in IT Shop**. Direct assignment to hierarchical roles may not be possible.

NOTE: IT Shop administrators can assign account definitions to IT Shop shelves if login is role-based. Target system administrators are not authorized to add account definitions in the IT Shop.

To add an account definition to the IT Shop

1. Select the category **Unix | Basic configuration data | Account definitions** (non role-based login).
- OR -
Select the category **Entitlements | Account definitions** (role-based login).
2. Select an account definition in the result list.
3. Select **Add to IT Shop** in the task view.
4. Assign the account definition to the IT Shop shelf in **Add assignments**
5. Save the changes.

To remove an account definition from individual IT Shop shelves

1. Select the category **Unix | Basic configuration data | Account definitions** (non role-based login).
- OR -
Select the category **Entitlements | Account definitions** (role-based login).
2. Select an account definition in the result list.
3. Select **Add to IT Shop** in the task view.

4. Remove the account definition from the IT Shop shelves in **Remove assignments**.
5. Save the changes.

To remove an account definition from all IT Shop shelves

1. Select the category **Unix | Basic configuration data | Account definitions** (non role-based login).
- OR -
Select the category **Entitlements | Account definitions** (role-based login).
2. Select an account definition in the result list.
3. Select **Remove from all shelves (IT Shop)** in the task view.
4. Confirm the security prompt with **Yes**.
5. Click **OK**.

The account definition is removed from all shelves by the One Identity Manager Service. All requests and assignment requests with this account definition are canceled in the process.

For more detailed information about request from company resources through the IT Shop, see the One Identity Manager IT Shop Administration Guide.

Related Topics

- [Master Data for an Account Definition](#) on page 34
- [Assigning Account Definitions to Departments, Cost Centers and Locations](#) on page 44
- [Assigning Account Definitions to Business Roles](#) on page 44
- [Assigning Account Definitions to all Employees](#) on page 45
- [Assigning Account Definitions Directly to Employees](#) on page 46
- [Assigning Account Definitions to System Roles](#) on page 46

Assigning Account Definitions to a Target System

The following prerequisites must be fulfilled if you implement automatic assignment of user accounts and employees resulting in administered user accounts (state "Linked configured"):

- The account definition is assigned to the target system.
- The account definition has the default manage level.

User accounts are only linked to the employee (state "Linked") if no account definition is given. This is the case on initial synchronization, for example.

To assign the account definition to a target system

1. Select the host in the category **Unix | Hosts**.
2. Select **Change master data** in the task view.
3. Select the account definition for user accounts from **Account definition (initial)**.
4. Save the changes.

Detailed information about this topic

- [Automatic Assignment of Employees to Unix User Accounts](#) on page 91


Deleting an Account Definition

You can delete account definitions if they are not assigned to target systems, employees, hierarchical roles or any other account definitions.

NOTE: If an account definition is deleted, the user accounts arising from this account definition are deleted.

To delete an account definition

1. Remove automatic assignments of the account definition from all employees.
 - a. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
 - b. Select an account definition in the result list.
 - c. Select **Change master data** in the task view.
 - d. Disable the option **Automatic assignment** to employees on the **General** tab.
 - e. Save the changes.
2. Remove direct assignments of the account definition to employees.
 - a. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
 - b. Select an account definition in the result list.
 - c. Select **Assign to employees** in the task view.
 - d. Remove employees from **Remove assignments**.
 - e. Save the changes.
3. Remove the account definition's assignments to departments, cost centers and locations.
 - a. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
 - b. Select an account definition in the result list.

- c. Select **Assign organizations**.
 - d. Remove the account definition's assignments to departments, cost centers and locations in **Remove assignments**.
 - e. Save the changes.
4. Remove the account definition's assignments to business roles.
 - a. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
 - b. Select an account definition in the result list.
 - c. Select **Assign business roles** in the task view.
Remove business roles from **Remove assignments**.
 - d. Save the changes.
5. If the account definition was requested through the IT Shop, it must be canceled and removed from all IT Shop shelves. For more detailed information, see the One Identity Manager IT Shop Administration Guide.
6. Remove the account definition assignment as required account definition for another account definition. As long as the account definition is required for another account definition, it cannot be deleted. Check all the account definitions.
 - a. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
 - b. Select an account definition in the result list.
 - c. Select **Change master data** in the task view.
 - d. Remove the account definition from the **Required account definition** menu.
 - e. Save the changes.
7. Remove the account definition's assignments to target systems.
 - a. Select the host in the category **Unix | Hosts**.
 - b. Select **Change master data** in the task view.
 - c. Remove the assigned account definitions on the **General tab**.
 - d. Save the changes.
8. Delete the account definition.
 - a. Select the category **Unix | Basic configuration data | Account definitions | Account definitions**.
 - b. Select an account definition in the result list.
 - c. Click , to delete the account definition.

Password Policies

One Identity Manager provides you with support for creating complex password policies, for example, for system user passwords, the employees' central password as well as passwords for individual target systems. Password policies apply not only when the user enters a password but also when random passwords are generated.

Predefined password policies are supplied with the default installation that you can use or customize if required. You can also define your own password policies.

Detailed information about this topic

- [Predefined Password Policies](#) on page 51
- [Editing Password Policies](#) on page 52
- [Custom Scripts for Password Requirements](#) on page 55
- [Restricted Passwords](#) on page 57
- [Testing a Password](#) on page 58
- [Testing Generating a Password](#) on page 58
- [Assigning a Password Policy](#) on page 58

Predefined Password Policies

You can customize predefined password policies to meet your own requirements, if necessary.

Password for logging into One Identity Manager

The password policy "One Identity Manager password policy" is used for logging into One Identity Manager. This password policy defines the settings for the system user passwords (`DialogUser.Password` and `Person.DialogUserPassword`) as well as the access code for a one off log in on the Web Portal (`Person.Passcode`).

The password policy "One Identity Manager password policy" is also labeled as the default and is used when no other password policy is found.

Password policy for forming employees' central passwords

An employee's central password is formed from the target system specific user accounts by respective configuration. The password policy "Employee central password policy" defines the settings for the central password (`Person.CentralPassword`).

- ❗ **IMPORTANT:** Ensure that the password policy "Employee central password policy" does not violate the target system specific password requirements.

Password policies for target systems

A predefined password policy that you can apply to the user account password columns, is provided for every target system.


- ① **NOTE:** When you update One Identity Manager version 7.x to One Identity Manager version 8.0.5, the configuration parameter settings for forming passwords are passed on to the target system specific password policies.
- ① **IMPORTANT:** If you are not working with target system specific password policies, the default policy applies. In this case, ensure that the password policy "One Identity Manager password policy" does not violate the target system requirements.

The password policy "Unix password policy" is predefined for Unix-based systems. You can apply this password policy to Unix user accounts (UNIXUser.Password) of a Unix host.

If the hosts' password requirements differ, it is recommended that you set up your own password policies for each host.

Editing Password Policies

To edit a password policy

1. Select the category **Manager | Basic configuration data | Password policies** in the Unix.
2. Select the password policy in the result list and select **Change master data** in the task view.
 - OR -
 - Click  in the result list toolbar.
3. Edit the password policy's master data.
4. Save the changes.





Detailed information about this topic

- [General Master Data for a Password Policy](#) on page 52
- [Policy Settings](#) on page 53
- [Character Sets for Passwords](#) on page 54
- [Custom Scripts for Password Requirements](#) on page 55

General Master Data for a Password Policy

Enter the following master data for a password policy.

Table 13: Master Data for a Password Policy

| Property | Meaning |
|--------------------------|--|
| Display name | Password policy name. Translate the given text using the  button. |
| Description | Spare text box for additional explanation. Translate the given text using the  button. |
| Error Message | Custom error message outputted if the policy is not fulfilled. Translate the given text using the  button. |
| Owner (Application Role) | Application roles whose members can configure the password policies. |
| Default policy | Mark as default policy for passwords. <div style="border-left: 1px solid #0070C0; padding-left: 10px; margin-left: 20px;"> <p> NOTE: The password policy "One Identity Manager password policy" is marked as the default policy. This password policy is applied if no other password policies can be found.</p> </div> |

Policy Settings

Define the following settings for a password policy on the **Password** tab.

Table 14: Policy Settings

| Property | Meaning |
|-----------------------|---|
| Initial password | Initial password for new user accounts. If no password is given when the user account is added or a random password is generated, the initial password is used. |
| Password confirmation | Reconfirm password. |
| Min. Length | Minimum length of the password. Specify the number of characters a password must have. |
| Max. length | Maximum length of the password. Specify the number of characters a password can have. |
| Max. errors | Maximum number of errors. Set the number of invalid passwords. If the user has reached this number the user account is blocked. |
| Validity period | Maximum age of the password. Enter the length of time a password can be used before it expires. |
| Password history | Enter the number of passwords to be saved. If the value '5' is entered, for example, the last 5 passwords of the user are |

| Property | Meaning |
|------------------------|--|
| | saved. |
| Min. password strength | Specifies how secure the password must be. The higher the password strength, the more secure it is. The password strength is not tested if the value is '0'. The values '1', '2', '3' and '4' gauge the required complexity of the password. The value '1' demands the least complex password. The value '4' demands the highest complexity. |
| Name properties denied | Specifies whether name properties are permitted in the password. |

Character Sets for Passwords

Use the **Character classes** tab to specify which characters are permitted for a password.

Table 15: Character Classes for Passwords

| Property | Meaning |
|---|--|
| Min. letters | Specifies the minimum number of alphabetical characters the password must contain. |
| Min. number lower case | Specifies the minimum number of lowercase letters the password must contain. |
| Min. number uppercase | Specifies the minimum number of uppercase letters the password must contain. |
| Min. number digits | Specifies the minimum number of digits the password must contain. |
| Min. number special characters | Specifies the minimum number of special characters the password must contain. |
| Permitted special characters | List of permitted characters. |
| Denied special characters | List of characters, which are not permitted. |
| Max. identical characters in total | Maximum number of identical characters that can be present in the password in total. |
| Max. identical characters in succession | Maximum number of identical character that can be repeated after each other. |

Custom Scripts for Password Requirements

You can implement custom scripts for testing and generating password if the password requirements cannot be mapped with the existing settings options. Scripts are applied in addition to the other settings.

Detailed information about this topic

- [Script for Checking a Password](#) on page 55
- [Script for Generating a Password](#) on page 56

Script for Checking a Password

You can implement a check script if additional policies need to be used for checking a password, which cannot be mapped with the available settings.

Syntax for Check Scripts

```
Public Sub CCC_CustomPwdValidate( policy As VI.DB.Passwords.PasswordPolicy, spwd As System.Security.SecureString)
```

With parameters:

policy = password policy object

spwd = password to test

TIP: To use a base object, take the property Entity of the PasswordPolicy class.

Example for a script for testing a password

A password cannot have '?' or '!' at the beginning. The script checks a given password for validity.

```
Public Sub CCC_PwdValidate( policy As VI.DB.Passwords.PasswordPolicy, spwd As System.Security.SecureString)
    Dim pwd = spwd.ToInsecureArray()
    If pwd.Length>0
        If pwd(0)="?" Or pwd(0)="!"
            Throw New Exception("#LD("Password can't start with '?' or '!")#)
        End If
    End If
    If pwd.Length>2
        If pwd(0) = pwd(1) AndAlso pwd(1) = pwd(2)
```

```

        Throw New Exception(#LD("Invalid character sequence in password")#)
    End If
End If
End Sub

```

To use a custom script for checking a password

1. Create your script in the category **Script Library** in the Designer.
2. Edit the password policy.
 - a. Select the category **Manager | Basic configuration data | Password policies** in the Unix.
 - b. Select the password policy in the result list.
 - c. Select **Change master data** in the task view.
 - d. Enter the name of the script to test the password in **Check script** on the **Scripts** tab.
 - e. Save the changes.

Related Topics

- [Script for Generating a Password](#) on page 56

Script for Generating a Password

You can implement a generating script if additional policies need to be used for generating a random password, which cannot be mapped with the available settings.

Syntax for Generating Script

```
Public Sub CCC_PwdGenerate( policy As VI.DB.Passwords.PasswordPolicy, spwd As System.Security.SecureString)
```

With parameters:

policy = password policy object

spwd = generated password

TIP: To use a base object, take the property Entity of the PasswordPolicy class.

Example for a script to generate a password

The script replaces the invalid characters '?' and '!' in random passwords.

```
Public Sub CCC_PwdGenerate( policy As VI.DB.Passwords.PasswordPolicy, spwd As System.Security.SecureString)
```

```
    Dim pwd = spwd.ToInsecureArray()
```



```

' replace invalid characters at first position
If pwd.Length>0
    If pwd(0)="?" Or pwd(0)="!"
        spwd.SetAt(0, CChar("_"))
    End If
End If
End Sub

```

To use a custom script for generating a password

1. Create your script in the category **Script Library** in the Designer.
2. Edit the password policy.
 - a. Select the category **Manager | Basic configuration data | Password policies** in the Unix.
 - b. Select the password policy in the result list.
 - c. Select **Change master data** in the task view.
 - d. Enter the name of the script to generate a password in **Generation script** on the **Scripts** tab.
 - e. Save the changes.

Related Topics

- [Script for Checking a Password](#) on page 55

Restricted Passwords

You can add words to a list of restricted terms to prohibit them from being used in passwords.

NOTE: The restricted list applies globally to all password policies.

To add a term to the restricted list

1. Select the category **Base Data | Security Settings | Restricted passwords** in the Designer.
2. Create a new entry with the menu item **Object | New** and enter the term to be excluded to the list.
3. Save the changes.

Testing a Password

When you test a password, all the password policy settings, custom scripts and the restricted passwords are taken into account.

To test whether a password conforms to the password policy

1. Select the category **Manager | Basic configuration data | Password policies** in the Unix.
2. Select the password policy in the result list.
3. Select **Change master data** in the task view.
4. Select the **Test** tab.
5. Select the table and object to be tested in **Base object for test**.
6. Enter a password in **Enter password to test**.

A display next to the password shows whether it is valid or not.

Testing Generating a Password

When you generate a password, all the password policy settings, custom scripts and the restricted passwords are taken into account.

To generate a password that conforms to the password policy

1. Select the category **Manager | Basic configuration data | Password policies** in the Unix.
2. Select the password policy in the result list.
3. Select **Change master data** in the task view.
4. Select the **Test** tab.
5. Click **Generate**.

This generates and displays a password.

Assigning a Password Policy

The password policy "Unix password policy" is predefined for Unix-based systems. You can apply this password policy to Unix user accounts (UNIXUser.Password) of a Unix host.


If the hosts' password requirements differ, it is recommended that you set up your own password policies for each host.

- IMPORTANT:** If you are not working with target system specific password policies, the default policy applies. In this case, ensure that the password policy "One Identity Manager password policy" does not violate the target system requirements.

To reassign a password policy

1. Select the category **Manager | Basic configuration data | Password policies** in the Unix.
2. Select the password policy in the result list.
3. Select **Assign objects** in the task view.
4. Click **Add** in the **Assignments** section and enter the following data.

Table 16: Assigning a Password Policy

| Property | Description |
|-----------------|--|
| Apply to | Application scope of the password policy. <i>To specify an application scope</i> <ol style="list-style-type: none">a. Click  next to the text box.b. Select the table which contains the password column under Table.c. Select the specific target system under Apply to.d. Click OK. |
| Password column | The password column's identifier. |
| Password policy | The identifier of the password policy to be used. |

5. Save the changes.

To change a password policy's assignment

1. Select the category **Manager | Basic configuration data | Password policies** in the Unix.
2. Select the password policy in the result list.
3. Select **Assign objects** in the task view.
4. Select the assignment you want to change in **Assignments**.
5. Select the new password policy to apply from the **Password Policies** menu.
6. Save the changes.

Initial Password for New Unix User Accounts

Table 17: Configuration Parameters for Formatting Initial Passwords for User Accounts

| Configuration parameter | Meaning |
|--|--|
| QER\Person\UseCentralPassword | This configuration parameter specifies whether the employee's central password is used in the user accounts. The employee's central password is automatically mapped to the employee's user account in all permitted target systems. This excludes privileged user accounts, which are not updated. |
| QER\Person\UseCentralPassword\PermanentStore | This configuration parameter controls the storage period for central passwords. If the parameter is set, the employee's central password is permanently stored. If the parameter is not set, the central password is only used for publishing to existing target system specific user accounts and is subsequently deleted from the One Identity Manager database. |
| TargetSystem\Unix\Accounts\InitialRandomPassword | This configuration parameter specifies whether a random generated password is issued when a new user account is added. It must contain at least those character sets set in the configuration subparameters. |

You have the following possible options for issuing an initial password for a new Unix user account.

- Use the employee's central password. The employee's central password is mapped to the user account password.
 - Set the configuration parameter "QER\Person\UseCentralPassword" in the Designer.

If the configuration parameter "QER\Person\UseCentralPassword" is set, the employee's central password is automatically mapped to an employee's user account in each of the target systems. This excludes privileged user accounts, which are not updated.
 - Use the configuration parameter "QER\Person\UseCentralPassword\PermanentStore" in the Designer to specify whether an employee's central password is permanently saved in the One Identity Manager database or only until the password has been published in the target system.

The password policy "Employee central password policy" is used to format the central password.

IMPORTANT: Ensure that the password policy "Employee central password policy" does not violate the target system specific password requirements.

- Create user accounts manually and enter a password in their master data.
- Specify an initial password to be used when user accounts are created automatically.
 - Apply the target system specific password policies and enter an initial password in the password policies.
- Assign a randomly generated initial password to enter when you create user accounts.
 - Set the configuration parameter "TargetSystem\Unix\Accounts\InitialRandomPassword" in the Designer.
 - Apply target system specific password policies and define the character sets that the password must contain.
 - Specify which employee will receive the initial password by email.

Related Topics

- [Password Policies](#) on page 51
- [Email Notifications about Login Data](#) on page 61

Email Notifications about Login Data

Table 18: Configuration Parameters for Notifications about Login Data

| Configuration parameter | Meaning |
|--|--|
| TargetSystem\Unix\Accounts\InitialRandomPassword\SendTo | This configuration parameter specifies to which employee the email with the random generated password should be sent (manager cost center/department/location/business role, employee's manager or XUserInserted). If no recipient can be found, the password is sent to the address stored in the configuration parameter "TargetSystem\Unix\DefaultAddress". |
| TargetSystem\Unix\Accounts\InitialRandomPassword\SendTo\MailTemplateName | This configuration parameter contains the name of the mail template sent to inform users about their initial login data (name of the user account). Use the mail template "Employee - new account created". |
| TargetSystem\Unix\Accounts\ | This configuration parameter contains the name of |

| Configuration parameter | Meaning |
|---|---|
| InitialRandomPassword\SendTo\ MailTemplatePassword | the mail template sent to inform users about their initial login data (initial password). Use the mail template "Employee - initial password for new user account". |
| TargetSystem\Unix\DefaultAddress | The configuration parameter contains the recipient's default email address for sending notifications about actions in the target system. |

You can configure the login information for new user accounts to be sent by email to a specified person. In this case, two messages are sent with the user name and the initial password. Mail templates are used to generate the messages. The mail text in a mail template is defined in several languages, which means the recipient's language can be taken into account when the email is generated. Mail templates are supplied in the default installation with which you can configure the notification procedure.

To use email notifications about login data

1. Ensure that the email notification system is configured in One Identity Manager. For more detailed information, see the One Identity Manager Configuration Guide.
2. Enable the configuration parameter "Common\MailNotification\DefaultSender" in the Designer and enter the email address for sending the notification.
3. Ensure that all employees have a default email address. Notifications are sent to this address. For more detailed information, see the One Identity Manager Identity Management Base Module Administration Guide.
4. Ensure that a language culture can be determined for all employees. Only then can they receive email notifications in their own language. For more detailed information, see the One Identity Manager Identity Management Base Module Administration Guide.

When a randomly generated password is issued for the new user account, the initial login data for a user account is sent by email to a previously specified person.

To send initial login data by email

1. Set the configuration parameter "TargetSystem\Unix\Accounts\InitialRandomPassword" in the Designer.
2. Set the configuration parameter "TargetSystem\Unix\Accounts\InitialRandomPassword\SendTo" in the Designer and enter the message recipient as the value.
3. Set the configuration parameter "TargetSystem\Unix\Accounts\InitialRandomPassword\SendTo\MailTemplateAccountName" in the Designer.

By default, the message sent uses the mail template "Employee - new account created". The message contains the name of the user account.

4. Set the configuration parameter "TargetSystem\Unix\Accounts\InitialRandomPassword\SendTo\MailTemplatePassword" in the Designer.

By default, the message sent uses the mail template "Employee - initial password for new user account". The message contains the initial password for the user account.

TIP: Change the value of the configuration parameter in order to use custom mail templates for these mails.

Target System Managers

For more detailed information about implementing and editing application roles, see the One Identity Manager Application Roles Administration Guide.

Implementing Application Roles for Target System Managers

1. The One Identity Manager administrator assigns employees to be target system managers.
2. These target system managers add employees to the default application role for target system managers.

The default application role target system managers are entitled to edit all Unix hosts in One Identity Manager.

3. Target system managers can authorize more employees as target system managers, within their scope of responsibilities and create other child application roles and assign individual Unix hosts.

Table 19: Default Application Roles for Target System Managers

| User | Task |
|------------------------|---|
| Target System Managers | <p>Target system managers must be assigned to the application role Target systems Unix or a sub application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Assume administrative tasks for the target system. • Create, change or delete target system objects, like user accounts or groups. • Edit password policies for the target system. • Prepare groups for adding to the IT Shop. • Configure synchronization in the Synchronization Editor and defines the mapping for comparing target systems and One Identity Manager. |

| User | Task |
|------|--|
| | <ul style="list-style-type: none"> • Edit the synchronization's target system types and outstanding objects. • Authorize other employees within their area of responsibility as target system managers and create child application roles if required. |

To initially specify employees to be target system administrators

1. Log in to the Manager as One Identity Manager administrator (application role **Base role | Administrators**)
2. Select the category **One Identity Manager Administration | Target systems | Administrators**.
3. Select **Assign employees** in the task view.
4. Assign the employee you want and save the changes.

To add the first employees to the default application as target system managers.

1. Log yourself into the Manager as target system administrator (application role **Target systems | Administrator**).
2. Select the category **One Identity Manager Administration | Target systems | Unix**.
3. Select **Assign employees** in the task view.
4. Assign the employees you want and save the changes.

To authorize other employees as target system managers when you are a target system manager

1. Login to the Manager as target system manager.
2. Select the application role in the category **Unix | Basic configuration data | Target system managers**.
3. Select **Assign employees** in the task view.
4. Assign the employees you want and save the changes.

To define target system managers for individual hosts.

1. Login to the Manager as target system manager.
 2. Select the category **Unix | Hosts**.
 3. Select the host in the result list.
 4. Select **Change master data** in the task view.
 5. Select the application role on the **General** tab in the **Target system manager** menu.
- OR -

Click  next to the **Target system manager** menu to create a new application role.

- Enter the application role name and assign the parent application role **Target system | Unix**.
 - Click **OK** to add the new application role.
6. Save the changes.
 7. Assign the application role to employees, who are authorized to edit the host in One Identity Manager.

Related Topics

- [One Identity Manager Users for Managing a Unix-Base Target System](#) on page 8
- [General Master Data for Unix Hosts](#) on page 70

Editing a Server

Servers must know your server functionality in order to handle Unix specific processes in One Identity Manager. For example, the synchronization server.

You have several options for defining a server's functionality:

- Create an entry for the Job server in the category **Base Data | Installation | Job server** in the Designer. For detailed information, see the One Identity Manager Configuration Guide.
- Select an entry for the Job server in the category **Manager | Basic configuration data | Server** in the Unix and edit the Job server master data.

Use this task if the Job server has already been declared in One Identity Manager and you want to configure special functions for the Job server.

- NOTE:** One Identity Manager must be installed, configured and started in order for a server to execute its function in the One Identity Manager Service network. Proceed as follows in the One Identity Manager Installation Guide.

To edit a Job server and its functions

1. Select the category **Unix | Basic configuration data | Server** in the Manager.
2. Select the Job server entry in the result list.
3. Select **Change master data** in the task view.
4. Edit the Job server's master data.
5. Select **Assign server functions** in the task view and specify server functionality.
6. Save the changes.

Detailed information about this topic

- [Master Data for a Job Server](#) on page 66
- [Server Functions of a Job Server](#) on page 68

Master Data for a Job Server

NOTE: All editing options are available to you in the Designer, in the category **Base Data | Installation | Job server**.

Table 20: Job Server Properties

| Property | Meaning |
|------------------------------|---|
| Server | Job server name. |
| Full server name | Full server name in accordance with DNS syntax. Example: <Name of servers>.<Fully qualified domain name> |
| Target System | Computer account target system. |
| Language culture | Language of the server. |
| Server is cluster | Specifies whether the server maps a cluster. |
| Server belongs to cluster | Cluster to which the server belongs. NOTE: The properties Server is cluster and Server belongs to cluster are mutually exclusive. |
| IP address (IPv6) | Internet protocol version 6 (IPv6) server address. |
| IP address (IPv4) | Internet protocol version 4 (IPv4) server address. |
| Copy process (source server) | Permitted copying methods that can be used when this server is the source of a copy action. Only the methods "Robocopy" and "Rsync" are currently supported. If no method is given, the One Identity Manager Service determines the operating system of the server during runtime. Replication then takes place between servers with a Windows operating system using "Robocopy" and |

Property Meaning

| | |
|--|--|
| | between servers with the Linux operating system using "rsync". If the operating systems of the source and destination servers differ, it is important that the right copy method is applied for successful replication. A copy method is chosen that supports both servers. |
| Coding | Character set coding that is used to write files to the server. |
| Parent Job server | Name of the parent Job server. |
| Executing server | <p>Name of the executing server. The name of the server that exists physically and where the processes are handled.</p> <p>This input is evaluated when One Identity Manager Service is automatically updated. If the server is handling several queues the process steps are not supplied until all the queues that are being processed on the same server have completed their automatic update.</p> |
| Queue | Name of the queue to handle the process steps. Each One Identity Manager Service within the network must have a unique queue identifier. The process steps are requested by the job queue using exactly this queue name. The queue identifier is entered in the One Identity Manager Service configuration file. |
| Server operating system | Operating system of the server. This input is required to resolve the path name for replicating software profiles. Permitted values are "Win32", "Windows", "Linux" and "Unix". If the input is empty, "Win32" is assumed. |
| Service account data | One Identity Manager Service user account information. In order to replicate between non-trusted systems (non-trusted domains, Linux server) the One Identity Manager Service user information has to be declared for the servers in the database. This means that the service account, the service account domain and the service account password have to be entered for the server. |
| One Identity Manager Service installed | <p>Specifies whether a One Identity Manager Service is installed on this server. This option is enabled by the procedure QBM_PJobQueueLoad the moment the queue is called for the first time.</p> <p>The option is not automatically removed. If necessary, you can reset this option manually for servers whose queue is no longer enabled.</p> |
| Stop One Identity Manager Service | <p>Specifies whether the One Identity Manager Service has stopped. If this option is set for the Job server, the One Identity Manager Service does not process any more tasks.</p> <p>You can make the service start and stop with the appropriate administrative permissions in program "Job Queue Info".</p> |

| Property | Meaning |
|------------------------------|--|
| No automatic software update | Specifies whether to exclude the server from automatic software updating. i NOTE: Servers must be manually updated if this option is set. |
| Software update running | Specifies whether a software update is currently being executed. |
| Server Function | Server functionality in One Identity Manager. One Identity Manager processes are handled depending on the server function. |

Related Topics

- [Server Functions of a Job Server](#) on page 68

Server Functions of a Job Server

The server function defines the functionality of a server in One Identity Manager. One Identity Manager processes are handled depending on the server function.

i | **NOTE:** All editing options are available to you in the Designer, in the category **Base Data** | **Installation** | **Job server**.

i | **NOTE:** More server functions may be available depending on which modules are installed.

Table 21: Permitted Server Functions

| Server Function | Remark |
|-------------------|---|
| CSV connector | Server on which the CSV connector for synchronization is installed. |
| Domain controller | The Active Directory domain controller. Servers that are not labeled as domain controller are considered to be member servers. |
| Printer server | Server which acts as a print server. |
| Generic server | Server for generic synchronization with a custom target system. |
| Home server | Server for adding home directories for user accounts. |
| Update Server | This server executes automatic software updating of all other servers. The server requires a direct connection to the database server that the One Identity Manager database is installed on. The server can execute SQL tasks. |

| Server Function | Remark |
|---|---|
| | The server with the installed One Identity Manager database, is labeled with this functionality during initial installation of the schema. |
| SQL processing server | This server can process SQL tasks. Several SQL processing servers can be set up to spread the load of SQL processes. The system distributes the generated SQL processes throughout all the Job servers with this server function. |
| Native database connector | The server can connect to an ADO.Net database. |
| One Identity Manager database connector | Server on which the One Identity Manager connector is installed. This server executes synchronization with the target system One Identity Manager. |
| One Identity Manager Service installed | Server on which a One Identity Manager Service is installed. |
| Primary domain controller | Primary domain controller. |
| Profile Server | Server for setting up profile directories for user accounts. |
| SAM synchronization Server | Server for running synchronization with an SMB-based target system. |
| SMTP host | Server from which the One Identity Manager Service sends email notifications. Prerequisite for sending mails using the One Identity Manager Service is SMTP host configuration. |
| Default report server | Server on which reports are generated. |
| Windows PowerShell connector | The server can run Windows PowerShell version 3.0 or later. |
| Unix connector | The server can connect to a Unix system using SSH. |
| AIX connector | The server can connect to an AIX system using SSH. |

Related Topics

- [Master Data for a Job Server](#) on page 66

Unix Host

The Synchronization Editor sets up the hosts in the One Identity Manager database by using a default template.

- NOTE:** After initial synchronization of the hosts, you must enter the primary group, which will be used by default to set up the user accounts.

To edit a Unix host's master data

1. Select the category **Unix | Hosts**.
2. Select the host in the result list.
3. Select **Change master data** in the task view.
4. Edit the host's master data.
5. Save the changes.

Related Topics

- [General Master Data for Unix Hosts](#) on page 70

General Master Data for Unix Hosts

Enter the following data on the **General** tab:

Table 22: General Master Data for a Host

| Property | Description |
|---------------|---|
| Host name | Name of the host. |
| Primary group | User account's primary group. This group is used as primary group when creating a user account. |
| Device | The computer is connected to this device. Specify a new device using the button next to the menu. |




| Property | Description |
|------------------------------|--|
| AIX system | Specifies whether this host is an IBM AIX system. The following properties are offered additionally for user accounts on IBM AIX systems. |
| Account definition (initial) | <p>Initial account definition for creating user accounts. This account definition is used if automatic assignment of employees to user accounts is used for this host and user accounts should be created which are already managed (state "linked configured"). The account definition's default manage level is applied.</p> <p>User accounts are only linked to the employee (state "Linked") if no account definition is given. This is the case on initial synchronization, for example.</p> |
| Target System Managers | <p>Application role, in which target system managers are specified for the host. Target system managers only edit the objects from hosts that are assigned to them. Therefore, each host can have a different target system manager assigned to it.</p> <p>Select the One Identity Manager application role whose members are responsible for administration of this host. Use the  button to add a new application role.</p> |
| Synchronized by | Type of synchronization through which the data is synchronized between the host and One Identity Manager. |

Table 23: Permitted Values

| Value | Synchronization by | Provisioned by |
|----------------------|----------------------------|----------------------------|
| One Identity Manager | Active Directory connector | Active Directory connector |
| No synchronization | none | none |

-  **NOTE:** You can only specify the synchronization type when adding a new host. No changes can be made after saving.
 "One Identity Manager" is used when you create a host with the Synchronization Editor.
-  **NOTE:** If you select "No synchronization" you can define custom processes to exchange data between One Identity Manager and the target system.


| | |
|------------------------------|---|
| Operating system description | Description of the operating system. |
| Distribution | Installed distribution of the operating system. |

| Property | Description |
|-----------------------|--|
| Distribution version | Version of the installed distribution. |
| Kernel version | Current version of the kernel. |
| Operating system type | Type of operating system, for example, Linux, AIX, UNIX. |

Specifying Categories for Inheriting Permissions

In One Identity Manager, groups can be selectively inherited by user accounts. For this, groups and user accounts are divided into categories. The categories can be freely selected and are specified by a template. Each category is given a specific position within the template. The template contains two tables; the user account table and the group table. Use the user account table to specify categories for target system dependent user accounts. Enter your categories for the target system dependent groups, administrative roles, subscriptions and disabled service plans in the . Each table contains the category items "Position1" to "Position31".

To define a category

1. Select the category **Unix | Hosts**.
2. Select the host in the result list.
3. Select **Change master data** in the task view.
4. Switch to the **Mapping rule category** tab.
5. Expand the respective base node of the user account or group table.
6. Click  to enable category.
7. Enter a name for the user account and group categories in the current language.
8. Save the changes.

Detailed information about this topic

- [Unix Group Inheritance Based on Categories](#) on page 109

How to Edit a Synchronization Project

Synchronization projects, in which a host is already used as a base object, can also be opened using the Manager. You can, for example, check the configuration or view the synchronization log in this mode. The Synchronization Editor is not started with its full functionality. You cannot run certain functions, such as, running synchronization or simulation, starting the target system browser and others.

NOTE: The Manager is locked for editing throughout. To edit objects in the Manager, close the Synchronization Editor.

To open an existing synchronization project in the Synchronization Editor

1. Select the category **Unix | Hosts**.
2. Select the host in the result list. Select **Change master data** in the task view.
3. Select **Edit synchronization project...** from the task view.

Related Topics

- [Customizing Synchronization Configuration](#) on page 24

Overview of the Unix Host

Use this task to obtain an overview of the most important information about a host.

To obtain an overview of a host

1. Select the category **Unix | Hosts**.
2. Select the host in the result list.
3. Select **Unix host overview** in the task view.

Displaying Unix Login Shells

This information about a host's login shells is loaded into One Identity Manager and cannot be edited. You can use login shells when setting up user accounts.

To display login shells

1. Select the category **Unix | Hosts | <host name> | Login shells**.
2. Select the login shell in the result list.
3. Select **Unix login shell overview** in the task view.

Related Topics

- [Creating a Formatting Rule for IT Operating Data](#) on page 39
- [General Master Data of a Unix User Account](#) on page 81

Unix User Accounts

You can use One Identity Manager to manage your local Unix-based target system user accounts. User accounts obtain the required access rights to the resources through membership in groups.

Detailed information about this topic

- [Linking User Accounts to Employees](#) on page 75
- [Supported User Account Types](#) on page 76
- [Entering Master Data for Unix User Accounts](#) on page 80
- [Automatic Assignment of Employees to Unix User Accounts](#) on page 91

Linking User Accounts to Employees

The central component of the One Identity Manager is to map employees and their master data with permissions through which they have control over different target systems. For this purpose, information about user accounts and permissions can be read from the target system into the One Identity Manager database and linked to employees. This gives an overview of the permissions for each employees in all of the connected target systems. One Identity Manager provides the possibility to manage user accounts and their permissions. You can provision modifications in the target systems. Employees are supplied with the necessary permissions in the connected target systems according to their function in the company. Regular synchronization keeps data consistent between target systems and the One Identity Manager database.

Because requirements vary between companies, the One Identity Manager offers different methods for supplying user accounts to employees. One Identity Manager supports the following method for linking employees and their user accounts.

- Employees and user accounts can be entered manually and assigned to each other.
- Employees can automatically obtain their account definitions using user account resources. If an employee does not have a user account in a host, a new user account is created. This is done by assigning account definitions to an employee

using the integrated inheritance mechanism followed by process handling.

When you manage account definitions through user accounts, you can specify the way user accounts behave when employees are enabled or deleted.

NOTE: If employees obtain their user accounts through account definitions, they have to have a central user account and obtain their company IT data through assignment to a primary department, primary location or a primary cost center.

- An existing employee is automatically assigned when a user account is added or a new employee is created if necessary. In this case, employee master data is created on the basis of the existing user account master data. This mechanism can be implemented if a new user account is created manually or by synchronization. This method, however, is not the One Identity Manager default method. Define criteria for finding employees for automatic employee assignment.

Related Topics

- [Entering Master Data for Unix User Accounts](#) on page 80
- [Setting Up Account Definitions](#) on page 33
- [Automatic Assignment of Employees to Unix User Accounts](#) on page 91
- For more detailed information about handling and administration of employees and user accounts, see the One Identity Manager Target System Base Module Administration Guide.

Supported User Account Types

Different types of user accounts, such as default user accounts, administrative user accounts or service accounts, can be mapped in One Identity Manager.

Detailed information about this topic

- [Properties for Mapping User Accounts](#) on page 76
- [Default User Accounts](#) on page 77
- [Administrative User Accounts](#) on page 78
- [Privileged User Accounts](#) on page 79

Properties for Mapping User Accounts

The following properties are used for mapping different user account types.

- Identity (column IdentityType)
The identity describes the type of user account.

Table 24: Identities of User Accounts

| Identity | Description | Value of the column "IdentityType" |
|-----------------------------|--|---|
| Primary identity | Employee's default user account. | Primary |
| Organizational identity | Secondary user account used for various roles within the organization, f. ex. In sub-agreements with other functional areas. | Organizational |
| Personalized admin identity | User account with administration rights used by one person. | Admin |
| Sponsored identity | User account used for example for training purposes. | Sponsored |
| Shared identity | User account with administration rights used by several people. | Shared |
| Service identity | Service account. | Service |

- Privileged user account (column IsPrivilegedAccount)
Use this option to flag user accounts with special, privileged permissions. This includes administrative user accounts or service accounts, for example. This option is not used to flag default user accounts.

Default User Accounts

Normally, each employee obtains a default user account, which has the permissions they require for their regular work. The user accounts are linked to the employee. The effect of the link and the scope of the employee's inherited properties on the user accounts can be configured through an account definition and its manage levels.

To create default user accounts through account definitions

1. Create an account definition and assign the manage level "Unmanaged" or "Full managed" to it.
2. Specify the effect of temporarily or permanently disabling, deleting or the security risk of an employee on its user accounts and group memberships for each manage level.

3. Create a formatting rule for IT operating data.

An account definition specifies which rules are used to generate the IT operating data for example, whether the container for a user account is made up of the employee's department, cost center, location or business role and which default values will be used if no IT operating data can be found through the employee's primary roles.

Which IT operating data is required, depends on the target system. The following settings are recommended for default user accounts:

- Use the default value "1" in the formatting rule for the column `IsGroupAccount` and set the option **Always use default value**.
- Use the default value "primary" in the formatting rule for the column `IdentityType` and set the option **Always use default value**.

4. Enter the effective IT operating data for the target system. Select the concrete target system under **Effects on**.

Specify in the departments, cost centers, locations or business roles, which IT operating data should apply when you set up a user account.

5. Assign the account definition to employees.

When the account definition is assigned to an employee, a new user account is created through the inheritance mechanism and subsequent processing.

Related Topics

- [Setting Up Account Definitions](#) on page 33
- [Properties for Mapping User Accounts](#) on page 76

Administrative User Accounts

An administrative user account must be used for certain administrative tasks.

Administrative user accounts are normally predefined in the target system and have fixed identifiers and login names, for example, "Administrator".

Administrative user accounts are loaded through synchronization into the One Identity Manager. To assign a manager to administrative user accounts, assign an employee to the user account in One Identity Manager.

NOTE: You can automatically label administrative user accounts as privileged user accounts. To do this, set the schedule "Mark selected user accounts as privileged" in the Designer.

Related Topics

- [Properties for Mapping User Accounts](#) on page 76
- [Privileged User Accounts](#) on page 79

Privileged User Accounts

Privileged user accounts are used to provide employees with additional privileges. This includes administrative user accounts or service accounts, for example. The user accounts are marked with the property **Privileged user account** (IsPrivilegedAccount).

NOTE: The criteria used to label user accounts automatically as privileged, are defined as extensions to the view definition (ViewAddOn) on the table TSBVAccountIsPrivDetectRule (table type "Union"). The evaluation is done in the script TSB_SetIsPrivilegedAccount.

To create privileged users through account definitions

1. Create an account definition. Create a new manage level for privileged user accounts and assign this manage level to the account definition.
2. If you want to prevent properties for privileged user accounts being overwritten, set the property **IT operating data overwrites** for the manage level, to the value "Only initially". In this case, the properties are populated just once when the user accounts is created.
3. Specify the effect of temporarily or permanently disabling, deleting or the security risk of an employee on its user accounts and group memberships for each manage level.
4. Create a formatting rule for IT operating data.

An account definition specifies which rules are used to generate the IT operating data for example, whether the container for a user account is made up of the employee's department, cost center, location or business role and which default values will be used if no IT operating data can be found through the employee's primary roles.

Which IT operating data is required, depends on the target system. The following settings are recommended for privileged user accounts:

- Use the default value "1" in the formatting rule for the column IsPrivilegedAccount and set the option **Always use default value**.
 - You can also specify a formatting rule for the column IdentityType. The column owns different permitted values, which represent user accounts.
 - To prevent privileged user accounts inheriting default user groups, define a template for the column IsGroupAccount with the default value "0" and set the option **Always use default value**.
5. Enter the effective IT operating data for the target system.
Specify in the departments, cost centers, locations or business roles, which IT operating data should apply when you set up a user account.
 6. Assign the account definition directly to employees who work with privileged user accounts.

When the account definition is assigned to an employee, a new user account is created through the inheritance mechanism and subsequent processing.

- 1 **NOTE:** Specify a formatting rule for a naming schema if it is required by the company for privileged user account login names.

To use a prefix with a login name, set the configuration parameter "TargetSystem\Unix\Accounts\PrivilegedAccount\AccountName_Prefix" in the Designer. To use a postfix with a login name, set the configuration parameter "TargetSystem\Unix\Accounts\PrivilegedAccount\AccountName_Postfix" in the Designer.

These configuration parameters are evaluated in the default installation, if a user account is marked with the property **Privileged user account** (IsPrivilegedAccount). The user account login names are renamed according to the formatting rules. This also takes place if the user accounts are labeled as privileged by the schedule "Mark selected user accounts as privileged".

Related Topics


- [Setting Up Account Definitions](#) on page 33
- [Properties for Mapping User Accounts](#) on page 76

Entering Master Data for Unix User Accounts

A user account can be linked to an employee in the One Identity Manager. You can also manage user accounts separately from employees.

- 1 **NOTE:** It is recommended to use account definitions to set up user accounts for company employees. In this case, some of the master data described in the following is mapped through templates from employee master data.
- 1 **NOTE:** If employees obtain their user accounts through account definitions, they have to have a central user account and obtain their company IT data through assignment to a primary department, primary location or a primary cost center.

To edit master data for a user account

1. Select the category **Unix | User accounts**.
2. Select the user account in the result list and run the task **Change master data**.
- OR -
Click  in the result list toolbar.
3. Edit the user account's resource data.
4. Save the changes.

To manually assign or create a user account for an employee

1. Select the **Employees | Employees**.
2. Select the employee in the result list and run **Assign Unix user accounts** from the task view.
3. Assign a user account.
4. Save the changes.

Detailed information about this topic

- [General Master Data of a Unix User Account](#) on page 81
- [User Account Master Data for AIX Systems](#) on page 84

Related Topics

- [Setting Up Account Definitions](#) on page 33
- [Supported User Account Types](#) on page 76
- [Linking User Accounts to Employees](#) on page 75

General Master Data of a Unix User Account

Enter the following data on the **General** tab:

Table 25: Additional Master Data for a User Account

| Property | Description |
|--------------------|--|
| Host | The user account's host. |
| Employee | Employee that uses this user account. An employee is already entered if the user account was generated by an account definition. If you create the user account manually, you can select an employee in the menu. If you use automatic employee assignment, an associated employee is created and entered into the user account when the user account is saved. |
| Account definition | Account definition through which the user account was created. Use the account definition to automatically fill user account master data and to specify a manage level for the user account. The One Identity Manager finds the IT operating data of the assigned employee and enters it in the corresponding fields in the user account. i NOTE: The account definition cannot be changed once the user account has been saved. |
| Manage level | User account's manage level. Select a manage level from the menu. You can only specify the manage level can if you have also entered an account |

| Property | Description |
|-------------------------|--|
| | definition. All manage levels of the selected account definition are available in the menu. |
| Login shell | Shell that is executed if a user logs in to Unix using a terminal based login. |
| User name | Name of the user account for logging in to a Unix host. If an account definition is assigned, this field is automatically filled with the employee's central user account depending on the manage level. |
| User ID | User ID for the user account in the Unix host. |
| Password | <p>Password for the user account. Depending on the configuration parameter "Person\UseCentralPassword" the employee's central password can be mapped to the user account's password. If you use an initial password for the user accounts, it is automatically entered when a user account is created.</p> <p>i NOTE: One Identity Manager password policies are taken into account when a user password is being verified. Ensure that the password policy does not violate the target system's requirements.</p> |
| Password confirmation | Reconfirm password. |
| Primary group ID | Identifier of the user account's primary group. |
| Primary group | <p>Name of the user account's primary group. This defines the group ownership of files created by the user.</p> <p>A user account's primary group is determined as follows:</p> <ul style="list-style-type: none"> • If you entered a primary group in the host, the group is used as primary group when a user account is created. • If you did not enter a primary group, a new group is created with the display name of the new user account assigned as the primary group. |
| Home directory | The user's full home directory path, for example /home/user001. |
| Risk index (calculated) | Maximum risk index values for all assigned groups. This property is only visible if the configuration parameter "QER\CalculateRiskIndex" is set. For more detailed information, see the One Identity Manager Risk Assessment Administration Guide. |
| Category | Categories for the inheritance of groups by the user account. Select one or more categories from the menu. Groups can be selectively inherited by user accounts. To do this, groups and user accounts or contacts are divided into categories. |

| Property | Description |
|---|---|
| Comment (GECOS) | Spare text box for additional explanation. Additional information about the user account, which is found in the GECOS in /etc/passwd. If an account definition is assigned, this field is automatically filled with the employee's internal name depending on the manage level. |
| Identity | User account's identity type |
| Table 26: Permitted values for the identity. | |
| Value | Description |
| Primary identity | Employee's default user account. |
| Organizational identity | Secondary user account used for different roles in the organization, for example for subcontracts with other functional areas. |
| Personalized admin identity | User account with administrative permissions, used by one employee. |
| Sponsored identity | User account that is used for training purposes, for example. |
| Shared identity | User account with administrative permissions, used by several employees. |
| Service identity | Service account. |
| Groups can be inherited | <p>Specifies whether the user account groups can inherit through the employee. If this option is set, the user account inherits groups through hierarchical roles or IT Shop requests.</p> <ul style="list-style-type: none"> • If you add an employee with a user account to a department, for example, and you have assigned groups to this department, the user account inherits these groups. • If an employee has requested group membership in the IT Shop and the request is granted approval, the employee's user account only inherits the group if the option is set. |
| Privileged user account | Specifies whether this is a privileged user account. |

Related Topics

- [Setting Up Account Definitions](#) on page 33
- [Password Policies](#) on page 51
- [Initial Password for New Unix User Accounts](#) on page 60
- [Unix Group Inheritance Based on Categories](#) on page 109

- [Supported User Account Types](#) on page 76
- [General Master Data for Unix Hosts](#) on page 70
- [Disabling User Accounts for AIX Systems](#) on page 96

User Account Master Data for AIX Systems

You can enter additional master data for user accounts in an IBM AIX system, like limits, password data, security data or information about encrypting the file system. This data is shown if the host is labeled with the option **AIX system**.

Detailed information about this topic

- [User Account Limits](#) on page 84
- [User Account Password Data](#) on page 85
- [Security Relevant User Account Master Data](#) on page 87
- [Master Data of a User Account's Encrypted File System](#) on page 88
- [General Master Data for Unix Hosts](#)

User Account Limits

On the **Limits** tab, you can enter the following limits for resources of the user's processes in an AIX system. This data is mapped in `/etc/security/limits`.

Table 27: Limits for User Accounts in an AIX System

| Property | Description |
|------------------|---|
| Core size (soft) | Soft limit for the size of the core dump file that can be created by a user process. (Parameter <code>core</code>). |
| Core size (hard) | Absolute maximum limit for the size of the core dump file that can be created by a user process. (Parameter <code>core_hard</code>). |
| CPU time (soft) | Soft limit for the time (in seconds) a user process may take. (Parameter <code>cpu</code>). |
| CPU time (hard) | Maximum amount of time (in seconds) the user process may take. (Parameter <code>cpu_hard</code>). |
| Data size (soft) | Soft limit for the size of the process' data segment for a user process. (Parameter <code>data</code>). |
| Data size (hard) | Maximum size of a process' data segment for a user process. (Parameter <code>data_hard</code>). |

| Property | Description |
|-------------------------|--|
| File size (soft) | Soft limit for the size of a file a user process can create or extend. (Parameter <code>fsize</code>). |
| File size (hard) | Absolute maximum size of a file a user process can create or extend. (Parameter <code>fsize_hard</code>). |
| Memory size (soft) | Soft limit for the maximum amount of physical memory a user process can take up. (Parameter <code>rss</code>). |
| Memory size (hard) | Maximum amount of physical memory a user process can take up. (Parameter <code>rss_hard</code>). |
| Stack size (soft) | Soft limit for the size of the process' stack segment for a user process. (Parameter <code>stack</code>). |
| Stack size (hard) | Maximum size of a process' stack segment for a user process. (Parameter <code>stack_hard</code>). |
| File descriptors (soft) | Soft limit for the number of file descriptors a user process can have open at the same time. (Parameter <code>nofiles</code>). |
| File descriptors (hard) | Absolute maximum number of file descriptors a user process can have open at the same time. (Parameter <code>nofiles_hard</code>). |
| Threads (soft) | Soft limit for the number of threads per process. (Parameter <code>threads</code>). |
| Threads (hard) | Absolute maximum number of threads per process. (Parameter <code>threads_hard</code>). |
| Processes (soft) | Soft limit for the number of processes per user. (Parameter <code>nproc</code>). |
| Processes (hard) | Absolute maximum for the number of processes per user. (Parameter <code>nproc_hard</code>). |

User Account Password Data

On the **Password** tab you can enter the following additional information about a user account in the AIX system. This data is mapped in `/etc/security/user`.

Table 28: Password Data for User Accounts in an AIX System

| Property | Description |
|---------------------|--|
| <code>minlen</code> | Minimum number of characters a password must have. (Parameter <code>minlen</code>). |

| Property | Description |
|----------------|--|
| maxrepeats | Maximum number of characters that can be repeated in passwords. The default value 8 specifies that a maximum has not been fixed. (Parameter maxrepeats). |
| mindiff | Minimum number of unique characters that passwords must contain. (Parameter mindiff). |
| minalpha | Specifies the minimum number of alphabetical characters a new password must contain. (Parameter minalpha). |
| minloweralpha | Specifies the minimum number of lowercase letters a new password must contain. (Parameter minloweralpha). |
| minupperalpha | Specifies the minimum number of uppercase letters a new password must contain. (Parameter minupperalpha). |
| mindigit | Specifies the minimum number of digits a new password must contain. (Parameter mindigit). |
| minspecialchar | Specifies the minimum number of special characters a new password must contain. (Parameter minspecialchar). |
| minother | Specifies the minimum number of non-alphabetical characters a new password must contain. (Parameter minother). |
| dictionlist | Dictionary file of black listed passwords. Verifies passwords do not include standard UNIX words. (Parameter dictionlist). |
| histexpire | Number of weeks before a password can be reused. (Parameter histexpire). |
| histsize | Number of password iterations allowed before an old password can be used again. (Parameter histsize). |
| minage | Minimum number of weeks before a password can be changed. (Parameter minage). |
| maxage | Maximum number of weeks before a password must be changed. (Parameter maxage). |
| maxexpired | Maximum number of weeks beyond maxage that an expired password can be changed by the user. (Parameter maxexpired). |
| pwdchecks | Methods to apply to new passwords that check the password quality. The value contains a comma delimited list of method names. (Parameter pwdchecks). |
| pwdwarntime | Number of days before the system issues a warning that a password change is required. (Parameter pwdwarntime). |

Security Relevant User Account Master Data

On the **security** tab you can enter the following additional information about a user account in the AIX system. This data is mapped in `/etc/security/user`.

Table 29: Additional Security Relevant Data for User Accounts in an AIX System

| Property | Description |
|----------------|---|
| account_locked | Specifies whether the user account is locked. (Parameter <code>account_locked</code>). |
| admin | Defines the administrative status of the user. (Parameter <code>admin</code>). |
| admgroups | Lists the groups the user administrates. (Parameter <code>admgroups</code>). |
| auditclasses | The user account's audit classes. (Parameter <code>auditclasses</code>). |
| auth1 | Additional mandatory methods for authenticating the user. (Parameter <code>auth1</code>). |
| auth2 | Additional optional methods for authenticating the user. (Parameter <code>auth2</code>). |
| core_compress | Enables or disables core file compression. (Parameter <code>core_compress</code>). |
| core_path | Enables or disables core file path specification. (Parameter <code>core_path</code>). If this attribute has a value of On, core files will be placed in the given directory. otherwise, core files are placed in the user's current working directory. |
| core_naming | Naming conventions for the core file. If this option is set, the core file is stamped with a process ID, the time and date. (Parameter <code>core_naming</code>). |
| daemon | Specifies whether the user can execute programs using the cron daemon or the src (system resource controller) daemon. (Parameter <code>daemon</code>). |
| dce_export | Specifies whether the DCE registry can overwrite the local user information with the DCE user information during a DCE export operation. (Parameter <code>dce_export</code>). |
| expires | Expiration date of the user account. (Parameter <code>expires</code>). |
| login | Specifies whether the user can log in to the system with the <code>login</code> command. (Parameter <code>login</code>). |
| logintimes | Times, days, or both, the user is allowed to access the system. (Parameter <code>logintimes</code>). |
| loginretries | Number of unsuccessful login attempts allowed after the last successful login before the system locks the account. (Parameter <code>loginretries</code>). A value of 0 or a negative value, indicates no maximum age. |
| projects | List of projects that the user's processes can be assigned to. The value is a list of comma-delimited project names. (Parameter <code>projects</code>). |

| Property | Description |
|----------|--|
| registry | Defines the authentication registry where the user is administered. (Parameter registry). |
| rlogin | Permits access to the account from a remote location with the telnet or rlogin commands. (Parameter rlogin). |
| su | Specifies whether another user can switch to the specified user account with the su command. (Parameter su). |
| sugroups | Groups that can use the su command to switch to the specified user. (Parameter sugroups). |
| SYSTEM | System's authentication mechanism for the user. (Parameter SYSTEM). |
| tpath | The user's trusted path status. (Parameter tpath). |
| ttys | Lists the terminals that can access the user. (Parameter ttys). |
| umask | Determines file permissions. (Parameter umask). The default value is 022. |

Related Topics

- [Disabling User Accounts for AIX Systems](#) on page 96

Master Data of a User Account's Encrypted File System

On the **Encrypted File System** tab you can enter the following additional information for using encrypted file system (EFS) for a user account in an AIX system. This data is mapped in `/etc/security/user`.

Table 30: User Account Master Data for Encrypted File Systems

| Property | Description |
|-----------------------------|--|
| efs_adminks_access | Defines the efs_admin keystore location (Parameter efs_adminks_access). Permitted values: <ul style="list-style-type: none"> • file • ldap |
| efs_allowksmodechangebyuser | Specifies whether the user can change the mode or not. (Parameter efs_allowksmodechangebyuser). |
| efs_file_algo | Algorithm used to generate the file protection key. (Parameter efs_file_algo). Permitted values: <ul style="list-style-type: none"> • AES_128_CBC |

| Property | Description |
|---------------------|---|
| | <ul style="list-style-type: none"> AES_192_CBC AES_256_CBC |
| efs_initialks_mode | Initial mode of the user keystore. (Parameter efs_initialks_mode). Permitted values: <ul style="list-style-type: none"> guard Admin |
| efs_keystore_access | User keystore location. (Parameter efs_keystore_access). Permitted values: <ul style="list-style-type: none"> none file |
| efs_keystore_algo | Algorithm used to generate the user private key when the keystore is created. (Parameter efs_keystore_algo). Permitted values: <ul style="list-style-type: none"> RSA_1024 RSA_2048 RSA_4096 |

Additional Tasks for Managing Unix User Accounts

After you have entered the master data, you can apply different tasks to it. The task view contains different forms with which you can run the following tasks.

Overview of Unix User Accounts

Use this task to obtain an overview of the most important information about a user account.

To obtain an overview of a user account

1. Select the category **Unix | User accounts**.
2. Select the user account in the result list.
3. Select **Unix user account overview** in the task view.

Changing the Manage Level of a Unix User Account

The default manage level is applied if you create user accounts using automatic employee assignment. You can change a user account manage level later.

To change the manage level for a user account

1. Select the category **Unix | User accounts**.
2. Select the user account in the result list.
3. Select **Change master data** in the task view.
4. Select the manage level in the **Manage level** menu on the tab **General**.
5. Save the changes.

Related Topics

- [Entering Master Data for Unix User Accounts](#) on page 80

Assigning Unix Groups Directly to Unix User Accounts

Groups can be assigned directly or indirectly to a user account. Indirect assignment is carried out by allocating the employee and groups in hierarchical roles, like departments, cost centers, locations or business roles. If the employee has a user account in Unix, the groups in the role are inherited by this user account.

To react quickly to special requests, you can assign groups directly to the user account.

To assign groups directly to user accounts

1. Select the category **Unix | User accounts**.
2. Select the user account in the result list.
3. Select **Assign groups** in the task view.
4. Assign groups in **Add assignments**.
- OR -
Remove groups from **Remove assignments**.
5. Save the changes.

Related Topics

- [Assigning Unix Groups to Unix User Accounts](#) on page 100

Assigning Extended Properties to a Unix User Account

Extended properties are meta objects that cannot be mapped directly in the One Identity Manager, for example, operating codes, cost codes or cost accounting areas.

To specify extended properties for a user account

1. Select the category **Unix | User accounts**.
2. Select the user account in the result list.
3. Select **Assign extended properties** in the task view.
4. Assign extended properties in **Add assignments**.
- OR -
Remove assignments to extended properties in **Remove assignments**.
5. Save the changes.

For more detailed information about using extended properties, see the One Identity Manager Identity Management Base Module Administration Guide.

Automatic Assignment of Employees to Unix User Accounts

Table 31: Configuration Parameters for Automatic Employee Assignment

| Configuration parameter | Meaning |
|--------------------------------------|--|
| TargetSystem\Unix\PersonAutoFullsync | This configuration parameter specifies the mode for automatic employee assignment for user accounts added to or updated in the database through synchronization. |
| TargetSystem\Unix\PersonAutoDefault | This configuration parameter specifies the mode for automatic employee assignment for user accounts added to the database outside synchronization. |
| TargetSystem\Unix\PersonExcludeList | List of all user accounts for which automatic employee assignment should not take place. Names given in a pipe () delimited list that is handled as a regular search pattern. Example: Root |

| Configuration parameter | Meaning |
|--|---|
| TargetSystem\Unix\ PersonAutoDisabledAccounts | This configuration parameters specifies whether employees are automatically assigned to disable user accounts. User accounts do not obtain an account definition. |

When you add a user account, an existing employee can be assigned automatically or added if necessary. In the process, the employee master data is created based for existing user master data. This mechanism can follow on after a new user account has been created manually or through synchronization. Define criteria for finding employees to apply to automatic employee assignment. If a user account is linked to an employee through the current mode, the user account is given, through an internal process, the default manage level of the account definition entered in the user account's target system. You can customize user account properties depending on how the behavior of the manage level is defined.

If you run this procedure during working hours, automatic assignment of employees to user accounts takes place from that moment onwards. If you disable the procedure again later, the changes only affect user accounts added or updated after this point in time. Existing employee assignment to user accounts remain intact.

- NOTE: It is not recommended to assign employees using automatic employee assignment in the case of administrative user accounts. Use the task **Change master data** to assign employees to administrative user account for the respective user account.

Run the following tasks to assign employees automatically.

- If employees can be assigned by user accounts during synchronization, set the parameter "TargetSystem\Unix\PersonAutoFullsync" in the Designer and select the required mode.
- If employees can be assigned by user accounts outside synchronization, set the parameter "TargetSystem\Unix\PersonAutoDefault" in the Designer and select the required mode.
- Specify the user accounts in the configuration parameter "TargetSystem\Unix\PersonExcludeList" which must not be assigned automatically to employees.

Example:

ROOT

- Use the configuration parameter "TargetSystem\Unix\PersonAutoDisabledAccounts" to specify whether employees can be automatically assigned to disabled user accounts. User accounts do not obtain an account definition.
- Assign an account definition to the host. Ensure the manage level to be used is entered as default automation level.
- Define the search criteria for employees assigned to the host.

NOTE:

The following applies for synchronization:

- Automatic employee assignment takes effect if user accounts are added or updated.

The following applies outside synchronization:

- Automatic employee assignment takes effect if user accounts are added.

NOTE: Following synchronization, employees are automatically created for user accounts in the default installation. If there are no account definitions for the host at the time of synchronization, user accounts are linked to employees. However, account definitions are not assigned. The user accounts are, therefore, in a "Linked" state.

To select user accounts through account definitions

1. Create an account definition.
2. Assign an account definition to the host.
3. Assign the account definition and manage level to the user accounts in a "linked" state.
 - a. Select the category **Unix | User accounts | Linked but not configured | <host>**.
 - b. Select the task **Assign account definition to linked accounts**.

For more detailed information about assigning employees automatically, see the One Identity Manager Target System Base Module Administration Guide.

Related Topics

- [Creating an Account Definition](#) on page 34
- [Assigning Account Definitions to a Target System](#) on page 48
- [Editing Search Criteria for Automatic Employee Assignment](#) on page 93

Editing Search Criteria for Automatic Employee Assignment

Criteria for employee assignment are defined in the host. In this case, you specify which user account properties must match the employee's properties such that the employee can be assigned to the user account. You can limit search criteria further by using format definitions. The search criteria are written in XML notation in the column "Search criteria for automatic employee assignment" (AccountToPersonMatchingRule) of the UNXHost table.

Search criteria are evaluated when employees are automatically assigned to user accounts. Furthermore, you can create a suggestion list for assignments of employees to user accounts based on the search criteria and make the assignment directly.

NOTE: When the employees are assigned to user accounts on the basis of search criteria, user accounts are given the default manage level of the account definition entered in the user account's target system. You can customize user account properties depending on how the behavior of the manage level is defined.

It is not recommended to make assignment to administrative user accounts based on search criteria. Use the task **Change master data** to assign employees to administrative user account for the respective user account.

NOTE: One Identity Manager supplies a default mapping for employee assignment. Only carry out the following steps when you want to customize the default mapping.

To specify criteria for employee assignment

1. Select the category **Unix | Hosts**.
2. Select the host in the result list.
3. Select **Define search criteria for employee assignment** in the task view.
4. Specify which user account properties must match with which employee so that the employee is linked to the user account.

Table 32: Default Search Criteria for User Accounts and Contacts

| Apply to | Column on Employee | Column on User Account |
|--------------------|---------------------------------------|-------------------------|
| Unix user accounts | Central user account (CentralAccount) | User name (AccountName) |

5. Save the changes.

Direct Assignment of Employees to User Accounts Based on a Suggestion List

You can create a suggestion list in the "Assignments" view for assignments of employees to user accounts based on the search criteria. User accounts are grouped in different views for this.

Table 33: Manual Assignment View

| View | Description |
|-----------------------|---|
| Suggested assignments | This view lists all user accounts to which One Identity Manager can assign an employee. All employees are shown who were found using the search criteria and can be assigned. |

| View | Description |
|-----------------------------|---|
| Assigned user accounts | This view lists all user accounts to which an employee is assigned. |
| Without employee assignment | This view lists all user accounts to which no employee is assigned and for which no employee was found using the search criteria. |

TIP: By double-clicking on an entry in the view, you can view the user account and employee master data.

To apply search criteria to user accounts

- Click **Reload**.

All possible assignments based on the search criteria are found in the target system for all user accounts. The three views are updated.

To assign employees directly over a suggestion list

1. Click **Suggested assignments**.

- a. Click **Select** for all user accounts to be assigned to the suggested employee. Multi-select is possible.
- b. Click **Assign selected**.
- c. Confirm the security prompt with **Yes**.
The selected user accounts are assigned to the employees found using the search criteria.

– OR –

2. Click **No employee assignment**.

- a. Click **Select employee...** for the user account to which you want to assign the employee. Select an employee from the menu.
- b. Click **Select** for all user accounts to which you want to assign the selected employees. Multi-select is possible.
- c. Click **Assign selected**.
- d. Confirm the security prompt with **Yes**.
This assigns the selected user accounts to the employees shown in the "Employee" column.

To remove assignments

1. Click **Assigned user accounts**.

- a. Click **Select** for all user accounts whose employee assignment you want to remove. Multi-select is possible.
- b. Click **Delete selected**.

- c. Confirm the security prompt with **Yes**.

The assigned employees are deleted from the selected user accounts.

For more detailed information about defining search criteria, see the One Identity Manager Target System Base Module Administration Guide.

Related Topics

- [Automatic Assignment of Employees to Unix User Accounts](#) on page 91

Disabling User Accounts for AIX Systems

NOTE: The behavior described in the following, only applies to user account in an AIX system.

Table 34: Configuration Parameter for User Accounts

| Configuration parameter | Meaning |
|----------------------------------|---|
| QER\Person\TemporaryDeactivation | This configuration parameter specifies whether user accounts for an employee are locked if the employee is temporarily or permanently disabled. |

The way you disable user accounts depends on how they are managed.

Scenario:

- The user account is linked to employees and is managed through account definitions.

User accounts managed through account definitions are disabled when the employee is temporarily or permanently disabled. The behavior depends on the user account manage level. User accounts with the manage level "Full managed" are disabled depending on the account definition settings. For user accounts with another manage level, modify the column template `UNIXAccount.AIX_account_Locked` accordingly.

Scenario:

- The user accounts are linked to employees. No account definition is applied.

User accounts managed through user account definitions are disabled when the employee is temporarily or permanently disabled. The behavior depends on the configuration parameter "QER\Person\TemporaryDeactivation".

- If the configuration parameter is set, the employee's user accounts are disabled if the employee is permanently or temporarily disabled.
- If the configuration parameter is not set, the employee's properties do not have any effect on the associated user accounts.

To lock a user account when the configuration parameter is disabled

1. Select the category **Unix | User accounts**.
2. Select the user account in the result list.
3. Select **Change master data** in the task view.
4. Set the option **account_locked** on the **Security** tab.
5. Save the changes.

Scenario:

- User accounts not linked to employees.

To lock a user account, which is not linked to an employee

1. Select the category **Unix | User accounts**.
2. Select the user account in the result list.
3. Select **Change master data** in the task view.
4. Set the option **account_locked** on the **Security** tab.
5. Save the changes.

Related Topics

- [Setting Up Account Definitions](#) on page 33
- [Setting Up Manage Levels](#) on page 36
- [Deleting and Restoring Unix User Accounts](#) on page 97
- For more detailed information about deactivating and deleting employees and user accounts, see the One Identity Manager Target System Base Module Administration Guide.

Deleting and Restoring Unix User Accounts

- NOTE:** As long as an account definition for an employee is valid, the employee retains the user account that was created by it. If the account definition assignment is removed, the user account created through this account definition, is deleted.

To delete a user account

1. Select the category **Unix | User accounts**.
2. Select the user account in the result list.
3. Delete the user account.
4. Confirm the security prompt with **Yes**.

To restore user account

1. Select the category **Unix | User accounts**.
2. Select the user account in the result list.
3. Click **Undo delete** in the result list toolbar.

Configuring Deferred Deletion

By default, user accounts are finally deleted from the database after 30 days. The user accounts are initially disabled. You can reenable the user accounts until deferred deletion is run. After deferred deletion is run, the user account are deleted from the database and cannot be restored anymore. You can configure an alternative delay on the table UNXAccount in the Designer.

Related Topics

- [Disabling User Accounts for AIX Systems](#) on page 96
- For more detailed information about deactivating and deleting employees and user accounts, see the One Identity Manager Target System Base Module Administration Guide.

Unix Groups

In the Unix host, user accounts can be gathered into groups, which can be used to regulate access to resources. Local groups are loaded into One Identity Manager by synchronization. You can set up new groups or to edit already existing groups.


To add users to groups, you assign the groups directly to users. This can be assignments of groups to departments, cost centers, location, business roles or to the IT Shop.

Detailed information about this topic

- [Entering Master Data for Unix Groups](#) on page 99
- [Assigning Unix Groups to Unix User Accounts](#) on page 100

Entering Master Data for Unix Groups

To edit group master data

1. Select the category **Unix | Groups**.
2. Select the group in the result list and run **Change master data** in the task view.
- OR -
Click  in the result list toolbar.
3. Edit a group's master data.
4. Save the changes.

Detailed information about this topic

- [General Master Data for an Unix Group](#) on page 99

General Master Data for an Unix Group

Enter the following data on the **General** tab:

Table 35: General Master Data

| Property | Description |
|-------------------------|--|
| Group name | Name of the group. |
| Group ID | Group's identifier. |
| Host | Group's host. |
| IT Shop | Specifies whether the group can be requested through the IT Shop. This group can be requested by staff through the Web Portal and granted through a defined approval process. The group can still be assigned directly to hierarchical roles. |
| Only for use in IT Shop | Specifies whether the group can only be requested through the IT Shop. This group can be requested by staff through the Web Portal and granted through a defined approval process. Direct assignment of the group to hierarchical roles or user accounts is not permitted. |
| Service item | Service item data for requesting the group through the IT Shop. |
| Risk index | Value for evaluating the risk of assigning the group to user accounts. Enter a value between 0 and 1. This property is only visible when the configuration parameter QER\CalculateRiskIndex is set. For more detailed information about risk assessment, see the One Identity Manager Risk Assessment Administration Guide. |
| Category | Categories for group inheritance. Groups can be selectively inherited by user accounts. To do this, groups and user accounts are divided into categories. Use this menu to allocate one or more categories to the group. |

Related Topics

- [Unix Group Inheritance Based on Categories](#) on page 109
- For more detailed information about preparing groups for requesting through the IT Shop, see the One Identity Manager IT Shop Administration Guide.

Assigning Unix Groups to Unix User Accounts

Groups can be assigned directly or indirectly to user accounts. In the case of indirect assignment, employees and groups are assigned to hierarchical roles, such as , departments, cost centers, locations or business roles. The groups assigned to an employee are calculated from the position in the hierarchy and the direction of inheritance.

If you add an employee to roles and that employee owns a user account, the user account is added to the groups. Prerequisites for indirect assignment of employees to user accounts:

- Assignment of employees and groups is permitted for role classes (department, cost center, location or business role).
- The user accounts are marked with the option **Groups can be inherited**.

Furthermore, groups can be assigned to employees through IT Shop requests. Add employees to a shop as customers so that groups can be assigned through IT Shop requests. All groups assigned to this shop can be requested by the customers. Requested groups are assigned to the employees after approval is granted.

Detailed information about this topic

- [Assigning Unix Groups to Departments, Cost Centers and Locations](#) on page 101
- [Assigning Unix Groups to Business Roles](#) on page 102
- [Assigning Unix User Accounts directly to an Unix Group](#) on page 103
- [Adding Unix Groups to System Roles](#) on page 104
- [Adding Unix Groups to the IT Shop](#) on page 104

Assigning Unix Groups to Departments, Cost Centers and Locations

Assign groups to departments, cost centers or locations so that the group can be assigned to user accounts through these organizations.

To assign a group to departments, cost centers or locations (non role-based login)

1. Select the category **Unix | Groups**.
 2. Select the group in the result list.
 3. Select **Assign organizations**.
 4. Assign organizations in **Add assignments**.
 - Assign departments on the **Departments** tab.
 - Assign locations on the **Locations** tab.
 - Assign cost centers on the **Cost center** tab.
- OR -
- Remove the organizations from **Remove assignments**.
5. Save the changes.

To assign groups to a department, cost center or location (role-based login)

1. Select the category **Organizations | Departments**.
- OR -
Select the category **Organizations | Cost centers**.
- OR -
Select the category **Organizations | Locations**.
2. Select the department, cost center or location in the result list.
3. Select **Assign Unix groups**.
4. Assign groups in **Add assignments**.
- OR -
Remove assignments to groups in **Remove assignments**.
5. Save the changes.

Related Topics

- [Assigning Unix Groups to Business Roles](#) on page 102
- [Assigning Unix User Accounts directly to an Unix Group](#) on page 103
- [Adding Unix Groups to System Roles](#) on page 104
- [Adding Unix Groups to the IT Shop](#) on page 104

Assigning Unix Groups to Business Roles

Installed Modules: Business Roles Module

Assign the group to business roles so that the group is assigned to user accounts through these business roles.

To assign a group to a business role (non role-based login)

1. Select the category **Unix | Groups**.
2. Select the group in the result list.
3. Select **Assign business roles** in the task view.
4. Assign business roles in **Add assignments**.
- OR -
Remove business roles from **Remove assignments**.
5. Save the changes.

To assign groups to a business role (non role-based login)

1. Select the category **Business roles | <Role class>**.
2. Select the business role in the result list.
3. Select **Assign Unix groups**.
4. Assign groups in **Add assignments**.
- OR -
Remove assignments to groups in **Remove assignments**.
5. Save the changes.

Related Topics

- [Assigning Unix Groups to Departments, Cost Centers and Locations](#) on page 101
- [Assigning Unix User Accounts directly to an Unix Group](#) on page 103
- [Adding Unix Groups to System Roles](#) on page 104
- [Adding Unix Groups to the IT Shop](#) on page 104

Assigning Unix User Accounts directly to an Unix Group

Groups can be assigned directly or indirectly to user accounts. Indirect assignment is carried out by allocating the employee and groups in company structures, like departments, cost centers, locations or business roles. If the employee has a user account in a Unix-based target system, the groups in the role are inherited by this user account.

To react quickly to special requests, you can assign groups directly to user accounts.

To assign a group directly to user accounts

1. Select the category **Unix | Groups**.
2. Select the group in the result list.
3. Select **Assign user accounts** in the task view.
4. Assign user accounts in **Add assignments**.
- OR -
Remove user accounts from **Remove assignments**.
5. Save the changes.

Related Topics

- [Assigning Unix Groups Directly to Unix User Accounts](#) on page 90
- [Assigning Unix Groups to Departments, Cost Centers and Locations](#) on page 101

- [Assigning Unix Groups to Business Roles](#) on page 102
- [Adding Unix Groups to System Roles](#) on page 104
- [Adding Unix Groups to the IT Shop](#) on page 104

Adding Unix Groups to System Roles

Installed Modules: System Roles Module

Use this task to add a group to system roles. If you assign a system role to employees, all the employees' user accounts inherit the group.

NOTE: Groups with the option **Only use in IT Shop** can only be assigned to system roles that also have this option set. For more detailed information, see the One Identity Manager System Roles Administration Guide.

To assign a group to system roles

1. Select the category **Unix | Groups**.
2. Select the group in the result list.
3. Select **Assign system roles in the task view**.
4. Assign system roles in **Add assignments**.
- OR -
Remove system roles from **Remove assignments**.
5. Save the changes.

Related Topics

- [Assigning Unix Groups to Departments, Cost Centers and Locations](#) on page 101
- [Assigning Unix Groups to Business Roles](#) on page 102
- [Assigning Unix User Accounts directly to an Unix Group](#) on page 103
- [Adding Unix Groups to the IT Shop](#) on page 104

Adding Unix Groups to the IT Shop

Once a group has been assigned to an IT Shop shelf, it can be requested by the shop customers. To ensure it can be requested, further prerequisites need to be guaranteed.

- The group must be labeled with the option **IT Shop**.
- The group must be assigned to a service item.

- The group must be also labeled with the option **Only use in IT Shop** if the role can only be assigned to employees using IT Shop requests. Direct assignment to hierarchical roles may not be possible.

1 | **NOTE:** IT Shop administrators can assign groups to IT Shop shelves if login is role-based. Target system administrators are not authorized to add groups in the IT Shop.

To add a group to the IT Shop

1. Select the category **Unix | Groups** (non role-based login).
- OR -
Select the category **Entitlements | Unix groups** (role-based login).
2. Select the group in the result list.
3. Select **Add to IT Shop** in the task view.
4. Assign the IT Shop shelf in **Add assignments**.
5. Save the changes.

For more detailed information about request from company resources through the IT Shop, see the One Identity Manager IT Shop Administration Guide.

Related Topics

- [General Master Data for an Unix Group](#) on page 99
- [Removing a Unix Group from an IT Shop Shelf](#) on page 105
- [Removing a Unix Group from all IT Shop Shelves](#) on page 106

Removing a Unix Group from an IT Shop Shelf

To remove a group from individual IT Shop shelves

1. Select the category **Unix | Groups** (non role-based login).
- OR -
Select the category **Entitlements | Unix groups** (role-based login).
2. Select the group in the result list.
3. Select **Add to IT Shop** in the task view.
4. Remove the group from the IT Shop shelves in **Remove assignments**.
5. Save the changes.

Removing a Unix Group from all IT Shop Shelves

To remove a group from all IT Shop shelves

1. Select the category **Unix | Groups** (non role-based login).
- OR -
Select the category **Entitlements | Unix groups** (role-based login).
2. Select the group in the result list.
3. Select **Remove from all shelves (IT Shop)** in the task view.
4. Confirm the security prompt with **Yes**.
5. Click **OK**.

The group is removed from all shelves by the One Identity Manager Service. All requests and assignment requests with this group are canceled in the process.

Additional Tasks for Managing Unix Groups

After you have entered the master data, you can apply different tasks to it. The task view contains different forms with which you can run the following tasks.

Overview of Unix Groups

Use this task to obtain an overview of the most important information about a group.

To obtain an overview of a group

1. Select the category **Unix | Groups**.
2. Select the group in the result list.
3. Select **Unix group overview** in the task view.

Adding Unix Groups to Unix Groups

Use this task to add a group to another group.

To assign groups directly to a group

1. Select the category **Unix | Groups**.
2. Select the group in the result list.
3. Select **Assign groups** in the task view.
4. Assign child groups of the selected group in **Add assignments**.
- OR -
Remove assignments to groups in **Remove assignments**.
5. Save the changes.

Effectiveness of Group Memberships

Table 36: Configuration Parameter for Conditional Inheritance

| Configuration parameter | Active Meaning |
|--|---|
| QER\Structures\Inherite\GroupExclusion | Preprocessor relevant configuration parameter for controlling effectiveness of group memberships. If the parameter is set, memberships can be reduced on the basis of exclusion definitions. The database has to be recompiled after changes have been made to the parameter. |

When groups are assigned to user accounts an employee may obtain two or more groups, which are not permitted in this combination. To prevent this, you can declare mutually exclusive groups. To do this, you specify which of the two groups should apply to the user accounts if both are assigned.

It is possible to assign an excluded group directly, indirectly or by IT Shop request at any time. One Identity Manager determines whether the assignment is effective.

NOTE:

- You cannot define a pair of mutually exclusive groups. That means, the definition "Group A excludes group B" AND "Group B excludes groups A" is not permitted.
- You must declare each group to be excluded from a group separately. Exclusion definitions cannot be inherited.
- One Identity Manager does not check whether membership of an excluded group is permitted in another group.

The effect of the assignments is mapped in the tables UNXAccountInUNIXGroup and BaseTreeHasUNIXGroup through the column XIsInEffect.

Example of the effect of group memberships

- Group A is defined with permissions for triggering requests in a host. A group B is authorized to make payments. A group C is authorized to check invoices.
- Group A is assigned through the department "Marketing", group B through "Finance" and group C through the business role "Control group".

Clara Harris has a user account in this host. She primarily belongs to the department "marketing". The business role "Control group" and the department "Finance" are assigned to her secondarily. Without an exclusion definition, the user account obtains all the permissions of groups A, B and C.

By using suitable controls, you want to prevent an employee from being able to trigger a request and to pay invoices. That means, groups A, B and C are mutually exclusive. An employee that checks invoices may not be able to make invoice payments as well. That means, groups B and C are mutually exclusive.

Table 37: Specifying excluded groups (table UNXGroupExclusion)

| Effective Group | Excluded Group |
|-----------------|----------------|
| Group A | |
| Group B | Group A |
| Group C | Group B |

Table 38: Effective Assignments

| Employee | Member in Role | Effective Group |
|--------------|-----------------------------------|------------------|
| Ben King | Marketing | Group A |
| Jan Bloggs | Marketing, finance | Group B |
| Clara Harris | Marketing, finance, control group | Group C |
| Jenny Basset | Marketing, control group | Group A, Group C |

Only the group C assignment is in effect for Clara Harris. It is published in the target system. If Clara Harris leaves the business role "control group" at a later date, group B also takes effect.

The groups A and C are in effect for Jenny Basset because the groups are not defined as mutually exclusive. That means that the employee is authorized to trigger request and to check invoices. If this should not be allowed, define further exclusion for group C.

Table 39: Excluded groups and effective assignments

| Employee | Member in Role | Assigned Group | Excluded Group | Effective Group |
|-----------------|-----------------------|-----------------------|-----------------------|------------------------|
| Jenny Basset | Marketing | Group A | | Group C |
| | Control group | Group C | Group B Group A | |

Prerequisites

- The configuration parameter "QER\Inherit\GroupExclusion" is enabled.
- Mutually exclusive groups belong to the same host.

To exclude a group

1. Select the category **Unix | Groups**.
2. Select a group in the result list.
3. Select **Exclude groups** in the task view.
4. Assign the groups that are mutually exclusive to the selected group in **Add assignments**.
- OR -
Remove the conflicting groups that are no longer mutually exclusive in **Remove assignments**.
5. Save the changes.

Unix Group Inheritance Based on Categories

In One Identity Manager, groups can be selectively inherited by user accounts. For this, groups and user accounts are divided into categories. The categories can be freely selected and are specified by a template. Each category is given a specific position within the template. The template contains two tables; the user account table and the group table. Use the user account table to specify categories for target system dependent user accounts. Enter your categories for the target system dependent groups, administrative roles, subscriptions and disabled service plans in the . Each table contains the category items "Position1" to "Position31".


Every user account can be assigned to one or more categories. Each group can also be assigned to one or more categories. The group is inherited by the user account when at least one user account category item matches an assigned group. The group is also inherited by the user account if the group or the user account is not put into categories.

- NOTE:** Inheritance through categories is only taken into account when groups are assigned indirectly through hierarchical roles. Categories are not taken into account when groups are directly assigned to user accounts.

Table 40: Category Examples

| Category Position | Categories for User Accounts | Categories for Groups |
|-------------------|------------------------------|----------------------------------|
| 1 | Default user | Default permissions |
| 2 | System user | System user permissions |
| 3 | System administrator | System administrator permissions |

Figure 2: Example of inheriting through categories.



To use inheritance through categories

- Define the categories in the host environment.
- Assign categories to user accounts through their master data.
- Assign categories to groups through their master data.

Related Topics

- [Specifying Categories for Inheriting Permissions](#) on page 72
- [General Master Data of a Unix User Account](#) on page 81
- [General Master Data for an Unix Group](#) on page 99

Assigning Extended Properties to an Unix Group

Extended properties are meta objects that cannot be mapped directly in the One Identity Manager, for example, operating codes, cost codes or cost accounting areas.


To specify extended properties for a group

1. Select the category **Unix | Groups**.
2. Select the group in the result list.
3. Select **Assign extended properties** in the task view.
4. Assign extended properties in **Add assignments**.
- OR -
Remove extended properties from **Remove assignments**.
5. Save the changes.

For more detailed information about using extended properties, see the One Identity Manager Identity Management Base Module Administration Guide.

Deleting Unix Groups

To delete a group

1. Select the category **Unix | Groups**.
2. Select the group in the result list.
3. Delete the group using .
4. Confirm the security prompt with **Yes**.

The group is deleted completely from the One Identity Manager database and from Unix.

Reports about Unix Objects

One Identity Manager makes various reports available containing information about the selected base object and its relations to other One Identity Manager database objects. The following reports are available for Unix-based target systems.

NOTE: Other sections may be available depending on the which modules are installed.

Table 41: Reports for the Target System

| Report | Description |
|--|--|
| Overview of all Assignments | This report finds all roles containing employees with at least one user account in the selected host system. |
| Show orphaned user accounts | This report shows all host's user accounts, which are not assigned to an employee. The report contains group memberships and risk assessment. |
| Show employees with multiple user accounts | This report shows all employees with more than one user account in the host. The report is a risk assessment. |
| Show unused user accounts | This report shows all user accounts in the host, which have not been used in the last few months. The report contains group memberships and risk assessment. |
| Show entitlement drifts | This report shows all host's groups that are the result of manual operations in the target system rather than using One Identity Manager. |
| Show user accounts with an above average number of system entitlements | This report contains all the host's user accounts with an above average number of group memberships. |
| Unix user account and group administration | This report contains a summary of user account and group distribution in all host systems. You can find this report in the category My One Identity Manager . |
| Data quality summary for Unix user accounts | This report contains different evaluations of user account data quality in all host systems. You can find this report in the category My One Identity Manager . |

Overview of all Assignments

The report "Overview of all Assignments" is displayed for certain objects, for example, permissions, compliance rules or roles. The report finds all the roles, for example, departments, cost centers, locations, business roles and IT Shop structures in which there are employee who own the selected base object. In this case, direct as well as indirect base object assignments are included.

Example

- If the report is created for a resource, all roles are determined in which there are employees with this resource.
- If the report is created for a group, all roles are determined in which there are employees with this group.
- If the report is created for a compliance rule, all roles are determined in which there are employees with this compliance rule.
- If the report is created for a department, all roles are determined in which employees of the selected department are also members.
- If the report is created for a business role, all roles are determined in which employees of the selected business role are also members.

To display detailed information about assignments









- To display the report, select the base object from the navigation or the result list and select the report **Overview of all assignments**.
- Use the  **Used by** button in the report's toolbar to select the role class (department, location, business role or IT Shop structure) for which you determine if roles exist in which there are employees with the selected base object.
All the roles of the selected role class are shown. The color coding of elements identifies the role in which there are employees with the selected base object. The meaning of the report control elements is explained in a separate legend. In the report's toolbar, click  to open the legend.
- Double-click a control to show all child roles belonging to the selected role.
- By clicking the  button in a role's control, you display all employees in the role with the base object.
- Use the small arrow next to  to start a wizard that allows you to bookmark this list of employee for tracking. This creates a new business role to which the employees are assigned.

Figure 3: Toolbar for Report "Overview of all assignments"



Table 42: Meaning of Icons in the Report Toolbar

| Icon | Meaning |
|---|---|
|  | Show the legend with the meaning of the report control elements |
|  | Saves the current report view as a graphic. |
|  | Selects the role class used to generate the report. |
|  | Displays all roles or only the affected roles. |

Appendix: Configuration Parameters for Managing Unix

The following configuration parameters are additionally available in One Identity Manager after the module has been installed.

Table 43: Configuration parameter

| Configuration parameter | Description |
|--|---|
| TargetSystem\Unix | Preprocessor relevant configuration parameter to control the component parts for the managing Unix-based custom target systems. If the parameter is set, the target system components are available. Changes to the parameter require recompiling the database. |
| TargetSystem\Unix\Accounts | This configuration parameter permits configuration of user account data. |
| TargetSystem\Unix\Accounts\InitialRandomPassword | This configuration parameter specifies whether a random generated password is issued when a new user account is added. The password must contain at least those character sets that are defined in the password policy. |
| TargetSystem\Unix\Accounts\InitialRandomPassword\SendTo | This configuration parameter specifies to which employee the email with the random generated password should be sent (manager cost center/department/location/role, employee's manager or XUserInserted). If no recipient can be found, the password is sent to the address stored in the configuration parameter "TargetSystem\Unix\DefaultAddress". |
| TargetSystem\Unix\Accounts\InitialRandomPassword\SendTo\MailTemplateName | This configuration parameter contains the name of the mail template sent to inform users about their initial login data (name of the user account). Use the mail template "Employee - new account |

| Configuration parameter | Description |
|--|---|
| | created". |
| TargetSystem\Unix\Accounts\ InitialRandomPassword\SendTo\ MailTemplatePassword | This configuration parameter contains the name of the mail template sent to inform users about their initial login data (initial password). Use the mail template "Employee - initial password for new user account". |
| TargetSystem\Unix\Accounts\ MailTemplateDefaultValues | This configuration parameter contains the mail template used to send notifications if default IT operating data mapping values are used for automatically creating a user account. Use the mail template "Employee - new user account with default properties created". |
| TargetSystem\Unix\Accounts\ PrivilegedAccount | This configuration parameter allows configuration of settings for privileged Unix user accounts. |
| TargetSystem\Unix\Accounts\ PrivilegedAccount\ AccountName_Postfix | This configuration parameter contains the postfix for formatting login names for privileged user accounts. |
| TargetSystem\Unix\Accounts\ PrivilegedAccount\ AccountName_Prefix | This configuration parameter contains the prefix for formatting login names for privileged user accounts. |
| TargetSystem\Unix\DefaultAddress | The configuration parameter contains the recipient's default email address for sending notifications about actions in the target system. |
| TargetSystem\Unix\ MaxFullsyncDuration | This configuration parameter contains the maximum runtime for synchronization. No recalculation of group memberships by the DBQueue Processor can take place during this time. If the maximum runtime is exceeded, group membership are recalculated. |
| TargetSystem\Unix\ PersonAutoDefault | This configuration parameter specifies the mode for automatic employee assignment for user accounts added to the database outside synchronization. |
| TargetSystem\Unix\ PersonAutoDisabledAccounts | This configuration parameters specifies whether employees are automatically assigned to disable user accounts. User accounts do not obtain an account definition. |
| TargetSystem\Unix\ PersonAutoFullSync | This configuration parameter specifies the mode for automatic employee assignment for user accounts added to or updated in the database through synchronization. |

| Configuration parameter | Description |
|---|--|
| TargetSystem\Unix\ PersonExcludeList | List of all user accounts for which automatic employee assignment should not take place. Names given in a pipe () delimited list that is handled as a regular search pattern. Example: Root |

Appendix: Default Project Template for Unix-Based Target Systems

A default project template ensures that all required information is added in the One Identity Manager. This includes mappings, workflows and the synchronization base object. If you do not use a default project template you must declare the synchronization base object in One Identity Manager yourself.

Use a default project template for initially setting up the synchronization project. For custom implementations, you can extend the synchronization project with the Synchronization Editor.

The template uses mappings for the following schema types.

Table 44: Mapping unix schema types to tables in the One Identity Manager schema.

| Schema type in Unix-based target system | Table in the One Identity Manager schema |
|--|---|
| Group | UNXGroup |
| Host | UNXHost |
| LoginShell | UNXLoginShell |
| User | UNXAccount |

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales or other inquiries, such as licensing, support, and renewals, visit <https://www.oneidentity.com/company/contact-us.aspx> or call +1-800-306-9329.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product

A

- account definition 33
 - add to IT Shop 47
 - assign automatically 45
 - assign to all employees 45
 - assign to business role 44
 - assign to cost center 44
 - assign to department 44
 - assign to employee 43, 46
 - assign to location 44
 - assign to system roles 46
 - assign to Unix host 48
 - create 34
 - delete 49
 - IT operating data 39-40
 - manage level 36
- architecture overview 7

C

- calculation schedule
 - disable 31
- configuration parameter 115

D

- direction of synchronization
 - direction target system 19, 25
 - in the Manager 19

E

- email notification 61

- employee assignment
 - automatic 91
 - manual 94
 - remove 94
 - search criteria 93
 - table column 93
- exclusion definition 107

I

- IT operating data
 - change 42
- IT Shop shelf
 - assign account definition 47

J

- Job server
 - edit 13

L

- login data 61

M

- membership
 - modify provisioning 29

N

- notification 61

O

object

- delete immediately 27
- outstanding 27
- publish 27

One Identity Manager

- administrator 8
- target system administrator 8
- target system manager 8, 63
- user 8

outstanding object 27

P

password

- initial 61

password policy 51

- assign 58
- character sets 54
- check password 58
- conversion script 55-56
- default policy 52, 58
- display name 52
- edit 52
- error message 52
- excluded list 57
- failed logins 53
- generate password 58
- initial password 53
- name components 53
- password age 53
- password cycle 53
- password length 53
- password strength 53

predefined 51

test script 55

project template 118

provisioning

members list 29

S

schema

changes 26

shrink 26

update 26

synchronization

authorizations 12

base object

create 26

configure 19, 24

connection parameter 19, 24, 26

different hosts 26

extended schema 26

prevent 31

scope 24

set up 11

start 19

synchronization project

create 16, 19

target system schema 26

user 12

variable 24

variable set 26

workflow 19, 25

synchronization analysis report 30

synchronization configuration

customize 24-26

synchronization log 23

retention period 24

- synchronization project
 - create 16, 19
 - disable 31
 - edit 73
 - project template 118
- synchronization server
 - configure 13
 - install 13
 - Job server 13
- synchronization workflow
 - create 19, 25

T

- target system synchronization 27
- template
 - IT operating data, modify 42

U

- Unix group
 - add to IT Shop 104
 - add to system role 104
 - assign extended properties 111
 - assign group 106
 - assign to business role 102
 - assign to cost center 101
 - assign to department 101
 - assign to location 101
 - assign user account 90, 100, 103
 - category 99, 109
 - delete 111
 - edit 99
 - effective 107
 - exclusion 107
 - group ID 99

- host 99
- primary group 70, 81
- remove from IT Shop 105-106
- risk index 99
- service item 99
- Unix host 73
 - account definition 70
 - account definition (initial) 48
 - AIX system 70
 - application roles 8
 - category 72, 109
 - employee assignment 93
 - overview of all assignments 113
 - primary group 70
 - report 112
 - set up 70
 - synchronization 70
 - target system manager 8, 63, 70
- Unix login shell 73
- Unix user account
 - account definition 48, 81
 - administrative user account 78
 - assign employee 75, 80-81, 91
 - assign extended properties 91
 - assign group 90, 103
 - category 81, 109
 - comment (Gecos) 81
 - default user accounts 77
 - delete 97
 - disable (AIX system) 96
 - EFS (AIX system) 88
 - employee 81
 - encrypted file system (AIX system) 88
 - group ID 81

- groups can be inherited 39
- home directory 81
- host 81
- identity 39, 76, 81
- inherit group 81
- limits (AIX system) 84
- lock 97
- login shell 39, 81
- manage level 81, 90
- password 81
 - initial 60
- password data (AIX system) 85
- primary group 70, 81
- privileged user account 39, 79, 81
- restore 97
- risk index 81
- security (AIX system) 87
- set up 80
- type 76
- user account UID 81
- user name 81

user account

- administrative user account 78
- apply template 42
- default user accounts 77
- identity 76
- password
 - notification 61
- privileged user account 79
- type 76