



One Identity Manager 8.1.4

Process Monitoring and Troubleshooting Guide

Copyright 2020 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC .

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.
Attn: LEGAL Dept
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our Web site (<http://www.OneIdentity.com>) for regional and international office information.


Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal. All other trademarks are the property of their respective owners.

Legend

 **WARNING: A WARNING icon highlights a potential risk of bodily injury or property damage, for which industry-standard safety precautions are advised. This icon is often associated with electrical hazards related to hardware.**

 **CAUTION: A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.**

Contents

About this guide	5
Monitoring handling of processes	6
Working with the Job Queue Info program	6
Views in the Job Queue Info	7
Updating the views	8
Changing the column configuration in the Job Queue Info program	8
Changing program settings in the Job Queue Info	9
Creating and using custom filters in the Job queue	10
Monitoring how processes are run	11
Details about process handling	12
Details about process step handling	13
Details of the process step parameters	14
OUT parameters	15
Hidden parameters	15
Re-enabling process steps and processes	16
Enabling and disabling extended logging of process steps	17
Determining Job server and web server status	18
Displaying DBQueue processing	19
Displaying Job queue progress	20
Emergency stop	20
Support for error localization in One Identity Manager	22
Overview of the system configuration and transport history	22
Displaying error messages in the One Identity Manager tools	23
The error message window in One Identity Manager tools	23
Displaying error log messages	25
Displaying system journal messages	28
Displaying the One Identity Manager Service log file	30
One Identity Manager application server status	31
Which authentication module is the current user using?	31
Which system user is the current user using?	32
Which permissions apply to the current user?	33

Which program functions are available to the current user?	34
Which permissions level does the user use?	34
Configuring logs in One Identity Manager	36
Configuring the retention periods of messages in the system journal	36
Recording process handling errors in the system journal	38
Recording logins and logoffs in the system journal	38
Global configuration of logging with NLog	39
Logging the One Identity Manager components	41
Configuring One Identity Manager Service logging	42
Prerequisites for displaying the log file	42
Configuring the log file	43
Authentication method for displaying the log file	45
Advanced logging in the One Identity Manager Service	45
Extended debugging in One Identity Manager Service	46
Outputting custom messages in the One Identity Manager Service log file	46
Recording messages in the event view	47
HTTPLogPlugins log file	48
Output of extended return values from individual process components	49
Configuring notification behavior for DBQueue Processor initialization	50
Enabling the crash recorder	50
Appendix: One Identity Manager configuration files	52
Application-specific configuration files	52
Global configuration file for One Identity Manager tools	54
About us	55
Contacting us	55
Technical support resources	55
Index	56

About this guide

One Identity Manager describes the various methods of monitoring processing and of localizing errors in *One Identity Manager Process Monitoring and Troubleshooting Guide*. It also explains advanced log configuration in One Identity Manager.

It is assumed that you understand the concept and the architecture of One Identity Manager. It is also assumed that you are thoroughly familiar with the One Identity Manager tools.

You can find additional notes about error localization and troubleshooting in the other One Identity Manager guides.

Available documentation

You can access One Identity Manager documentation in the Manager and in the Designer by selecting the **Help | Search** menu item. The online version of One Identity Manager documentation is available in the Support portal under [Technical Documentation](#). You will find videos with additional information at www.YouTube.com/OneIdentity.

Detailed information about this topic

- [Monitoring handling of processes](#) on page 6
- [Support for error localization in One Identity Manager](#) on page 22
- [Configuring logs in One Identity Manager](#) on page 36

Monitoring handling of processes

The Job Queue Info program helps you check the current status of the services running in the One Identity Manager network. It enables a detailed and comprehensive overview of the requests in the Job queue and various One Identity Manager Service requests on the servers. This program makes it easier to work with processes, supplies status information during run-time and allows errors to be quickly recognized and debugged.

Detailed information about this topic

- [Monitoring how processes are run on page 11](#)
- [Details about process handling on page 12](#)
- [Details about process step handling on page 13](#)
- [Details of the process step parameters on page 14](#)
- [Re-enabling process steps and processes on page 16](#)
- [Enabling and disabling extended logging of process steps on page 17](#)
- [Determining Job server and web server status on page 18](#)
- [Displaying DBQueue processing on page 19](#)
- [Displaying Job queue progress on page 20](#)
- [Emergency stop on page 20](#)

Working with the Job Queue Info program

The Job Queue Info program has several views for the layout of processes and process steps in the Job queue. In the Job Queue Info program, you can:

- Monitor handling of Job queue processes.
- Monitor processing of the DBQueue.
- Monitor the status of the Job server and web server.

- Display the One Identity Manager Service log file.
- Display the system journal.

Views in the Job Queue Info

The Job Queue Info has several views for displaying and editing processes and process steps in the Job queue.

Table 1: Job Queue Info views

View	Description
Job queue	This view shows the contents of the Job queue grouped by processes. In the first level of the hierarchy, all the processes are shown with a process count. If a process node is opened, all the processes are shown with start times. The complete process with its hierarchy is displayed under a process node. Each process step contains its success and failure branches as sub elements.
Job server	This view shows the Job queue contents sorted by executing servers. At the first hierarchy level, all Job servers are displayed, with their counts of the different processes, that exist in the Job queue for the Job server. If a Job server node is opened, the process tasks are listed and the number of process step per process task is shown. The process steps are listed by start time under the process task node.
Process History	The shows the contents of the JobHistory table. The course of the process execution is displayed by sorted processes. You can limit the list of processes in the process history to only processes with errors in the program settings. If you select a failed process step, the entire error message is shown in a tooltip.
Base objects	The process history entries and the current job queue entries are summarized here in this view for the object being processed. If an error occurs during processing and the processing of the process is stopped (Frozen or Overlimit status), you can analyze the previous processing sequence in this view. Once all processes have been successfully handled for this object the error messages are removed from the view.
Process	This view gives an overview of how process steps are linked within a process. In this way, the execution sequence of individual process steps for large processes can be monitored better. After selecting a process, all its process steps are displayed.
Process step	In this view detailed information is displayed for each process step. The view shows the data structure for a process step at compilation time. After selecting a process step, specific information from the Job queue is mapped as well as each parameter of the selected process step with its values.

View	Description
Parameters	After selecting a process step, the passing parameters of the process step are displayed with their names and their values. If the selected node does not represent a process step, the parameter view is cleared.
Affected objects	This view shows all objects that are affected by a process step.
Progress	This view displays the number of entries in the Job queue is queried. The current value is represented by a number and inserted, at the same time, into a bar graph. The process step progress state is shown in different colors.
Server state	This view gives you a faster overview of all the Job servers and Web servers available in the network.
DBQueue	Calculation tasks in the DialogDBQueue table used for DBQueue Processor processing are displayed in this view. The number, sort order and name of the queued requests are displayed.
System journal	Displays entries in the system journal.

Updating the views

To update the views in Job Queue Info, choose **F5**. If the view focus is on a base object then the whole display is updated and the hierarchy tree is closed. This update refreshes the contents of all views. This update also refreshes the contents of other views.

The views can only ever display a snap-shot of the queue because the contents of the job queue is continually changing. Therefore, when a node is opened or the view is updated, the necessary information may have already been deleted from the job queue. If this is the case, the corresponding entry in the hierarchical display is deleted or the corresponding element is not shown.

Changing the column configuration in the Job Queue Info program

In some of the program views, you can specify which columns are to be displayed.

To specify which columns to display

- Select a node in the hierarchical display and select **Configure columns** from the context menu.

Select the columns you want to display by moving through the list and accepting with the arrow buttons, then change the order in which they are displayed.

To change the width of the columns on display

- Double-click a column boundary to optimize the column width.
- Use **Shift + double-click** for a column boundary to optimize the width of all columns.

Changing program settings in the Job Queue Info

To change the program settings

- In the Job Queue Info, select the **Database | Settings** menu.

Table 2: Program settings

Setting	Meaning
Language	Language for formatting data, such as data formats, time formats or number formats.
Other user interface language	Language for the user interface. The initial program login uses the system language for the user interface. Changes to the language settings take effect after the program has been restarted. The language is set globally for all One Identity Manager programs, which means the language setting does not have to be configured for each program individually.
Result limit	Number of entries to load and display for processes or process steps.
Polling interval	Specifies the number of seconds between data requests. The views are updated at the end of every interval. If the value is 0, the views are not updated. In this case, use F5 to update.
HTTP port of the Job server	HTTP port at which the One Identity Manager Service operates for polling the server state of the Job server. The default value is port 1880.
Status query timeout (s)	Maximum delay for status queries. Job servers that do not respond within this time limit are considered unavailable.
Only show process errors	Limits the process history display to processes with errors. The setting does not effect how the process history is recorded, only how it is displayed.

Creating and using custom filters in the Job queue

Use custom filters if you frequently run specific search queries in the Job queue (JobQueue table).

To create custom filters

1. Select the **Filter | Define filter** menu item.
2. In the **Filer method** pane, select the filter method you want to use. Custom filters allow you to run the following searches:
 - **Wildcard:** Search for a string using wildcards.
 - **SQL:** Search for entries with a SQL condition.
3. In the **Filter parameter** pane, define the search pattern.
 - Enter the search pattern for the **Wildcard** filter method. Use of wildcards * in the search pattern is permitted.
Example:
Pattern* - searches for all entries whose display value starts with the "Pattern" string
*Pattern - searches for all entries whose display value ends with the "Pattern" string
Pattern - searches for all entries whose display value contains the "Pattern" string
Pattern - searches for all entries whose display value matches the "Pattern" string
 - Enter a condition for the **SQL** filter method. Enter the condition as a valid database query WHERE clause. You can enter the database queries as a SQL query directly or compile the database queries with a wizard. Use the **Expert view** or **Simple view** button to switch to the appropriate view.
4. To save the filter, enter a name and a description for the search filter in the **Save filter** pane and click **Save**.
5. To apply a filter, click **Filter**.

To use a saved filter in the Job Queue Info

1. In the Job Queue Info, select the **Filter | Define filter** menu item.
2. Double-click the search filter in the **Saved filters** pane.
3. Click **Filter**.

Monitoring how processes are run

To monitor process information

- In the Job Queue Info, in the **Job queue** view or the **Base objects** view, select a process and select the **Monitor process** context menu entry.

The process information is updated regularly.

TIP: To monitor the complete job queue, select the **Monitor job queue** context menu in the **Job queues** view.

The context menu entry is only available if the logged-in user has the **Option to monitor the Job queue in Job Queue Info** (JobQueue_Monitor) program function.

In order to improve the overview, the execution progress of a process step is mirrored in the color of the text.

Table 3: Job queue display - meaning of the colors

Color	Meaning	Progress state
Orange	This process step is being processed.	Processing
Yellow	This process step is loaded for processing.	Loaded
Green	This process step is ready for processing.	True
Blue	This process step has already been processed.	Finished
Black	This process step is not ready for processing.	False
Red	The process step being dealt with cannot be processed. You can re-enable process steps with Frozen status and therefore set them again for processing. The error message is shown in a tooltip.	Frozen
Purple	The process step being dealt with cannot be processed. You can re-enable process steps with Overlimit status and therefore set them again for processing. The error message is shown in a tooltip.	Overlimit
Light purple	The process step cannot be found.	Missing

TIP:

- Use **Ctrl + F2** you can mark individual process steps with a bookmark. Use **F2** or **Shift + F2** to switch between the selected process steps.
- To display the objects affected by a process step, use the **Affected objects** view.

Related topics

- [Re-enabling process steps and processes](#) on page 16

Details about process handling


This view gives an overview of how process steps are linked within a process. In this way, the execution sequence of individual process steps for large processes can be monitored better.

To display details of the process handling

- In Job Queue Info, select a process and select the **View | Process** menu item.
All the process steps of the selected process are displayed.

The process step and its properties are displayed through a special control element. The process step name is displayed in the control's header. The progress state of the process step is clarified by the use of a color icon (●). All other entries represent the parameters for this process step. You can hide or show the parameter list by clicking on the **▼ ▲** icons in the header of the control element.

Figure 1: The process view



Each control element entry has a tooltip.

The process step's tooltip displays the following information:

- Name of the executing queue
- Name of the process component
- Name of the process task name
- Progress state

- Start time of the process step
- Error Message

A parameter's tooltip show the following information:

- Parameter name
- Parameter value

Table 4: Displaying process's process steps - meaning of the colors

Color	Meaning	Progress state
Orange	This process step is being processed.	Processing
Yellow	This process step is loaded for processing.	Loaded
Green	This process step is ready for processing.	True
Blue	This process step has already been processed.	Finished
Black	This process step is not ready for processing.	False
Red	The process step being dealt with cannot be processed. You can re-enable process steps that have Frozen or Overlimit status and therefore queue them again for processing.	Frozen/Overlimit/unknown

Details about process step handling

In this view detailed information is displayed for each process step. The view shows the data structure for a process step at compilation time. After selecting a process step, specific information from the Job queue is mapped as well as each parameter of the selected process step with its values.




To display details of the process step handling

- In Job Queue Info, select a process step and select the **View | Process step** menu.

Figure 2: Process step view

Process step	
UID_Job	0A4349C3-454A-46F7-BD32-02386291
BasisObjectKey	
ComponentAssembly	HandleObjectComponent
ComponentClass	VI.JobService.JobComponents.Hand
DeferOnError	False
ErrorNotify	False
ErrorMessages	
ExecutionType	INTERNAL
GenProcID	7BA8D4CF-568F-4EF0-8FBB-E01E587
IgnoreErrors	False
IsRootJob	True
IsSplitOnly	False
IsToFreezeOnError	False
JobChainName	Proc: vid_InsertForHandleObject Obj
LimitationCount	0
MaxInstance	0
MinutesToDefer	0
NotifyAddress	
NotifyAddressSuccess	
NotifyBody	
NotifyBodySuccess	

Table 5: Process step view - meaning of icons

Icon	Meaning
	Selection of a process step and its parameters.
	Displays a column from the Jobqueue table and the value.
	Displays a process step parameter and the value.

TIP: You can copy the data currently selected in the view into the clipboard by pressing **Ctrl + C**. The data format is column name value.

Details of the process step parameters

After selecting a process step, the passing parameters of the process step are displayed with their names and their values. If the selected node does not represent a process step, the parameter view is cleared.

To display process step parameters

- In the Job Queue Info, select a process step and select the **View | Parameter** menu.

TIP: You can copy the data currently selected in the view into the clipboard using **Ctrl + C**. The data format is column name value.

OUT parameters

Parameters of the **OUT** or **INOUT** type are parameters that a process component can use to output a value. This value is then available in all subsequent process steps in the process and can be used as a value for parameters of the **IN** type.

The Job Queue Info program is not technically capable of determining the point at which or for which process step these parameters are valid. For this reason, OUT parameters are added to the list of parameters of a process step and are highlighted in blue.

They cannot be seen in the view of the process step under <ParamIN> of a process step because this view presents the data structure of every process step at compilation time. However, the OUT parameters are created in the context of the process.

The time at which the process is loaded into the Job Queue Info is important. If a parameter is overwritten several times, only the state at the time of data query is displayed.

Example

Step 1	OUT parameter: X=1
Step 2	IN parameter: X=1
	Value changes: X=2
	OUT parameter: X=2
Step 3	IN parameter: X=2

If the process is loaded into the Job Queue Info before step 2 is processed, the Job Queue Info displays the **X=1** value for the OUT parameter. If the process is loaded after step 2 is processed, the **X=2** value is displayed for the OUT parameter.

For more information about each process step and how the parameters are filled, see the One Identity Manager Service log file.

Related topics

- [Displaying the One Identity Manager Service log file](#) on page 30
- [Output of extended return values from individual process components](#) on page 49

Hidden parameters

Parameters in the One Identity Manager Service log file and in the Job Queue Info program that are not to be displayed are labeled with the **Hidden** option. Values for hidden

parameters are shown as <HIDDEN>.

The following users can view hidden parameters in Job Queue Info.

- Administrative users
- Users with the **Option to see the values of hidden parameters in Job Queue Info** program function (JobQueue_ShowHiddenParameters)

Assign the appropriate permissions group to the program function.

Related topics

- [Which program functions are available to the current user?](#) on page 34

Re-enabling process steps and processes

The maximum number of times a process can appear in the Job queue can be limited in order to prevent mass modifications.

If the limit is exceeded, the process steps are set to **Overlimit** status and are therefore no longer collected for processing. You can re-enable these process steps for execution.

Critical process steps that have failed to be processed are given **Frozen** status. You can also re-enable these processes after correcting the error.

To re-enable process steps

- Select the process step in the Job Queue Info and select the **Re-enable process step** context menu item.

NOTE: Use **Shift + select** or **Ctrl + select** to select and re-enable multiple process steps.

To re-enable a process step

- Select the process in the Job Queue Info and select the **Restart process** context menu item.

IMPORTANT: When you restart a process, all process steps are processed again. All previously handled processes up to the point at which the error occurred are run again. This can lead to data inconsistencies in certain circumstances.

Sometimes a rerun of the failed process step is not desired. This might occur when the action to be carried out by the process has been carried out manually, for example, an expected directory has been manually added in the meantime. Even so, it may just happen that the process should be rerun even though the error has not been fixed, for example, for a rollback of already processed steps. In this case, to continue with the process, the next process step in the success or failure branch can be handled.

To run the subsequent process step

- Select the failed process step and select the **End with success** or the **End with error** context menu item.

NOTE:

- Both context menu entries are only viewable if there is an error/success successor and the process step has the **Frozen** status.
- Use **Shift+ select** or **Ctrl + select** to select multiple process steps and start further processing.

Enabling and disabling extended logging of process steps

Success and error messages from process handling are written to the One Identity Manager Service log file. In order to test your processes, you can enable logging mode for process steps in the Job Queue Info. In this case, the processing messages of the processing step are written along with the **Debug** level of information into a separate log. You can display the log in the Job Queue Info as well as in the log file of the One Identity Manager Service itself.

NOTE: The log mode is only available if the logged in user has usage permissions for the program function **Option to selectively set the logging mode of process steps in the Job queue in Job Queue Info** (JobQueue_LogMode).

To enable process step logging mode

- To log the messages on success and on failure, select the process step in the **Job queue** view in Job Queue Info and select the **Execution log | Create always** context menu.
- To log the messages on failure only, in the Job Queue Info, select the process step in the **Job queue** view and select the **Execution log | On Error** context menu item.

NOTE: You can set the log mode by default for separate process steps. To do this, edit the process step in the Designer in Process Editor. For detailed information about editing processes and process steps, see the *One Identity Manager Configuration Guide*.

To display the log in Job Queue Info

- In the **Job queues** view in Job Queue Info, select the process step and select the **Execution log | Display** context menu.

This displays the log in a separate window. If a process step was executed more than once, for example, if it is re-enabled more than once, several logs are displayed.

To display the log in the One Identity Manager Service log file

- In the Job Queue Info, select the **Server status** view on the **Job server** tab and select the **Show in browser** context menu item.
- The log is marked with a link entry Log written to Job_<UID_Job>_<yyyymmdd>_<Timestamp>.log. Click the link to display the log.

The files are stored in the One Identity Manager Service log directory.

Repository structure:

```
<Log directory>\JobLogs\<First 4 digits of the UID_Job>\Job_<UID_Job>_<yyyymmdd>_<Timestamp>.log
```

To end log mode

- in Job Queue Info, in the **Job queue** view, select the process step and select the **Execution log | Disable** context menu item.

Related topics

- [Displaying the One Identity Manager Service log file](#) on page 30
- [Which program functions are available to the current user?](#) on page 34

Determining Job server and web server status

This view gives you a faster overview of all the Job servers and Web servers available in the network.

NOTE: Set the HTTP port to be queried and the maximum response time in the program settings.

One Identity Manager Service configurations of each Job server stored in the database are used to get more detailed results of Job server status queries. This is especially required if the HTTP server port has been set individually or a Job server processes several queues.

NOTE: In the Designer, configure and enable the **Get configuration file from the Job server and write in the Job server configuration** schedule to import the One Identity Manager Service configuration of the Job server into the database. For more detailed information, see the *One Identity Manager Configuration Guide*.

To query the status of all the existing Job servers in the database

- In the Job Queue Info, open the **View | Server status** view, select the **Job server** tab and press **F5**.

To query the status of a single Job server

1. In the Job Queue Info, select the **View | Server state** menu item.
2. On the **Job server** tab, select the Job server and then the **Get status** context menu item.

NOTE: Use the **Enter credentials** context menu item to enter a user and password to request the server status. The user information is retained until the server lists are reloaded or until the next time the Job Queue Info program is started.

If the server responds, the system time, the One Identity Manager Service version and the One Identity Manager Service account name are determined and displayed. The software update status as well as the current version of the software are also displayed.

TIP: Use **Refresh server list** or **F6** to reload the list of servers.

To display a Job server's services

1. In the Job Queue Info, select the **View | Server state** menu item.
2. On the **Job server** tab, select the Job server and select the **Show in browser** context menu item.

The One Identity Manager Service HTTP server for the Job server is queried and the varying One Identity Manager Service services are displayed.

To show the status of a web server

1. In the Job Queue Info, select the **View | Server status** menu item.
2. On the **Web server** tab, select the web server and select the **Show in browser** context menu item.

TIP: Use **Refresh server list** or **F6** to reload the list of servers.

Related topics

- [Changing program settings in the Job Queue Info](#) on page 9
- [Prerequisites for displaying the log file](#) on page 42

Displaying DBQueue processing

Within One Identity Manager, changes to inheritance-relevant data, such as changes to assignments or changes to specific system data, such as changes to the user interface for a system user, necessitate recalculation of the resulting data. These calculations are queued in the DBQueue and processed by the DBQueue Processor.

To display DBQueue entries

- In the Job Queue Info, select the **View | DBQueue** menu.

Calculation tasks in the DialogDBQueue table used for DBQueue Processor processing are displayed in this view. The number, sort order and name of the queued requests are displayed. The display is updated at fixed time intervals of 2 seconds.

Displaying Job queue progress

NOTE: A queue is initialized when the One Identity Manager Service starts. The One Identity Manager Service queries the Job queue to see which processes are waiting for its own queue. During the initialization phase, no processes are handled and it may take a long time, particularly if the Job queue is very full.

In the Job Queue Info, in the **Progress** view, a warning shows you the queue being initialized. Click the message to get more detail.

To display the Job queue sequence

- In the Job Queue Info, select the **View | Progress** menu.

This queries the number of entries in the Job queue. The current value is represented by a number and inserted, at the same time, into a bar graph. The process step progress state is shown in different colors. The display is updated every 5 seconds. The tooltip shows the timestamp and the number of process steps in the Job queue at this point.

Table 6: Progress view - meaning of the colors

Color	Meaning	Progress state
Black	Number of process steps that are not read for processing.	False
Green	Number of process steps ready for processing.	True
Yellow	Number of process steps loaded for processing.	Loaded
Blue	Number of process step that have completed processing	Finished
Red	Number of process steps with an unknown progress state	Frozen/Overlimit/Missing

Emergency stop

In certain circumstances, situations can occur in the system that require processing by One Identity Manager Service and processing of tasks by the DBQueue Processor to be stopped. For example, changes in One Identity Manager can sometimes cause the system to become overloaded by making mass entries in the job queue or the DBQueue.

To analyze this situation and to take the necessary steps to solve the problem where necessary, in the Job Queue Info program, you can stop the system and restart it once the problem has been fixed.

To temporarily halt process handling of a single Job server

1. In the Job Queue Info program, select the **View | Server state** menu item.
2. On the **Job server** tab, select the Job server and select the **Stop processing** context menu item.

NOTE: After solving the problem, you can use the **Start processing** context menu item to restart processing.

To stop processing entirely



1. In the Job Queue Info, select **Help | Emergency stop**.
2. To stop DBQueue processing, click the **DBQueue Processor** button.
From this point on no new calculations are carried out in the database.
NOTE: After the problem is eliminated, you can click the button to restart DBQueue Processor.
3. Click the **One Identity Manager Service** button to stop collection of process steps for every One Identity Manager Service.

Process steps that have already been collected are still processed but no new process step are sent to the services.

NOTE: After the problem is eliminated, you can click the button to restart the running of services.

The following icons are displayed in the status bar of all administration tools to inform the user that DBQueue Processor processing and services have been stopped.

Table 7: Special icon in the status bar for system stop

Icon	Meaning
	The DBQueue Processor has been stopped.
	The server services have been stopped.

Support for error localization in One Identity Manager

At this point, the various possibilities for error localization within the One Identity Manager are explained.

Detailed information about this topic

- [Overview of the system configuration and transport history](#) on page 22
- [Displaying error messages in the One Identity Manager tools](#) on page 23
- [Displaying the One Identity Manager Service log file](#) on page 30
- [One Identity Manager application server status](#) on page 31
- [Which authentication module is the current user using?](#) on page 31
- [Which system user is the current user using?](#) on page 32
- [Which permissions apply to the current user?](#) on page 33
- [Which program functions are available to the current user?](#) on page 34
- [Which permissions level does the user use?](#) on page 34

Overview of the system configuration and transport history

To obtain an overview of the system configuration

- Start the Designer or the Manager and select the **Help | Info** menu item.
The **System information** tab provides an overview of your current system administration and the installed modules with their versions.

IMPORTANT: You will need to provide this information if you contact the Support Team.

NOTE: If you have enabled vendor notification, this report is sent once a month to One Identity.

During a schema installation or schema update using the Configuration Wizard, the migration date and migration version are recorded in the database transport history.

When you import a transport package with the Database Transporter, the import date and description, the database version, and the transport package name are recorded in the transport history of the target database.

To display transport history

- Start the Designer and select the **Help | Transport history** menu item.

Displaying error messages in the One Identity Manager tools

The One Identity Manager tools offer various possible ways to display error messages.


Detailed information about this topic

- [The error message window in One Identity Manager tools](#) on page 23
- [Displaying error log messages](#) on page 25
- [Displaying system journal messages](#) on page 28

The error message window in One Identity Manager tools

Error messages for the One Identity Manager tools are shown in a separate window. In addition, a more detailed description of the error is displayed.

Figure 3: Error message window



- To send the messages, click on the **Send as mail** button.
This creates a new email message in the default mail program and copies over the error text.
- To copy the messages to the clipboard, open the context menu for the **Send as mail** button and click on **Copy to clipboard**.
- To record the steps taken that gave the error, start the Windows Steps Recorder.
 - Open the context menu for the **Send as mail** button and click on **Create problem report**.
 - Confirm the security prompt with **OK**.

You can now start recording the individual steps. Detailed information about recording the steps taken to reproduce a problem using the Windows Steps Recorder can be found in the [Microsoft documentation](#).

Configure the amount of information to be displayed using the options in the error message window.

To change options


- Open the configuration view for the error messages window with the  button and enable or disable the options you want.

Table 8: Options for displaying error messages


Option	Meaning
Show previous errors	Specifies whether all previous errors that lead to the current error, should also be shown.
Show One Identity error numbers	Specifies whether internal error numbers are shown.
Show error positions	Specifies whether error position are also shown in the program code.
Wrap long lines	Specifies whether long error messages are wrapped.
Show only user relevant	Specifies whether all error messages are to be displayed or only those error messages that are classified as user-relevant.
Show asynchronous calls	Specifies whether error messages in asynchronous method calls are shown.
Show crash report	Specifies whether error messages from the crash recorder are shown.

Related topics


- [Enabling the crash recorder](#) on page 50


Displaying error log messages

A program's error log, as in the Manager for example, collects all the messages, such as error messages and warnings, that have occurred since the program started. The error log is reinitialized when the program is restarted.

NOTE: In the Manager, the  icon in the program's status bar indicates new messages in the error log. Double-click the icon to open the error log.

To display items from the Manager error log

1. In the Manager, select the **View | Error log** menu item.
2. Enable the  view in the error log toolbar.

You can configure how the messages are displayed in the error log. To do this, switch the error log to advanced mode by clicking  on the right of the column headers. Here you have the possibility to debug individual actions.

TIP: You can apply different filters to limit the information being displayed. Click the

arrow in the column header and select a filter. The  icon in the log toolbar shows whether a filter is active.

Figure 4: Simple error log (above) and advanced error log (below)






















Table 9: Meaning of icons in the error log

Icon	Meaning
	Logs all critical error messages. (Severity level = Fatal)
	Logs all information. (Severity level = Info)
	Logs all warnings. (Severity level = Warning)
	Logs all error messages. (Severity level = error)
	Logs debugger output. This setting should only be used for testing. (Severity level = Debug)
	Logs highly detailed information. This setting should only be used for analysis purposes. The log file quickly becomes large and cumbersome. (Severity level = Trace)
	Adds a custom filter condition.
	Deletes filter condition.
	Searches for term.
	Searches next term.
	Marks all messages with a specific term.
Buffer size	Sets the message buffer size. The buffer's level is displayed next to the field.
	Deletes the buffer contents.
	Stops logging.
	Starts logging.
	Saves log to file.

Icon	Meaning
	Specifies which column are displayed in the error log.
	Copies selected messages to the clipboard.
	Opens the error log with a text editor.


The following information is displayed about a message. The range of information depends on the severity level of a message.

Table 10: Information about a message

Detail	Description
Severity code	Level of information supplied for the message.
Timestamp	Time and date of the log entry.
Logger name	One Identity Manager component from which the message was sent.
Message	Logged message.
Error Message	Detailed error message.
Data	Additional data about the message.
Sequence ID	Number of the line in the error log.
Stack trace	Complete stack trace for the error message.
Session ID	Session identification number. NOTE: If there is a filter set on the session ID, only the messages for this session are displayed, for example, loading collections and single objects. If the filter is not set, actions outside of the connection, such as loading of table definitions or configuration parameters, are also displayed.

TIP: Double-click a message to display detailed information.

Figure 5: Detailed information about a message




Related topics

- [Logging the One Identity Manager components](#) on page 41

Displaying system journal messages

The system journal is used to store information, warning, and error messages from different components of One Identity Manager, for example, DBQueue Processor, Configuration Wizard, or One Identity Manager Service. Actions in the Job Queue Info program, such as reactivating process steps, are also recorded in the system journal.

To display system journal entries in the Manager

1. In the Manager, select the **View | Error log** menu item.
2. Enable the  view in the error log toolbar.

To display system journal entries in the Job Queue Info

- In the Job Queue Info, select the **View | System journal** menu item.






TIP: You can apply different filters to limit the information being displayed. Click the arrow in the column header and select a filter. The  icon in the log toolbar shows if a filter is active.

Table 11: Displaying messages in the system journal

Icon	Meaning
	Information is written to the error log/system journal.
	A warning has been written to the system journal.
	A error has been written to the system journal.

TIP: Double-click a message to display detailed information.

Figure 6: Detailed information about a message



The following information is displayed about a message. The range of information depends on the type of message.

Table 12: Information about a message

Detail	Description
Message	Logged message.
Program	One Identity Manager component from which the message was sent.
Host	Computer from which the action was started.
Logged in system user	System user that triggered the action.
Type	Type of message. (W= Warning, I = Info, E = Error, T = Trace)
Date	Time and date of the log entry.

Related topics

- [Recording process handling errors in the system journal](#) on page 38

Displaying the One Identity Manager Service log file

You can use a browser front-end to display the One Identity Manager Service log file.

You call up the log file with the appropriate URL:

http://<server name> :<port number>


The default value is port 1880.

To open the One Identity Manager Service log file in the Job Queue Info

1. Start the Job Queue Info program.
2. In the **Server state** view, select the Job server and select the **Open in browser** context menu item.

The One Identity Manager Service HTTP server for the Job server is queried and the various One Identity Manager Service services are displayed.

Figure 7: The One Identity Manager Service log file



The messages to be displayed on the web page can be filtered interactively. There is a menu on the website for this. Only text contained in the log file can be displayed in this case. For example, if the message type is **Warning**, messages with the **Info** message type cannot also be displayed if the relevant filter is selected.

The log output is color-coded to make it easier to identify.

Table 13: Log file color code

Color	Meaning
Green	Processing successful
Yellow	Warnings occurred during processing
Red	Fatal errors occurred during processing

NOTE: If you want to retain the color information to send by email, you need to save the

| complete web page.

Related topics

- [Configuring One Identity Manager Service logging](#) on page 42
- [Prerequisites for displaying the log file](#) on page 42

One Identity Manager application server status

You can access the application server from a browser.

Use the appropriate URL for this:

`http://<server name>/<application name>`

`https://<server>/<application name>`

TIP: You can open the web server's status display in the Job Queue Info. In the Job Queue Info, select **View | Server state** in the menu and, on the **Web servers** tab, open the web server status display from the **Open in browser** context menu.

You will see different status information. Status information for the application server is displayed as performance indicators. Users with the **Enables log display in the application server** program function (AppServer_Logs) can see the log. In addition, API documentation is available here.

Related topics


- [Determining Job server and web server status](#) on page 18

Which authentication module is the current user using?

One Identity Manager uses different authentication modules for logging in to administration tools. Authentication modules identify the system users to be used and load the user interface and database resource editing permissions depending on their permission group memberships.

For detailed information about the One Identity Manager authentication modules, see the *One Identity Manager Authorization and Authentication Guide*.

To identify the current authentication module for the current user

- To display user information, double-click the icon  in the status bar.

The **System user** tab displays the following information about the authentication module used.

Table 14: Information about the user authentication module

Property	Description
Authenticated by	Name of the authentication module used for logging in.
Employee UID (UserID)	Unique ID for the current user's employee if an employee related authentication module is used to log in.

Related topics

- [Which system user is the current user using?](#) on page 32
- [Which permissions apply to the current user?](#) on page 33
- [Which program functions are available to the current user?](#) on page 34
- [Which permissions level does the user use?](#) on page 34

Which system user is the current user using?

Users log in to the running administration tool using a system ID. Permitted system user IDs are determined by the authentication module you select. When the system user logs in to the One Identity Manager administration tools, the user interface is displayed and editing permissions are assigned depending on the permissions groups to which the user belongs.

For detailed information about the One Identity Manager authentication modules and system users, see the *One Identity Manager Authorization and Authentication Guide*.

To identify the current system user for the current user:

- To display user information, double-click the icon  in the status bar.

The **System user** tab displays the following information about the system user.

Table 15: Information about the system user

Property	Description
System user	Name of system user.
Dynamic user	Specifies whether the logged in user is using a dynamic system user. Dynamic system users are applied when a role-based authentication module is used.

Related topics


- [Which authentication module is the current user using?](#) on page 31
- [Which permissions apply to the current user?](#) on page 33
- [Which program functions are available to the current user?](#) on page 34
- [Which permissions level does the user use?](#) on page 34

Which permissions apply to the current user?

The user interface displayed to and edit permissions available to the current user depend on the permissions groups to which their system user belongs.

For detailed information about permissions in One Identity Manager, see the *One Identity Manager Authorization and Authentication Guide*.

To identify the current permissions groups for the current user:

- To display user information, double-click the  icon in the status bar.

The **Permissions groups** tab lists the user's permissions groups.

NOTE: The **Read only** option on the **System user** tab indicates whether the current system user has read permissions only. If so, the user is not permitted to change data.

To identify which permissions are assigned to the current user for an object:

- Select the object for which you want to see the permissions.
- Select the **Properties** context menu.

On the **Permissions** tab, you can see which permissions groups give you which permissions for an object.

Related topics


- [Which authentication module is the current user using?](#) on page 31
- [Which system user is the current user using?](#) on page 32
- [Which program functions are available to the current user?](#) on page 34
- [Which permissions level does the user use?](#) on page 34

Which program functions are available to the current user?

Some functions in One Identity Manager tools are available only if the program functions are assigned to the current user. For example, this includes data export from the Manager, calling the SQL Editor in the Designer or showing DBQueue Processor information in all programs.

For detailed information about program functions in One Identity Manager, see the *One Identity Manager Authorization and Authentication Guide*.

To identify the program functions available to the current user:

- To display user information, double-click the  icon in the status bar.
The **Program functions** tab shows the program functions that are available.

Related topics

- [Which authentication module is the current user using?](#) on page 31
- [Which system user is the current user using?](#) on page 32
- [Which permissions apply to the current user?](#) on page 33
- [Which permissions level does the user use?](#) on page 34

Which permissions level does the user use?

To implement a One Identity Manager database or a One Identity Manager History Database on a SQL Server or a managed instance in Azure SQL Database, you are provided with SQL Server logins and database users for administrative users, configuration users and end users. Permissions at server and database level are matched to suit the user's tasks.

For detailed information about users and their permissions, see the *One Identity Manager Installation Guide* and the *One Identity Manager Data Archiving Administration Guide*.

NOTE:

- If you select an existing database connection in the login dialog, the access level of the login to be used is shown in a tooltip.
- Some user interfaces expect configuration user permissions at least. Logging in as an end user is not possible in this case.

To find the access level of the logged in user

- To display user information, double-click the icon in the program status bar 

On the **System user** tab, in the **SQL access level** field, you will see the access level for the current login. The access levels displayed are **End user**, **Configuration user**, **Administrative user**, **System administrator**, and **Unknown**.

Related topics

- [Which authentication module is the current user using?](#) on page 31
- [Which system user is the current user using?](#) on page 32
- [Which permissions apply to the current user?](#) on page 33
- [Which program functions are available to the current user?](#) on page 34

Configuring logs in One Identity Manager

One Identity Manager provides various options for extending its log. The log can be configured for each One Identity Manager component.

Detailed information about this topic

- [Configuring the retention periods of messages in the system journal](#) on page 36
- [Recording process handling errors in the system journal](#) on page 38
- [Recording logins and logoffs in the system journal](#) on page 38
- [Informationen zur OAuth 2.0/OpenID Connect Authentifizierung aufzeichnen](#)
- [Global configuration of logging with NLog](#) on page 39
- [Logging the One Identity Manager components](#) on page 41
- [Configuring One Identity Manager Service logging](#) on page 42
- [Output of extended return values from individual process components](#) on page 49
- [Configuring notification behavior for DBQueue Processor initialization](#) on page 50
- [Enabling the crash recorder](#) on page 50

Configuring the retention periods of messages in the system journal

Table 16: Configuration parameters for logging in the system journal

Configuration parameter	Meaning
Common Journal	General parameter for configuring the system journal.

Configuration parameter	Meaning
Common Journal LifeTime	Use this configuration parameter to specify the maximum retention period in days for a system journal entry in the database. Older entries are deleted from the database.
Common Journal LifeTime D	The configuration parameter contains the retention period in days for Debug type messages.
Common Journal LifeTime E	The configuration parameter contains the retention period in days for Error type messages.
Common Journal LifeTime I	The configuration parameter contains the retention period in days for Info type messages.
Common Journal LifeTime T	The configuration parameter contains the retention period in days for Trace type messages.
Common Journal LifeTime W	The configuration parameter contains the retention period in days for Warning type messages.
Common Journal LoginAudit	Logs successful One Identity Manager logins.
Common Journal Delete	This configuration parameter allows configuration of deletion behavior for system messages.
Common Journal Delete BulkCount	This configuration parameter contains the number of entries to be deleted in an operation.
Common Journal Delete TotalCount	This configuration parameter contains the total number of entries to be deleted in any processing run.

Messages in the system journal are regularly deleted by the DBQueue Processor.

To delete log entries in the system journal

- In the Designer, enable the **Common | Journal | LifeTime** configuration parameter and enter the maximum retention period for the entries in the system journal. Use the configuration sub parameters to specify the retention period for each warning level.
- If there is a large amount of data, you can specify the number of objects to delete per DBQueue Processor operation and run in order to improve performance. To do

this, use the **Common | Journal | Delete | BulkCount** and **Common | Journal | Delete | TotalCount** configuration parameters.

Recording process handling errors in the system journal

To log error in process handling in the system journal

- At the process steps in the Designer, enable the **Log errors to journal** option.

For detailed information about editing processes and process steps, see the *One Identity Manager Configuration Guide*.

Related topics

- [Displaying system journal messages](#) on page 28

Recording logins and logoffs in the system journal

One Identity Manager logins and One Identity Manager logoffs can be recorded in the system journal.

| NOTE: Logins and logoffs are recorded in the QBM_VDialogJournalLoginAudit view.

To record successful One Identity Manager logins

- In the Designer, set the **Common | Journal | LoginAudit** configuration parameter.

To record One Identity Manager logoffs

- In the Designer, set the **Common | Journal | LogoffAudit** configuration parameter.

Related topics

- [Displaying system journal messages](#) on page 28

Global configuration of logging with NLog

Configuration setting for logging messages are made by NLog in Globallog.config. Globallog.config is referenced in the One Identity Manager component's configuration files.

IMPORTANT: The settings in globallog.config apply globally to all One Identity Manager components. Use the application specific *.exe.config configuration file to customize individual components.

NOTE: The default settings of the globallog.config file assume that %localappdata% has write access.

If an *.exe does not have the correct permissions, by changing the logBaseDir variable in globallog.config or by introducing a special log configuration in the application-specific *.exe.config or Web.config configuration file, you can write the log to a directory with write access.

Use variables to define names, output path and layout of the log files. The variable appName is defined in the One Identity Manager component's configuration files.

The targets section defines the output targets for the messages. NLog already has predefined targets that you can use in the configuration file.

The rules section is used to define rules for logging the messages. For an exact description and functionality of NLog, see the online help (<http://nlog-project.org/>).

Example of file structure

```
<nlog autoReload="true" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <variable name="companyName" value="One Identity"/>
  <variable name="productTitle" value="One Identity Manager"/>
  <variable name="logBaseDir"
    value="{specialfolder:LocalApplicationData}/{companyName}/{productTitle}/{appName}"/>
  <variable name="layout" value="{longdate} {level:upperCase=true} ({logger}
    {event-context:item=SessionId}) : {event-context:item=Indentation}{message}
    {exception:format=ToString,StackTrace}" />
  <targets async="true">
    <default-wrapper xsi:type="BufferingWrapper" bufferSize="256"
      flushTimeout="2000" />
    <target name="logfile" xsi:type="File"
      fileName="{logBaseDir}/{appName}.log" layout="{layout}" encoding="utf-8"
      archiveFileName="{logBaseDir}/{appName}.{#}.log" maxArchiveFiles="7"
      archiveEvery="Day" archiveNumbering="Rolling"/>
  </targets>
```

```

<targets>
  <target name="eventLog" xsi:type="EventLog" source="{companyName}
    ${productTitle} ${appName}"
    layout="{message}{newline}{exception:format=toString}"/>
</targets>
<rules>
  <logger name="*" minlevel="Info" writeTo="logfile"/>
  <logger name="*" level="Fatal" writeTo="eventLog"/>
</rules>
</nlog>

```

You can enter the severity level through:

- `minlevel=` Messages are logged from this severity level.
- `level=` Message are logged which have exactly this severity level.

Table 17: Permitted severity levels

Severity Level	Description
Trace	Logs highly detailed information. This setting should only be used for analysis purposes. The log file quickly becomes large and cumbersome.
Debug	Logs debug steps. This setting should only be used for testing.
Info	Logs all information.
Warning	Logs all warnings.
Error	Logs all error messages.
Fatal	Logs all critical error messages.

By providing `logger name`, you specify for which One Identity Manager components messages are logged. Messages are logged for all components with the default setting `logger name="*"`. To limit logs to certain components, use the name contained in the log.

Table 18: Logger names of components

Logger name	Description
FrontendLog	Logs actions in front-ends.
JobGenLog	Logs during process generation.
Jobservice	Logs One Identity Manager Service messages.
ObjectLog	Logs object actions through the object level.

Logger name	Description
ProjectorEngine	Logs messages from the synchronization engine.
SqlLog	Logs database queries
StopWatch	Logs timings.
SystemConnection	Detailed logging of data communication with the system connection during synchronization, including system configuration and system connectors' data communication.
SystemConnector	Logs system connector data communication during synchronization.
Update	Logs update handling.
WebLog	Logs Web service actions.

Logging the One Identity Manager components

In the One Identity Manager default installation, the log files are written to the %LocalAppData%\One Identity\One Identity Manager\

All messages with a minimum information level of **Info** are recorded in the <appName>.log file. The files are kept for 7 days and backed up daily.

In addition, all messages with a severity level of **Fatal** are recorded in the event log for the **One Identity Manager <appName>** source.

Each One Identity Manager component supports message logging using the integrated NLog functionality. For an exact description and functionality, see the online help (<http://nlog-project.org/>).

The configuration files of the One Identity Manager component (*.exe.config) contain the nlog section, in which settings for logging by means of NLog are entered. Use the appName variable to pass One Identity Manager component names.

The configuration of the logs is defined in the globallog.config global configuration file. This file is referenced in the configuration files of the One Identity Manager components.

Example of a configuration file

```
<configuration>
  <configSections>
    ...
    <section name="nlog" type="NLog.Config.ConfigSectionHandler, NLog"/>
  </configSections>
</configuration>
```

```
</configSections>
...
<nlog autoReload="true" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <variable name="appName" value="Manager"/>
  <include file="{basedir}/globallog.config" ignoreErrors="true"/>
</nlog>
...
</configuration>
```

Related topics

- [Global configuration of logging with NLog on page 39](#)

Configuring One Identity Manager Service logging

Success and error messages from process handling are written to the One Identity Manager Service log file. Messages can also be written to a server's event log. A severity level can be configured for output to this log file.

You can create most of the settings in the One Identity Manager Service configuration file. Use the Job Service Configuration program to do this. For detailed information about working with Job Service Configuration and configuring the One Identity Manager Service, see the *One Identity Manager Configuration Guide*.

Detailed information about this topic

- [Prerequisites for displaying the log file on page 42](#)
- [Advanced logging in the One Identity Manager Service on page 45](#)
- [Extended debugging in One Identity Manager Service on page 46](#)
- [Outputting custom messages in the One Identity Manager Service log file on page 46](#)
- [Recording messages in the event view on page 47](#)
- [HTTPLogPlugins log file on page 48](#)
- [Global configuration of logging with NLog on page 39](#)

Prerequisites for displaying the log file

The One Identity Manager Service log files can be displayed using a HTTP server (<http://<server name>:<port number>>).

- Users require permission to open an HTTP server. The administrator must grant URL approval to the user to do this. This can be executed with the following command line call:

```
netsh http add urlacl url=http://*:<port number>/ user=<domain>\<user name>
```

If the One Identity Manager Service has to run under the Network Service (**NT Authority\NetworkService**) user account, explicit permissions for the internal web service must be granted. This can be executed with the following command line call:

```
netsh http add urlacl url=http://<IP address>:<port number>/ user="NT AUTHORITY\NETWORKSERVICE"
```

You can check the result with the following command line call:

```
netsh http show urlacl
```

To display the One Identity Manager Service log file, configure the following modules in the One Identity Manager Service configuration file:

- **FileLogWriter** module
Create the log file settings in this module.
- **Configuration** module
Configure the port for displaying the services. The default value is port 1880.
- **HTTP authentication** module
Set up an authentication method to display the log file.

For more detailed information about configuring the One Identity Manager Service, see the *One Identity Manager Configuration Guide*.

Detailed information about this topic

- [Configuring the log file](#) on page 43
- [Authentication method for displaying the log file](#) on page 45

Configuring the log file

To generate the log file, customize the **FileLogWriter** module in the One Identity Manager Service configuration file for each One Identity Manager Service.

Table 19: FileLogWriter parameters

Parameters	Description
Log file (OutputFile)	Name of the log file, including the directory name. Log information for the One Identity Manager Service is written to this file. IMPORTANT: The directory specified for the file must exist. If the file cannot be created, no error output is possible. Error messages then

Parameters	Description
	appear under Windows operating systems in the event log or under Linux operating systems in /var/log/messages.
Log rename interval (LogLifeTime)	<p>In order to avoid unnecessarily large log files, the module supports the functionality of exchanging the log file with a history list. The LogLifeTime specifies the maximum life of a log file before it is renamed as backup. If the log file has reached its maximum age, the file is renamed (for example, as JobService.log_20040819-083554) and a new log file is started.</p> <p>Timeout format: day.hour:minutes:seconds</p>
Process step log lifetime (JobLogLifeTime)	<p>Use this parameter to specify the length of time process step logs are kept. After this expires, the logs are deleted.</p> <p>Timeout format: day.hour:minutes:seconds</p> <p>For test purposes, you can enable logging of individual process steps in the Job Queue Info. The processing messages of the process step is written to a separate log with the Debug NLog severity. The files are stored in the log directory.</p> <p>Repository structure: <Log directory>\JobLogs\<<First 4 digits of the UID_Job>\Job_<UID_Job>_<yyyymmdd>_<Timestamp>.log</p>
Number of history logs (HistorySize)	Maximum number of log files. If several log files exist, the oldest backup file is deleted when a new log file is created so that the limit is not exceeded.
Max. log file size (MB) (MaxLogSize)	Maximum size in MB of the log file. Once the log file has reached the limit, it is renamed as a backup file and a new log file is created.
Max. length of parameters (ParamMaxLength)	Specifies the maximum number of characters a process step parameter is permitted to have in order to be written to the log file.
LogSeverity	<p>Severity levels of the logged messages.</p> <p>Permitted values are:</p> <ul style="list-style-type: none"> • Info: All messages are written to the event log. The event log quickly becomes large and confusing. • Warning: Only warnings and exception errors are written to the event log (default).

Parameters	Description
	<ul style="list-style-type: none"> • Serious: Only exception messages are written to the event log.
Add server name (AddServerName)	Specifies whether the server name is to be added to the log entries.

For more detailed information about configuring the One Identity Manager Service, see the *One Identity Manager Configuration Guide*.

Authentication method for displaying the log file

Use the HTTP authentication module to specify how authentication on the HTTP server works to access the services, for example, to display the log file or status display.

The following module types may be selected:

- BasicHttpAuthentication
With this authentication type, enter a specific user account and the corresponding password for accessing the HTTP server.
- WindowsHttpAuthentication
Use this authentication type to specify an Active Directory group, whose users can be authenticated on the HTTP server. A security ID (SID) or the Active Directory group name in the domain of the Job server can be specified. If Active Directory is not located in the domain of the Job server, the SID must be used.

NOTE: If a module is not specified, authentication is not required. In this case, all users can access the services.

For more detailed information about configuring the One Identity Manager Service, see the *One Identity Manager Configuration Guide*.

Advanced logging in the One Identity Manager Service

To use advanced logging for the One Identity Manager Service, configure the storage of log files in the One Identity Manager Service configuration file in the **Connection** module.

NOTE: The given directory must exist and the One Identity Manager Service user account must have write permissions to the directory.

Following parameters are available:

- Process generation log directory (JobGenLogDir)

Log files are created in this directory that record process generation instructions from One Identity Manager Service.

For more detailed information about configuring the One Identity Manager Service, see the *One Identity Manager Configuration Guide*.

Extended debugging in One Identity Manager Service

The **Configuration** module of the One Identity Manager Service configuration file provides two parameters for advanced debugging:

- DebugMode
- ComponentDebugMode

If the **Debug mode** (DebugMode) parameter is enabled, the One Identity Manager Service writes more extensive information into the log file, such as all parameters transferred to a component and the results of the process handling and their Out parameters.

Individual One Identity Manager Service process components can output additional process data to the One Identity Manager Service log file. For this purpose, you can enable the **Component debug mode** (ComponentDebugMode) parameter in the configuration module. Use this debug mode only for localizing errors because the effect on performance means that it is not recommended for normal use.

For more detailed information about configuring the One Identity Manager Service, see the *One Identity Manager Configuration Guide*.

Outputting custom messages in the One Identity Manager Service log file

You can use the RaiseMessage and AppData.Instance.RaiseMessage script engine tasks from within process steps to write custom messages to the One Identity Manager Service log file. Use the ScriptComponent process component to run the scripts.

The messages in the log file are marked in color depending on the specified severity (MsgSeverity parameter).

Figure 8: Example output of custom messages to the One Identity Manager Service log file

```
2007-08-10 12:48:58 - Warning: Example warning message
2007-08-10 12:48:58 - Info: Example Info message
2007-08-10 12:48:58 - Serious: Example error message
```

RaiseMessage

The output is consolidated with other messages and logged at the end of processing the process step.

Syntax:

```
RaiseMessage (MsgSeverity, "string")
```

Example:

```
RaiseMessage (MsgSeverity.Warning, "Example warning message")  
RaiseMessage (MsgSeverity.Info, "Example Info message")  
RaiseMessage (MsgSeverity.Serious, "Example error marked message")
```

AppData.Instance.RaiseMessage

The output is issued immediately during processing regardless of whether processing of the process step has ended.

Syntax:

```
AppData.Instance.RaiseMessage (MsgSeverity, "string")
```

Example:

```
AppData.Instance.RaiseMessage (MsgSeverity.Warning, "Example warning message")  
AppData.Instance.RaiseMessage (MsgSeverity.Info, "Example Info message")  
AppData.Instance.RaiseMessage (MsgSeverity.Serious, "Example error marked  
message")
```

For more examples of One Identity Manager Service log file output, see the script example on the installation medium in the directory QBM\dvd\AddOn\SDK\ScriptSamples.

IMPORTANT: You should never use the VB.NET functions `Msgbox` and `Inputbox` on servers. Use the functions `VID_Write2Log`, `RaiseMessage` or `AppData.Instance.RaiseMessage`.

Recording messages in the event view

To record One Identity Manager Service messages in the server's event log, modify the **EventLogLogWriter** module in the One Identity Manager Service's configuration file. To view the event log, you can use the results display in the Microsoft Management Console, for example.

Table 20: EventLogLogWriter parameters

Parameters	Description
EventLog	Name of the event log to which the messages are written. The messages are written to the application log with Application as the default value. NOTE: If more than one One Identity Manager Service write event logs on a server, make sure that the first eight letters in the log name are unique on the server.
LogSeverity	Severity levels of the logged messages. Permitted values are: <ul style="list-style-type: none">• Info: All messages are written to the event log. The event log quickly becomes large and confusing.• Warning: Only warnings and exception errors are written to the event log (default).• Serious: Only exception messages are written to the event log.
EventID	The ID of the messages written to the event log.
Category	The category of the messages written to the event log.
Source	The name of the source of the messages written to the event log.

Process handling error can also be written to a server's result log. For this purpose, use the LogComponent process component.

For more detailed information about configuring the One Identity Manager Service, see the *One Identity Manager Configuration Guide*.

Related topics

- [Ereignisprotokoll ändern](#)

HTTPLogPlugins log file

If the **HTTPLogPlugin** plug-in is configured in the One Identity Manager Service configuration file, a log file is generated with the HTTP queries of the One Identity Manager Service. The file is written in Apache HTTP Server Combined Log Format.

Example entry

```
172.19.2.18 - - [03/Feb/2005:14:55:48 +0100] "GET /resources/JobService.css HTTP/1.x"
OK - "http://<server name>:<port>/status/LogWriter/Config"Mozilla/5.0 (Windows; U;
5.1; en-US; rv:1.7.5) Gecko/20041108Firefox/1.0"
```


Table 21: Meaning of each entry

Entry	Meaning
172.19.2.18	IP address that sent the request.
-	Client user name using IDENT protocol (RFC 1413)-
-	User name of the client according to HTTP authentication.
[03/Feb/2005:14:55:48 +0100]	Time that the request is processed on the server
GET /resources/JobService.css HTTP/1.x	Request
OK	Status code-
-	Size of data sent back to the browser
"http://<server name> : <port>/status/LogWriter/Config"	URL from which the page can be accessed
"Mozilla/5.0 (Windows; U; Windows NT 5.1; de-DE; rv:1.7.5) Gecko/20041108Firefox/1.0"	Browser name

For more detailed information about configuring the One Identity Manager Service, see the *One Identity Manager Configuration Guide*.

Output of extended return values from individual process components

Table 22: Configuration parameter for outputting extended return values

Configuration parameter	Effect when set
Common Jobservice DoReturnOutput	The entire output of the parameter is written to the One Identity Manager Service log file when a error occurs in the case of process task that supply an extended return value.

Individual process components have process tasks with parameters that supply extended return values (OUT).

The entire output of the parameter is written to the One Identity Manager Service log file when a error occurs. For example, the output text of the listed commands or programs can be returned when you run a command or a program using the `CommandComponent` process component.

To log return values

- In the Designer, enable the **Common | Jobservice | DoReturnOutput** configuration parameter.

Related topics

- [OUT parameters](#) on page 15

Configuring notification behavior for DBQueue Processor initialization

If errors occur during initialization of the DBQueue Processor, messages are written to the application log. You can use the results display in the Microsoft Management Console, for example, to view the application log.

Use the **QBM | DBServerAgent | CreateNotification** configuration parameter to configure in which cases error messages are written to the application log. In the Designer, you can modify the configuration parameter as required.

Permitted values are:

- **0**: No logging.
- **1**: Only success messages are logged.
- **2**: Only error messages are logged.
- **3**: All messages are logged.

For more detailed information about the DBQueue Processor, see the *One Identity Manager Configuration Guide*.

Enabling the crash recorder

The crash recorder saves the previous 128 messages starting at **Debug** level and issues these in the error message window. You can configure the crash recorder using the configuration files for the One Identity Manager tools (*.exe.config).

Example for activating the crash recorder in the configuration file

```
<configuration>
  <configSections>
    ...
```

```
<section name="connectionbehaviour" type="System.Configuration.
NameValueSectionHandler" />
</configSections>
...
<appSettings>
    <add key="CrashRecorderBuffer" value="128" />
    <add key="CrashRecorderLevel" value="Error" />
</appSettings>
<connectionbehaviour>
    ...
</connectionbehaviour>
...
</configuration>
```

If the variable `CrashRecorderBuffer` is set to the value `0`, the crash record functionality is disabled.

Permitted values for `CrashRecorderLevel` are **Debug**, **Error**, **Fatal**, **Info**, **Off**, **Trace** and **Warn**.

Related topics

- [The error message window in One Identity Manager tools](#) on page 23

One Identity Manager configuration files

General configuration settings can be preset in a configuration file. The configuration file is kept in the program directory. Each administration tool can take its settings from a configuration file in NET executable format. Valid global configuration settings can also be defined through a configuration file in One Identity Manager's own format.

Detailed information about this topic

- [Application-specific configuration files](#) on page 52
- [Global configuration file for One Identity Manager tools](#) on page 54

Application-specific configuration files

NOTE: Use the `globallog.config` configuration file to define global settings that apply to all One Identity Manager components.

One Identity Manager components, such as the Manager or the Designer, have a configuration file for .NET executables with a predefined format for this. There is a configuration section in the file for each of the different modules of a One Identity Manager component.

NOTE: Entries are case-sensitive.

The root in the XML file is always called `configuration`. All other sections of the configuration file must be in the mandatory `configSections` section and their type must be defined.

Format of the configuration file using `.exe.config` as an example

```
<?xml version="1.0" encoding="utf-8" ?>
<configuration>
  <configSections>
    <section name="formprovider"
```

```

    type="System.Configuration.NameValueSectionHandler" />
    <section name="formarchives"
    type="System.Configuration.NameValueSectionHandler" />
    <section name="vicontrols"
    type="System.Configuration.NameValueSectionHandler" />
    <section name="connectionbehaviour"
    type="System.Configuration.NameValueSectionHandler" />
    <section name="dialogplugins"
    type="System.Configuration.NameValueSectionHandler" />
    <section name="consistencychecks"
    type="System.Configuration.NameValueSectionHandler" />
    <section name="nlog" type="NLog.Config.ConfigSectionHandler, NLog"/>
</configSections>
<dialogplugins>
    <add key="ComplianceRuleSimulation"
    value="VI.DialogEngine.Plugins.ComplianceRuleSimulation,
    AE.DialogEngine.Plugins" />
    <add key="ComplianceRuleSimulationSummary"
    value="VI.DialogEngine.Plugins.ComplianceRuleSimulationSummary,
    AE.DialogEngine.Plugins" />
</dialogplugins>
<consistencychecks>
    <add key="AE" value="VI.ConsistencyChecks.AE.dll" />
    <add key="Common" value="VI.ConsistencyChecks.Common.dll" />
</consistencychecks>
<formarchives>
    <add key="Forms" value="archive:.\???.Forms*.vif;10" />
    <add key="CustomForms" value="archive:.\AE.CustomForms*.vif;5" />
    <add key="CommonForms" value="archive:.\Common.Forms*.vif;5" />
</formarchives>
<vicontrols>
    <add key="defaultcontroldesign" value="System" />
</vicontrols>
<nlog autoReload="true" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
    <variable name="appName" value="Manager"/>
    <include file="{basedir}/globallog.config" ignoreErrors="true"/>
</nlog>
</configuration>

```

Related topics

- [Global configuration of logging with NLog on page 39](#)
- [Global configuration file for One Identity Manager tools on page 54](#)

Global configuration file for One Identity Manager tools

The Global.cfg is an XML configuration file in One Identity Manager's own simplified format. The advantage of this file is that run-time loading is supported. Each of the different modules has its own section allocated within the file.

NOTE: Entries are case-sensitive. Both the sections and the names of the values must be written in lower case.

You can find an example of a configuration file on the installation medium in the QBM\dvd\AddOn\SDK\ConfigSample directory. If the file Global.cfg is in the program directory, it is used when the One Identity Manager tools start up.

The root in the XML file is always called configuration. Each configuration file module and its values are defined in a section category respectively.

Format of global.cfg

```
<configuration>
  <category name="settings">
    <value name="language">English</value>
    <value name="autoupdateenabled">>true</value>
    <value name="connectiontimeout">15</value>
  </category>
  <category name="connections">
    <value name="database display 1">ConnectionString</value>
    <value name="database display 2">ConnectionString</value>
  </category>
</configuration>
```

TIP: To generate the (ConnectionString) connection parameters, use the Config Encryptor program. You will find this program on the installation medium in the directory QBM\dvd\AddOn\ConfigEncryptor.

Related topics

- [Application-specific configuration files on page 52](#)

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales and other inquiries, such as licensing, support, and renewals, visit <https://www.oneidentity.com/company/contact-us.aspx>.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product

*

*.exe.config 52

A

application server
 status display 31

C

combined log format 48
configurations
 ComponentDebugMode 46
 DebugMode 46
connection
 JobGenLogDir 45
Crashrecorder 50

D

database journal
 delete 36
 display 28
 log login 38
 log logoff 38
 retention period 36
DBQueue
 display 19
DBQueue Processor
 stop 20

E

emergency stop 20

error log 25
error message window 23
EventLogLogWriter
 EventLog 47
 LogSeverity 47

F

FileLogWriter 43
 HistorySize 43
 JobLogLifeTime 43
 LogLifeTime 43
 LogSeverity 43
 MaxLogSize 43
 OutPutFile 43
 ParamMaxLength 43

G

Global.cfg 54
Globallog.config 39

H

HTTP authentication
 BasicHttpAuthentication 45
 WindowsHttpAuthentication 45
HTTPLogPlugin
 log file 48

J

- Job queue
 - progress 20
- Job Queue Info 6
 - column configuration 8
 - create filter 10
 - database journal 28
 - emergency stop 20
 - HTTP port 9
 - language 9
 - One Identity Manager Service
 - log file 30
 - polling interval 9
 - process history 9
 - program setting 9
 - stop system 20
 - timeout 9
 - update 8
 - use filter 10
- Job server
 - continue processing 20
 - find state 18
 - stop processing 20

L

- Logger name
 - FrontendLog 39
 - JobGenLog 39
 - Jobservice 39
 - ObjectLog 39
 - ProjectorEngine 39
 - SqlLog 39
 - StopWatch 39

- SyncLog 39
- SystemConnection 39
- SystemConnector 39
- update 39
- WebLog 39

- LogWriter
 - FileLogWriter 43

N

- NLog 41
 - Logger name 39
 - severity level 39

O

- One Identity Manager Service
 - ComponentDebugMode 46
 - DebugMode 46
 - event log 47
 - FileLogWriter 43
 - generation log 45
 - HTTP Server 42
 - log file 17, 43, 46
 - display 30, 42
 - log file (HTTPLogPlugin) 48
 - NSProviderTrace.log 46
 - out parameter 49
 - RaiseMessage 46
 - services 42
 - StdioProcessor.log 46
 - stop 20

P

- process
 - frozen 16

- monitor 11
- over limit 16
- reenable 16
- restart 16
- process component
 - ComponentDebugMode 46
 - return value 49
- process handling
 - monitor 6
- process step
 - details 12-13
 - end on failure 16
 - end on success 16
 - execution log 17
 - execution state 11-12
 - frozen 16
 - log error 38
 - logging
 - disable 17
 - enable 17
 - over limit 16
 - parameter 14
 - hidden 15
 - out parameter 15, 49
 - reenable 16

S

- script
 - RaiseMessage 46
- server state 18
- system
 - stop 20
- system configurations
 - report 22

U

- user
 - access level 34
 - authentication module 31
 - dynamic 32
 - permissions group 33
 - program function 34
 - system user 32

W

- web server
 - find state 18