

Quest® Change Auditor Threat Detection 7.5
Deployment Guide



© 2025 Quest Software Inc.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of Quest Software Inc.

The information in this document is provided in connection with Quest Software products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of Quest Software products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, QUEST SOFTWARE ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL QUEST SOFTWARE BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF QUEST SOFTWARE HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Quest Software makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. Quest Software does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

Quest Software Inc.
Attn: LEGAL Dept.
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our website (<https://www.quest.com>) for regional and international office information.


Patents

Quest Software is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <https://www.quest.com/legal>.

Trademarks

Quest, the Quest logo, and Join the Innovation are trademarks and registered trademarks of Quest Software Inc. For a complete list of Quest marks, visit <https://www.quest.com/legal/trademark-information.aspx>. All other trademarks and registered trademarks are property of their respective owners.

Legend

 **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.

 **IMPORTANT NOTE, NOTE, TIP, MOBILE, or VIDEO:** An information icon indicates supporting information.

Contents

| | |
|---|-----------|
| Deploying Threat Detection | 4 |
| Introduction to Change Auditor Threat Detection | 5 |
| Who should have input on the deployment plan? | 5 |
| Components and workflow | 5 |
| Requirements and prerequisites | 6 |
| Events to configure | 7 |
| Port Requirements | 7 |
| Maintaining the Change Auditor database size | 7 |
| Deploying a Threat Detection server on ESX | 8 |
| Deploying a Threat Detection server on Hyper-V | 10 |
| Hyper-V resource control settings | 11 |
| Upgrading the Threat Detection server | 12 |
| Upgrade from Change Auditor version 7.0.2 | 12 |
| Upgrade from Change Auditor version 7.0 and 7.0.1 | 13 |
| Creating a Threat Detection configuration | 15 |
| Reviewing configuration status | 16 |
| Configured server deployment details | 16 |
| Removing a configuration | 17 |
| Historical events and your baseline calculations | 17 |
| Threat Detection configuration commands | 19 |
| Adding the PowerShell module | 20 |
| Viewing available commands and help | 20 |
| Threat Detection sample scripts | 20 |
| Connecting to Change Auditor | 20 |
| Connect-CAClient | 21 |
| Managing a Threat Detection configuration | 21 |
| New-CAThreatDetectionConfiguration | 22 |
| Get-CAThreatDetectionConfiguration | 22 |
| Set-CAThreatDetectionConfiguration | 24 |
| Remove-CAThreatDetectionConfiguration | 24 |
| Appendix: System Architecture | 25 |
| Threat Detection system overview | 26 |
| About us | 27 |
| Our brand, our vision. Together. | 27 |
| Contacting Quest | 27 |
| Technical support resources | 27 |

Deploying Threat Detection

- [Introduction to Change Auditor Threat Detection](#)
- [Who should have input on the deployment plan?](#)
- [Components and workflow](#)
- [Requirements and prerequisites](#)
- [Events to configure](#)
- [Port Requirements](#)
- [Deploying a Threat Detection server on ESX](#)
- [Deploying a Threat Detection server on Hyper-V](#)
- [Upgrading the Threat Detection server](#)
- [Creating a Threat Detection configuration](#)
- [Reviewing configuration status](#)
- [Removing a configuration](#)
- [Maintaining the Change Auditor database size](#)
- [Historical events and your baseline calculations](#)

Introduction to Change Auditor Threat Detection

To protect your data and your business, Change Auditor Threat Detection uses advanced machine learning, user and entity behavioral analytics (UEBA), and SMART correlation technology to spot anomalous activity and identify the highest risk users in your environment. The users with the highest risk scores are then highlighted in the Threat Detection dashboard, enabling you to prioritize your response and adjust policies to strengthen your organization's security and regulatory enforcement.

For details about using the Threat Detection dashboard see the Change Auditor Threat Detection User Guide.

This guide gives information about how Change Auditor integrates with the Threat Detection server to process event data. It is intended for administrators who are responsible for the implementation, deployment, and monitoring of the Change Auditor Threat Detection deployment and configuration.

Who should have input on the deployment plan?

A complete deployment plan requires the combined effort of the resources within your organization who are responsible for information security, such as:

- Chief Information Security Officers who understand the complexities of the enterprise's IT infrastructure and are responsible for the overall handling of key vulnerabilities. Change Auditor provides data to help them deliver security updates and communications.
- Security architects who are responsible for building and overseeing the implementation of the network's security measures. They need to define the threat priorities for their environment.
- Database and network administrators who are responsible for the implementation, deployment, and monitoring of the Change Auditor Threat Detection configuration.
- Auditors and network administrators who are responsible for reviewing the potential threats, optimizing the system by inputting feedback, and prioritizing and investigate the most serious threats.

Components and workflow

Change Auditor sends events in real time to the Threat Detection server to be used for analysis based on calculated user behavior baselines.

See the Change Auditor Threat Detection User Guide for details on Threat Detection concepts and terms.

To enable Threat Detection:

- 1 Apply the required licenses. (Change Auditor Threat Detection and any required Change Auditor auditing modules.) If you are using more than one coordinator, apply the license to all of them. To verify that a license is applied, right-click the coordinator icon in the system tray and select Licensing.
- 2 Configure required events for Threat Detection. See [Events to configure](#).
- 3 Deploy the Threat Detection server on a virtual computer. See [Deploying a Threat Detection server on ESX](#) and [Deploying a Threat Detection server on Hyper-V](#).
- 4 Configure Change Auditor to send collected event data to the Threat Detection server. See [Creating a Threat Detection configuration](#).
- 5 Login to the Threat Detection dashboard to see the alerts and data. See the Threat Detection User Guide for information about navigating the dashboard and using the data to secure your environment.

Requirements and prerequisites

For a successful deployment, ensure that your environment meets the minimum system requirements.

The Threat Detection server deployed on VMWare ESX is available in both 8 and 16 cores versions.

For a Hyper-v deployment, a single server is available and you select the number of cores during the deployment.

- **NOTE:** The number of cores impact the length of time it takes to process historical audit data and build the baseline. 16 cores is recommended, 8 cores can be used if processing less than 5 million events per day.

Deployment on VMWare ESX

- VMWare ESXI version 5.5 and above which is managed by VMware Vcenter 5.5 and above
- The following vSphere clients are supported:
 - With ESX 5.5 - vSphere Windows client.
 - With ESX 6.0 - vSphere Flash client.
 - With ESX 6.5 - vSphere Flex client, vSphere HTML5 client.
- Small and medium sized enterprise edition OVA:
 - OVA file size: ~10GB
 - CPU: 8 cores, Minimal 2.3 GHz, Recommended 2.4 GHz
 - RAM: 64 GB
 - I/O: 500 MB/sec
 - Disk: SAS 320 GB, SAS 930 GB
- Large sized enterprise edition OVA:
 - OVA file size: ~10GB
 - CPU: 16 cores, Minimal 2.3 GHz, Recommended 2.4 GHz
 - RAM: 64 GB
 - I/O: 500 MB/sec
 - Disk: SAS 320 GB, SAS 930 GB

Deployment on Microsoft Hyper-V

- Hyper-V host which running on Windows server 2016
- Threat Detection server requirements:
 - Template size: ~10 GB
 - CPU: 8 or 16 cores, Minimal 2.3 GHz, Recommended 2.4 GHz.
 - RAM: 64 GB
 - I/O: 500 MB/sec
 - Disk: SAS 320 GB, SAS 930 GB.

For all deployments:

- Obtain a static IP address for Threat Detection server and add DNS (A) record for it.
- Determine the number of historical days to use for your activity baseline. For information on how to determine the best amount for you, see [Historical events and your baseline calculations](#).

Events to configure

i | **NOTE:** Consider [Maintaining the Change Auditor database size](#) when adding events for Threat Detection auditing.

Events from the following modules are used to build models and generate alerts:

Table 1. Events used for modeling and alerts

| Module | Events |
|---|---|
| Change Auditor for Logon Activity | Authentication Activity events – these are the successful and failed interactive and remote interactive events (all enabled by default). Domain Controller Authentication events – Ensure that you enable the “User authenticated through Kerberos” event. By default, it is disabled. |
| Change Auditor for Active Directory | User and group events (all enabled by default). |
| Change Auditor for Windows File Servers | For optimal Threat Detection results, Quest recommends that you select file, folder, and share events that audit permission changes, create, delete, rename, and open actions during the template creation. |
| Change Auditor for EMC | |
| Change Auditor for NetApp | |

Port Requirements

The following ports are required for Threat Detection server operation:

Table 2. Port requirements

| Component | Ports |
|---|---|
| Coordinator to Threat Detection server | <ul style="list-style-type: none">SSH TCP 22 - Facilitates Threat Detection server upgrades and maintenance.HTTPS TCP 443 - Creation, removal, and operation of Threat Detection subscription. |
| Change Auditor client and Chrome web browser to Threat Detection server | <ul style="list-style-type: none">HTTPS TCP 443 - Threat Detection dashboard and interface. |
| Threat Detection server to Active Directory | <ul style="list-style-type: none">LDAP TCP/UDP 389 - Active Directory services.Global Catalog (GC) TCP 3268 - Active Directory services.DNS UDP 53 - Name resolution.Kerberos TCP 88 - Kerberos authenticated connections. |

Maintaining the Change Auditor database size

Some of the events required for Threat Detection can be very noisy and take up significant space in the Change Auditor database. Once the events are sent to the Threat Detection server for analysis storage in the Change Auditor database is no longer needed.

To ensure the database maintains a manageable size, Quest recommends that you purge events older than 30 days.

Particularly noisy events are:

- User authenticated through Kerberos
- File and folder open

Deploying a Threat Detection server on ESX

To download the Threat Detection server go to <https://support.quest.com/change-auditor/7.0.3/download-new-releases>.

The Threat Detection server, which is a version of Red Hat Enterprise Linux 7 (64 bit), is available as Open Virtual Appliance (OVA) file that must be deployed on VMWare ESXi using VMWare VSphere Client.

i | **NOTE:** Depending on the version of the ESXi, the deployment steps may be different. The below steps outline the process for vSphere Client version 6.5.

To deploy the Threat Detection server

- 1 Open vSphere client.
 - i** | **NOTE:** VMWare VSphere Client should be connected to VMWare vCenter not an individual ESXi host.
- 2 Select **Actions | Deploy OVF Template**.
- 3 Under **Select template**, choose **Local file**, browse for the OVA template, and click **Next**.
- 4 Under **Select name and location**, specify the name and inventory location for the deployed template and click **Next**.
- 5 On **Select a resource**, choose the destination computer for the OVA and click **Next**.
- 6 Under **Review details**, verify the OVF template details and click **Next**.
- 7 Under **Select Storage**, select the datastore for the configuration and the disk files and click **Next**. The **Thin Provision** option is recommended.
- 8 Under **Select networks**, choose a destination network for the virtual computer and select **Next**.
- 9 Under **Customize template**, enter the deployment properties for the Threat Detection sever.

| Property | Description |
|-----------------|---|
| Hostname | Fully qualified domain name of the Threat Detection server that has been registered in DNS. For example: hostname.yourcompany.com. |
| IP address | Static IPv4 address of the Threat Detection server. |
| Subnet mask | Subnet mask. For example: 255.255.255.0 |
| Default gateway | Default gateway IP address. |
| DNS | DNS server IP address. |

| Property | Description |
|----------------------|---|
| Integration password | <p>Password required for the integration between Change Auditor and the Threat Detection server. The integration password is used during the Threat Detection configuration.</p> <p>The password must be 8-24 characters and can only include the following supported values: a-z, A-Z, 1-0, @, \$.</p> <p>Maintain this password for use when creating the Threat Detection configuration.</p> |
| Root password | <p>Root password for the Threat Detection server. It must be 8-24 characters and can only include the following supported values: a-z, A-Z, 1-0, @, \$.</p> |

10 Click **Next**.

11 Under **Ready to complete**, verify the information and click **Finish**.

12 Once the deployment is complete, power on the Threat Detection server.

Quest recommends that you take a snapshot of the newly deployed virtual server. This allows you to revert to a clean state without redeploying the server if you need to start over or re-create a configuration.

You are now ready to create a Threat Detection configuration in Change Auditor.

Deploying a Threat Detection server on Hyper-V

To optimize your server utilization and reduce costs, you can choose to deploy a virtual Threat Detection server using a Hyper-V virtual machine deployment.

The Threat Detection server, which is a version of Red Hat Enterprise Linux 7 (64 bit), is available as .zip file that must be deployed on a Microsoft Hyper-V host environment by running a PowerShell script.

Begin by downloading the Change Auditor Hyper-V template (<https://support.quest.com/change-auditor/7.0.3/download-new-releases>) to the Hyper-V server.

i | **NOTE:** PowerShell version 5 or higher is required.

To deploy the Threat Detection server

- 1 For remote deployments using an IP address to connect the Hyper-V server (in absence of a Hyper-V server DNS record), perform the following:
 - Start the Windows Remote Management (WS-Management) /(WinRM) service.
 - Run this PowerShell command as an administrator to add the Hyper-V server IP address to the TrustedHosts list:

```
set-item wsman:\localhost\Client\TrustedHosts -value <Your_Hyper-V_Host_IP_Address>
```

- 2 From the Change Auditor client browse to the DeployThreatDetectionHyper-VServer.ps1 deployment script. By default it is located here: C:\Program Files\Quest\ChangeAuditor\Client\PowerShell Sample Scripts.

i | **NOTE:** You can run the script on the same computer as where you are deploying the Threat Detection server (local deployment) or from any other computer in the network (remote deployment).

- 3 Right-click the deployment script and select **Run with PowerShell**.
- 4 Enter the deployment properties for the Threat Detection sever.

| Property | Description |
|--|---|
| Hostname or IP address | The hostname or IP address of the Hyper-V server. |
| Hyper-V administrator | The account used to deploy the Threat Detection server. The user specified must be a Hyper-V administrator. |
| Hyper-V password | Password for the Hyper-V administrator. |
| Threat Detection Hyper-V template location | Location of the Threat Detection Hyper-V template zip file on the Hyper-V server. |
| Folder for the virtual machine HD files | The path of the folder where the Threat Detection server's hard disk files will be installed on the Hyper-V server during deployment. If the folder does not exist, it will be created. |
| Folder for the virtual machine configuration files | The path of the folder where the Threat Detection server's configuration files will be installed on the Hyper-V server during deployment. If the folder does not exist, it will be created. |
| Virtual machine name | The name of the Threat Detection server in the Hyper-V management console. |
| Number of virtual machine cores | The number of machine cores (8 or 16). NOTE: 16 cores is recommended, 8 cores can be used if processing less than 5 million events per day. |
| Network adapter | The script returns the list of available network adapters for the Threat Detection server. Select one from the list. |

| Property | Description |
|----------------------|--|
| VLAN identifier | The virtual local area network (VLAN) identifier which is a number between 1 and 4094. (This is only required if your network uses a VLAN.) |
| Hostname | Fully qualified domain name of the Threat Detection server registered in DNS. For example: hostname.yourcompany.com |
| IP address | Static IPv4 address of the Threat Detection server. |
| Subnet mask | Subnet mask for the Threat Detection server. For example: 255.255.255.0 |
| Default gateway | IP address of the default gateway for the Threat Detection server. |
| DNS | DNS server IP for the Threat Detection server. |
| Integration Password | Password required for the integration between Change Auditor and the Threat Detection server. The integration password is used during the Threat Detection configuration. The password must be 8-24 characters and can only include the following supported values: a-z, A-Z, 1-0, @, \$. Maintain this password for use when creating the Threat Detection configuration. |
| Root Password | The root password. It must be 8-24 characters and can only include the following supported values: a-z, A-Z, 1-0, @, \$. |

- 5 Review and confirm the Threat Detection server settings. To continue enter **Yes**. To change the properties, enter **No**.

The Hyper-V Threat Detection server will now be deployed. This may take several minutes.

- 6 If you are using System Center Virtual Machine Manager (SCVMM) to manage your Hyper-V hosts, refresh the Virtual Machine Manager (VMM) dashboard to display the Threat Detection server.
 - a Open the Virtual Machine Manager (VMM) dashboard. Under **VMs and Services**, select **All Hosts**.
 - b Right-click the Hyper-V host where the Threat Detection server is hosted and click **Refresh Virtual Machines**.

Quest recommends that you take a checkpoint of the newly deployed virtual server. This allows you to revert to a clean state without redeploying the server if you need to start over or re-create a configuration.

You are now ready to create a Threat Detection configuration in Change Auditor. See [Creating a Threat Detection configuration](#).

- i** **NOTE:** The Threat Detection server uses Dynamic MAC address for its network adapter. If you are using SCVMM to manage your Hyper-V hosts and you plan to move the Threat Detection server from one Hyper-V server to another, ensure that after moving, the server is allocated an unused MAC address or alternatively change the address to a static MAC address.

Hyper-V resource control settings

After you have deployed the Threat Detection server, you can select to adjust the Hyper-V processor settings to reserve an amount of processor capacity for a specific virtual machine or, alternatively, configure which virtual machine is given priority in your environment.

Change Auditor's deployment of a Threat Detection server uses the system defaults unless otherwise specified. To change the values for these properties, open the virtual machine's setting, select the Processor, and configure the associated resource control setting.

Table 3. Hyper-V CPU settings

| Property | Description | Best Practice |
|-----------------|--|--|
| Reserve | The percentage of logical processor resources that are reserved for the Threat Detection server. For example, if the host machine has 8 logical CPUs, then setting this value to 25% would reserve 2 of those CPUs for the Threat Detection server. The default value is dynamic based on the CPU. | Set this value to 100% to ensure the Threat Detection server will have access to the resources that it requires. |
| Relative Weight | Determines how the CPU is distributed when you want to set which virtual machine takes priority when there is contention for the processor. For example, a virtual machine with a relative weight of 200, receives twice as much processor time than one set to 100. The default value for all virtual machines is 100. | The weight ranges from 1-10000. To give the Threat Detection server priority, assign it with a higher weight than all other computers in your environment. |

Upgrading the Threat Detection server

For the Threat Detection system to function properly, the Threat Detection server must be compatible with the installed version of Change Auditor. To see if your Threat Detection server is compatible or if an upgrade is required see [Reviewing configuration status](#).

The upgrade process is dependent on your current version.

- [Upgrade from Change Auditor version 7.0.2](#)
- [Upgrade from Change Auditor version 7.0 and 7.0.1](#)

i **IMPORTANT:** Quest recommends that you take a snapshot (for ESX deployments) and a checkpoint (for Hyper-v deployments) of the Threat Detection server before beginning the upgrade process. This allows you to revert to the initial state.

For details see:

- [vSphere documentation](#)
- [Microsoft documentation](#)

Upgrade from Change Auditor version 7.0.2

You can upgrade your existing Threat Detection server with the `Update-CAThreatDetectionServer` command.

To upgrade the Threat Detection server:

- 1 Download the update package (UpdateTDServer-7.0.3.11486.zip) from <https://support.quest.com/change-auditor/7.0.3/download-new-releases>.
- 2 Run the `Update-CAThreatDetectionServer` command.

i **NOTE:** To run the command, you must have the Change Auditor PowerShell module installed and imported. By default, it is installed with the Change Auditor client and coordinator. You must also be a member of the Change Auditor Administrator group.

This command performs a series of steps to complete the upgrade of the Threat Detection Server:

- The update package is uploaded to the coordinator that you connected to through the `Connect-CAClient` command. A message displays when the upload is complete.
- The coordinator then uploads the update package to the Threat Detection server.

- The upgrade process will then begin on the Threat Detection server. The upgrade will take about 15 minutes to complete.
- 3 You can monitor the upgrade progress through the Change Auditor client under Administration Tasks | Configuration | Threat Detection or by running the [Get-CAThreatDetectionConfiguration](#) command.

Once complete, the configuration state will be “Configured”, the upgrade status will be “Upgrade succeeded”, and the Threat Detection server version will be updated to the current version.

i | **NOTE:** Change Auditor provides a sample script (UpdateThreatDetectionServer.ps1) that can be used to perform the upgrade. By default the script is located here: C:\Program Files\Quest\ChangeAuditor\Client\PowerShell Sample Scripts.

Update-CAThreatDetectionServer

Run this command to upgrade the Threat Detection sever.

Table 4. Available parameters

| Parameter | Description |
|------------------|--|
| -Connection | A connection obtained by using the Connect-CAClient command. |
| -FullPackagePath | The path for the update package. |

Example: Upgrade the Threat Detection server

```
Update-CAThreatDetectionServer -Connection $connection -FullPackagePath
C:\Users\UserA\Downloads\UpdateTDServer-7.0.3.11486.zip.
```

Upgrade from Change Auditor version 7.0 and 7.0.1

You can upgrade your existing Threat Detection server by running an update script and a series of configuration commands on the Threat Detection server. This will ensure that your existing configuration and Threat Detection information is maintained.

To upgrade the Threat Detection server:

- Download the update package (UpdateTDServer-7.0.3.11486.zip) from <https://support.quest.com/change-auditor/7.0.3/download-new-releases>.
- Log on to the Threat Detection server and upload the update package to the server. For details see, [Upload the update package to the Threat Detection server](#).
- Upgrade the Threat Detection server by running the update script. For details see, [Upgrade the Threat Detection server](#) and [Update-CAThreatDetectionServer](#).
- Join the Threat Detection server to the coordinator’s domain to enable single sign-on capability to the Threat Detection dashboard. For details see, [Join the Threat Detection server to the coordinator’s domain](#).
- Configure a service account that is used by the Treat Detection server for communicating with Active Directory to verify single-sign on user access to the dashboard. For details see, [Configure the service account](#).

Upload the update package to the Threat Detection server

To upload the update package to the Threat Detection server

- 1 Log on to the Threat Detection server through your preferred SFTP client with the username 'presidio' and the integration password specified during the Threat Detection server configuration.
i | **NOTE:** Ensure your SFTP client transfer setting is set to Binary before uploading the zip package.
- 2 Upload the UpdateTDServer-7.0.3.11486.zip file to the '/home/presidio' directory.

Upgrade the Threat Detection server

To upgrade the server:

- 1 Log on to the Threat Detection server with the username 'presidio' and the integration password specified during the Threat Detection server configuration.
- 2 Run 'cd /home/presidio/' to change the directory to the presidio home directory.
- 3 Run 'unzip UpdateTDServer-7.0.3.11486.zip' to unzip the update package.
- 4 Run 'cd /home/presidio/UpdateTDServer-7.0.3.11486' to change to the unzipped directory.
- 5 Run './update.sh' to run the upgrade script.
- 6 When prompted, enter the integration password.

The server will now be upgraded; this could take up to 15 minutes to complete.

A log file detailing the results of the update is generated after the update is complete. The log file is located here: /home/presidio/update logs and is called UpdateTDServer-YYYY-MM-DD.log. (Where the date is the date of the update.)

Join the Threat Detection server to the coordinator's domain

To join the server to the coordinator's domain:

- 1 While logged on to the Threat Detection server, open a command prompt.
- 2 Run 'cd /opt/quest/bin/' to change the directory to the Quest tools directory.
- 3 Run 'sudo ./vastool -u < User SamAccountName> join <domain FQDN>' to join the server to the coordinator's domain.
i | **NOTE:** The user must be a domain administrator or have been delegated the following tasks using the Active Directory Delegation Control wizard:
 - Create, delete, and manage user account.
 - Join a computer to the domain.
- 4 When prompted for the "Password for presidio", enter the integration password.
- 5 When prompted for the password for the domain, enter the password of the user account specified in step 3.

The Threat Detection server will now be joined to the domain.

- 6 Run './vastool info domain' to verify that the server is joined to the domain. The command will return the domain for the Threat Detection server.

Configure the service account

To configure the service account:

- 1 While logged on to the Threat Detection server with the username 'presidio' and the integration password specified during the Threat Detection server configuration open a command prompt.
- 2 Run 'cd /opt/quest/sbin' to change the directory to the Quest sbin tools directory.
- 3 Run 'sudo ./setup-mod_auth_vas4' to create the service account.
You will now be prompted with a series of questions, accept the default answers for the prompts.
- 4 When prompted for a sufficiently privileged domain account, enter the domain administrator account (SAMAccountName).
- 5 Accept the default answer to change group of /etc/opt/quest/vas/HTTP.keytab to Apache.
- 6 Specify any SPN aliases (if required) or Enter to finish.
- 7 Run 'sudo service httpd restart' to restart the httpd service to finish the configuration.
The service account will now be created in Active Directory.
- 8 Verify that the service account has been created in the Computers container in the same domain as the Threat Detection server. The service account will be a user account with the same name as the Threat Detection server with "HTTP" appended to it.

Creating a Threat Detection configuration

A Threat Detection configuration must be created to view activity, receive alerts, and analyze anomalies on the dashboard.

When a configuration is created, the Threat Detection server is automatically joined to your coordinator's domain and an associated service account is created. This is required to enable single-sign on to the Threat Detection dashboard.

To create a Threat Detection configuration

- 1 From Change Auditor select **Administration Tasks | Configuration | Threat Detection**.
- 2 Enter the Threat Detection server fully qualified domain name and integration password you created when deploying the Threat Detection server.
- 3 Enter the account used to join the Threat Detection server to your coordinator's domain. (Use this format for the account: <Domain>\<User Name>.)
 - i** **NOTE:** The user must be a domain administrator or have been delegated the following tasks using the Active Directory Delegation Control wizard:
 - Create, delete, and manage user account.
 - Join a computer to the domain.
- 4 Select how many days of historical events should be sent to Threat Detection server. For information on how to determine the best amount for you, see [Historical events and your baseline calculations](#).
- 5 Select **Apply Changes**.

Reviewing configuration status

The status of the Threat Detection configuration is displayed on the configuration page.

To see the Threat Detection configuration status

- 1 Select **Administration Tasks | Configuration | Threat Detection**.
- 2 Click **Refresh**.

Table 5. Available configuration states

| State | Description |
|--------------------|--|
| Configured | The Threat Detection server is properly configured. |
| Not configured | The Threat Detection server is not configured. See Creating a Threat Detection configuration . NOTE: If you see this status after removing a configuration and want to configure Threat Detection again, see Removing a configuration for details. |
| Update is required | An update is required on the Threat Detection server. See Upgrading the Threat Detection server . |
| License required | A valid Threat Detection license has not been applied. |
| License expired | The Threat Detection license has expired. |

Configured server deployment details

For a configured server, the following deployment details are displayed:

- State of the configuration.
- How many historical events have been sent to Threat Detection server.
- Status of the Threat Detection server.
- Status of the data processing. For example, building baseline.
- Threat Detection server version.
- Threat Detection subscription ID.
- Starting point in time for events to send.
- Subsystems that contain the event data that is being sent.
- Whether the Threat Detection subscription is enabled.
- How often how often (in milliseconds) events are sent.
- Interval (in milliseconds) that a heartbeat check is made for the configuration.
- Batch size. (The maximum number of events to include in a single notification message.)
- Url for notifications.
- Url for heartbeat notifications.
- When the last event was sent.
- Last event response (For example OK, HTTP 429 - Too many events being sent, and HTTP 401 - Unauthorized access.)
- When the last heartbeat was sent.

- When the last heartbeat response. (For example OK, HTTP 429 - Too many events being sent, and HTTP 401 - Unauthorized access.)
- Number of events sent.
- Number of batches sent.
- Number of heartbeats sent.
- Time of the event that was last sent.
- List of coordinators permitted to send events.
- The coordinator that is sending events. If the subscription is disabled, this is the last coordinator that sent events.

Removing a configuration

Deleting the configuration only removes configuration information from Change Auditor. It does not remove data or configuration on the Threat Detection server.

If you are removing the configuration as a part of a clean up process, you can delete the Threat Detection server after removing configuration.

If you are removing the configuration and plan to start over, you can either revert to a snapshot from a previously deployed (but not configured) Threat Detection server or deploy a new Threat Detection server.

i | **NOTE:** When you join the server to the domain during configuration, Change Auditor creates a computer and service account in the domain required for Integrated Windows Authentication. The computer and service account must be removed manually from the domain when a configuration is removed.

To remove a Threat Detection configuration

- 1 Select **Administration Tasks | Configuration | Threat Detection**.
- 2 Click **Remove Configuration**.

This removes the Threat Detection configuration from Change Auditor.

Historical events and your baseline calculations

Before the Threat Detection server can generate alerts, it needs to establish user behavior baseline. The baseline is built by processing 30 days of historical or real time events. Refer to the Change Auditor Threat Detection User Guide for information about baseline modeling.

When you create the Threat Detection configuration, you can specify how many days of historical events should be sent to the Threat Detection server to create the baseline.

i | **NOTE:** The baseline is more accurate if it is built using the exact configuration of events that you plan to analyze on an ongoing basis. If a new event is enabled after the initial baseline has been built (for instance, the User authenticated through Kerberos event) it may initially be treated as an anomaly as there is no history of it in the baseline.

Table 6. How to determine which type of events to use for a baseline

| Type of events to use | When to use... |
|---|---|
| Real-time events (0 days) NOTE: It will take at least 30 days before you start seeing alerts in the Threat Detection dashboard. | <ul style="list-style-type: none">• For a new installation of Change Auditor where no events have been collected.• If you just enabled events that need to be analyzed by Change Auditor Threat Detection. |
| Historical events (more than 0 days) | <ul style="list-style-type: none">• If you have been collecting all events supported by Change Auditor Threat Detection.• If you are not purging any of the events supported by Change Auditor Threat Detection. |

Use the following as guidance on the number of days to specify when you create your Threat Detection configuration:

- You should not specify more days than the number of days of events that exist in the Change Auditor database.
- You can enter between 1 and 90 days.
- If you specify less than 30 days, Threat Detection uses real time events to continue to build a baseline until 30 days of event have been analyzed.
- If you specify more than 30 days, the Threat Detection server starts generating alerts for any abnormal activity that happened after 30 days.

Threat Detection configuration commands

- [Adding the PowerShell module](#)
- [Viewing available commands and help](#)
- [Connecting to Change Auditor](#)
- [Managing a Threat Detection configuration](#)

Adding the PowerShell module

Change Auditor comes with a PowerShell module for you to use to manage your Threat Detection deployment. It is installed when you install the Windows client or a coordinator.

i | **NOTE:** Windows PowerShell version 3.0 or higher is required.

To import the Change Auditor PowerShell module:

- 1 Open a Windows PowerShell window and type the following at the Windows PowerShell command prompt:

```
Import-Module <path>
```

Where "<path>" is the file path for the ChangeAuditor.PowerShell.dll assembly found in the Change Auditor Windows client or Change Auditor coordinator folder.

- 2 To ensure that the module was added, type the following at the Windows PowerShell command prompt:

```
Get-Module -All
```

The registered PowerShell modules are listed.

Viewing available commands and help

- To view all available Change Auditor commands, enter:

```
Get-Command -Module ChangeAuditor.PowerShell
```

- To view help on each command including the syntax, enter:

```
Get-Help cmdletName
```

- To view an interactive command browser that shows you the layout of commands and the help for the commands, enter:

```
Show-Command cmdletName
```

Threat Detection sample scripts

Change Auditor includes the following sample scripts to help you configure and manage Threat Detection:

- CreateThreatDetectionConfiguration.ps1
- GetThreatDetectionConfiguration.ps1
- ModifyThreatDetectionConfiguration.ps1
- RemoveThreatDetectionConfiguration.ps1
- UpdateThreatDetectionServer.ps1

i | **NOTE:** By default they are located here: C:\Program Files\Quest\ChangeAuditor\Client\PowerShell Sample Scripts

Connecting to Change Auditor

- [Connect-CAClient](#)

Connect-CAClient

Most Change Auditor commands require a connection to a coordinator. You can make multiple connections to different coordinators or deployments in the same script as long as the version of Change Auditor is the same.

This connection can be assigned to a variable and used for any command that requires it. Use this command to search for a suitable coordinator in a Change Auditor installation and create a connection. Suitable coordinators are those which you have access to and can be located by searching through Active Directory service connection points.

NOTE: Connections are closed when the PowerShell session is ended or disconnected.

Table 1. Available parameters

| Parameter | Description |
|--|--|
| -Credential (Optional) | Windows credentials specifying the user to connect to the Change Auditor installation. All operations using this connection will be authorized as this user. When not specified, the current client running PowerShell is used. |
| -CoordinatorConnectionPoint (Optional) | Specify to use a specific coordinator found from a previous call to Find-CACoordinators. |
| -SelectLocalCoordinator (Optional) | Create a connection to the local coordinator. |
| -InstallationName (Optional) | The installation name to connect to. If an installation cannot be found with this name, no connection is made. If more than one Change Auditor installation exists in the current forest, this parameter is mandatory. Omitting it results in a connection failure due to ambiguity. |
| -DomainName (Optional) | The name of the domain where the Change Auditor installation exists. |
| -ComputerName (Optional) | The computer to connect to. |
| -Port (Optional) | The port to connect to. |
| -WaitForServiceReady (Optional) | The number of seconds to wait for the connected coordinator service to be ready. NOTE: If not specified, when the Change Auditor coordinator is not ready for connections due to an in-progress install or upgrade, an error is returned. The maximum is 144,000 seconds, or 10 hours. |

Example: Connect to the installation “XYZ” in the specified domain

```
Connect-CAClient -InstallationName 'XYZ' -DomainName 'DomainName.com'
```

Managing a Threat Detection configuration

- [New-CAThreatDetectionConfiguration](#)
- [Get-CAThreatDetectionConfiguration](#)
- [Set-CAThreatDetectionConfiguration](#)
- [Remove-CAThreatDetectionConfiguration](#)

New-CAThreatDetectionConfiguration

Use this command to create a Threat Detection configuration.

- i** | **NOTE:** When a configuration is created, the Threat Detection server is automatically joined to your coordinator's domain and an associated service account is created. This is required to enable single-sign on to the Threat Detection dashboard.
- i** | **NOTE:** Quest recommends that you use the sample script `CreateThreatDetectionConfiguration.ps` from `Program Files\Quest\ChangeAuditor\Client\PowerShell Sample Scripts`.
- i** | **NOTE:** When you create a new configuration, the underlying webhook subscription that is generated is marked as internal. This ensures that the required subscription cannot be removed from an existing configuration.

Table 2. Available parameters

| Parameter | Description |
|---------------------------------|---|
| -Connection | A connection obtained by using the <code>Connect-CAClient</code> command. See Connecting to Change Auditor . |
| -TDServer | The Threat Detection server fully qualified domain name. |
| -TDPassWord | The password used to access the Threat Detection server. Use the integration password that was specified during the Threat Detection server deployment. |
| -DomainAdminCredential | The credentials required to join the Threat Detection server to your coordinator's domain to enable access to the dashboard using windows integrated authentication. NOTE: The user must be a domain administrator or have been delegated the following tasks using the Active Directory Delegation Control wizard: <ul style="list-style-type: none">▪ Create, delete, and manage user account.▪ Join a computer to the domain. |
| -HistoricalDays (Optional) | The number of days of historical events to send to the Threat Detection server. For details, see Historical events and your baseline calculations . |
| -AllowedCoordinators (Optional) | The DNS or NetBIOS name of the coordinators permitted to send events. If none are specified, all coordinators installed at the time of configuration are permitted to send events. NOTE: The list order does not determine which coordinator is selected to send events. |

Example: Creating a configuration

```
New-CAThreatDetectionConfiguration -Connection $connection -TDServer  
'ServerName.Domain.Com' -TDPassWord $TDPassWord -DomainAdminCredential  
$DomainAdminCredential -HistoricalDays 30  
-AllowedCoordinators @('machine1.domain.com','machine2.domain.com')
```

Get-CAThreatDetectionConfiguration

Use this command to view the Threat Detection configuration information and information about the associated subscription.

Table 3. Available parameters

| Parameter | Description |
|-------------|---|
| -Connection | A connection obtained by using the Connect-CAClient command. See Connecting to Change Auditor . |

Example: Review Threat Detection configuration details

```
Get-CAThreatDetectionConfiguration -Connection $connection
```

Command output

The command returns the following information. For more information about some of these settings see the Change Auditor SIEM Integration Guide.

Table 4. Available configuration information

| Setting | Description |
|-----------------------|---|
| TDServer | The Threat Detection server fully qualified domain name. |
| ConfigurationState | State of the configuration: <ul style="list-style-type: none"> Configured: Threat Detection has been configured Unconfigured: Threat Detection has not been configured A valid Change Auditor Threat Detection license is required |
| HistoricalDays | How many days of historical events have been sent to Threat Detection server. |
| TDServerStatus | Status of the Threat Detection server: <ul style="list-style-type: none"> Online Offline |
| DataProcessingStatus | Status of the data processing. For example, building baseline. |
| TDServerVersion | Threat Detection server version. |
| TDSubscriptionId | Threat Detection subscription ID. |
| StartTime | Starting point in time for events to send. |
| Subsystems | Subsystems that have been selected for event sending. |
| TDSubscriptionEnabled | Whether the Threat Detection subscription is enabled. |
| NotificationInterval | How often how often (in milliseconds) events are sent. |
| HeartbeatInterval | Interval (in milliseconds) that a heartbeat check is made for the configuration. |
| BatchSize | Batch size. The maximum number of events to include in a single notification message. |
| NotificationUrl | Url for notifications. |
| HeartbeatUrl | Url for heartbeat notifications. |
| LastEventTime | When the last event was sent. |
| LastEventResponse | Last event response (For example OK, HTTP 429 - Too many events being sent, and HTTP 401 - Unauthorized access.) |
| LastHeartbeatTime | When the last heartbeat was sent. |
| LastHeartbeatResponse | The last heartbeat response. (For example OK, HTTP 429 - Too many events being sent, and HTTP 401 - Unauthorized access.) |
| EventsSent | Number of events sent. |
| BatchesSent | Number of batches sent. |
| HeartbeatsSent | Number of heartbeats sent. |
| BookmarkTime | Time the last event was sent. |

Table 4. Available configuration information

| Setting | Description |
|---------------------|---|
| AllowedCoordinators | List of coordinators permitted to send events. |
| LastCoordinator | The coordinator that is sending events. If the subscription is disabled, this is the last coordinator that sent events. |

Set-CAThreatDetectionConfiguration

Use this command to modify the list of allowed coordinators for the Threat Detection configuration.

Table 5. Available parameters

| Parameter | Description |
|---------------------------------|--|
| -Connection | A connection obtained by using the Connect-CAClient command. See Connecting to Change Auditor . |
| -AllowedCoordinators (Optional) | The DNS or NetBIOS name of the coordinators permitted to send events. If none are specified, all coordinators installed at the time of configuration are permitted to send events. NOTE: The list order does not determine which coordinator is selected to send events. |

Example: Modifying a configuration

```
Set-CAThreatDetectionConfiguration -Connection $connection -AllowedCoordinators @('machine1.domain.com', 'machine2.domain.com')
```

Example: To clear a previous list of allowed coordinators

```
Set-CAThreatDetectionConfiguration -Connection $connection -AllowedCoordinators @()
```

Remove-CAThreatDetectionConfiguration

Use this command to remove a Threat Detection configuration.



NOTE:

Deleting the configuration only removes configuration information from Change Auditor. It does not remove data or configuration on the Threat Detection server.

- If you are removing the configuration as a part of a clean up process, you can delete the Threat Detection server after removing configuration.
- If you are removing the configuration and plan to start over, you can either revert to a snapshot from a previously deployed (but not configured) Threat Detection server or deploy a new Threat Detection server.
- When you join the server to the domain during configuration, Change Auditor creates a computer and service account in the domain required for Integrated Windows Authentication. The computer and service account must be removed from the domain when a configuration is removed.

Table 6. Available parameters

| Parameter | Description |
|-------------|---|
| -Connection | A connection obtained by using the Connect-CAClient command. See Connecting to Change Auditor . |

Example: Remove the Threat Detection configuration

```
Remove-CAThreatDetectionConfiguration -Connection $connection
```

Appendix: System Architecture

- [Threat Detection system overview](#)

Threat Detection system overview

The integration process to analyze events includes the following:




Figure 1. Event processing for Threat Detection

- 1 Change Auditor agents collect events from various systems and the coordinator writes the events into the database.
- 2 Users create a Threat Detection configuration using the Change Auditor client.
- 3 As part of the configuration, the coordinator creates the webhook subscription to send events to the Threat Detection server. The subscription contains information such as where to send events (the URL of the webhook receiver in the Threat Detection server), which events to include, and the coordinator responsible for event forwarding.
- 4 The designated coordinator continually queries events from the Change Auditor database and sends them to the webhook receiver in the Threat Detection server.
- 5 Threat Detection server performs event modeling and scoring.
- 6 Threat indicators, alerts, and risky users are displayed in the Threat Detection dashboard.

Quest creates software solutions that make the benefits of new technology real in an increasingly complex IT landscape. From database and systems management, to Active Directory and Microsoft 3665 management, and cyber security resilience, Quest helps customers solve their next IT challenge now. Around the globe, more than 130,000 companies and 95% of the Fortune 500 count on Quest to deliver proactive management and monitoring for the next enterprise initiative, find the next solution for complex Microsoft challenges and stay ahead of the next threat. Quest Software. Where next meets now. For more information, visit www.quest.com.

Our brand, our vision. Together.

Our logo reflects our story: innovation, community and support. An important part of this story begins with the letter Q. It is a perfect circle, representing our commitment to technological precision and strength. The space in the Q itself symbolizes our need to add the missing piece—you—to the community, to the new Quest.

Contacting Quest

For sales or other inquiries, visit www.quest.com/contact.

Technical support resources

Technical support is available to Quest customers with a valid maintenance contract and customers who have trial versions. You can access the Quest Support Portal at <https://support.quest.com>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request.
- View Knowledge Base articles.
- Sign up for product notifications.
- Download software and technical documentation.
- View how-to-videos.
- Engage in community discussions.
- Chat with support engineers online.
- View services to assist you with your product.