



One Identity Manager 9.3

Attestation Administration Guide

Copyright 2025 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC .

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.
Attn: LEGAL Dept
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our website (<http://www.OneIdentity.com>) for regional and international office information.

Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal/trademark-information.aspx. All other trademarks are the property of their respective owners.

Legend

 **WARNING:** A WARNING icon highlights a potential risk of bodily injury or property damage, for which industry-standard safety precautions are advised. This icon is often associated with electrical hazards related to hardware.

 **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.

One Identity Manager Attestation Administration Guide
Updated - 06 January 2025, 10:31

For the most recent documents and product information, see [Online product documentation](#).

Contents

Attestation and recertification	10
One Identity Manager users for attestation	11
Attestation base data	13
Attestation types	13
Default attestation types	14
Additional tasks for attestation types	14
Overview of the attestation type	14
Assigning attestation procedures	15
Attestation procedure	15
General main data of an attestation procedure	15
Templates for attestation procedures	17
Providing information about attestation objects	19
Defining reports for attestation	20
Defining snapshot content	20
Default attestation procedures	22
Additional tasks for attestation procedures	22
Overview of the attestation procedure	22
Assigning approval policies to attestation procedures	23
Creating a copy	23
Attestation schedules	24
Default schedules	27
Assigning attestation policies	28
Assigning policy collections	28
Schedule overview	29
Starting schedules immediately	30
Compliance frameworks	30
Additional tasks for compliance frameworks	31
Compliance framework overview	31
Assigning attestation policies	31
Chief approval team	32
Attestation policy owners	32

Standard reasons for attestation	34
Predefined standard reasons for attestations	35
Providing terms of use for attestation	36
Assigning files to terms of use	36
Displaying the terms of use overview	37
Attestation policies	37
General main data of attestation policies	38
Specifying risk indexes for attestation guidelines	43
Default attestation policies	43
Additional tasks for attestation policies	44
The attestation policy overview	44
Assigning approvers to attestation policies	44
Assigning compliance frameworks to attestation policies	45
Mitigating controls	45
Running attestation for single objects	47
Showing or hiding conditions	48
Copy attestation policies	48
Showing selected objects	48
Deleting attestation policies	49
Disabling attestation policies	49
Sample attestation	50
Creating, editing, deleting samples	50
General main data of samples	51
Managing sampling data	52
Generating sampling data automatically	52
Using samples with attestation policies	53
Displaying the sample overview	54
Default sample for attesting memberships in system entitlements	54
Default sample for attesting identities	55
Grouping attestation policies	55
Creating and editing policy collections	56
General main data of policy collections	57
Assigning policy collections to attestation policies	58
Disabling policy collections	58
Deleting policy collections	59

Default policy collections	59
Custom mail templates for notifications	60
Creating and editing attestation mail templates	60
General properties of a mail template	61
Creating and editing a mail definition	62
Using base object properties	63
Use of hyperlinks in the Web Portal	64
Customizing email signatures	65
Copying mail templates for attestation	66
Displaying attestation mail templates previews	66
Deleting mail templates for attestation	67
Custom notification processes	67
Suspending attestation	68
Automatic attestation of policy violations	68
Approval processes for attestation cases	69
Approval policies for attestations	69
General main data of approval policies	70
Default approval policies	71
Editing approval workflows	71
Validity checking	71
Copying approval policies	72
Approval workflow for attestations	72
Working with the Workflow Editor	73
Setting up approval workflows	76
Editing approval levels	77
Editing approval steps	78
Properties of an approval step	78
Connecting approval levels	83
Copying approval workflows	83
Deleting approval workflows	84
The approval workflow overview	84
Default approval workflows	85
Selecting attestors	85
Default approval procedures	86
Determining attestors via attestation objects	88

Determining attestors via the primary role of the identity to attest	90
Determining attestors using the service item of the attestation object	92
Determining attestors via attestation object managers	93
Determining managers or members of a role as attestors	97
Determining attested identities as attestors	98
Determining identities linked to user accounts as attestors	99
Determining target system managers as attestors	99
Determining attestors via product owners	101
Determining attestors via owners of the attestation objects	102
Determining owners or approvers of attestation policies	105
Calculated approval	106
Approvals to be made externally	107
Waiting for further approval	108
Setting up approval procedures	109
General main data of an approval procedure	110
Queries for finding attestors	111
Specifying permitted approval procedures for tables	114
Overview of approval procedures	115
Copying an approval procedure	115
Deleting approval procedures	116
Determining the responsible attestors	116
Setting up multi-factor authentication for attestation	118
Prevent attestation by identity awaiting attestation	119
Automatic acceptance of attestation approvals	120
Phases of attestation	121
Setting up the staging phase	122
Criteria for the Staging phase	123
Setting up the challenge phase	124
Setting up withdrawal of entitlements	125
Attestation by peer group analysis	126
Configuring peer group analysis for attestations	128
Approval recommendations for attestations	129
Criteria for approval recommendations for attestation	130
Configuring approval recommendations for attestation	133
Managing attestation cases	135

Getting more information	135
Appointing other attestors	136
Escalating an attestation case	137
Attestors cannot be established	139
Automatic approval on timeout	140
Halting an attestation case on timeout	141
Attesting by chief approval team	143
Attestation sequence	145
Starting attestation	145
Attestation case overview	147
Approval sequence	147
Attestation history	148
Modifying approval workflows for pending attestation cases	149
Closing attestation cases for deactivated identities	151
Deleting attestation cases	151
Notifications in the attestation case	153
Requesting attestation	154
Reminding attestors	154
Scheduling attestation requests	156
Reminding attestors about attestation objects	156
Granting or denying attestation cases	157
Notifying delegates	158
Canceling attestation cases	159
Escalation of attestation cases	160
Delegating attestations	160
Rejecting approvals	160
Notifications with questions	161
Notifications from additional attestors	161
Link for verifying new external users	162
Default mail templates	162
Attestation by mail	163
Processing attestation mails	166
Adaptive cards attestation	166
Using adaptive cards for attestations	168
Adding and deleting recipients and channels	169

Creating, editing, and deleting adaptive cards for attestations	170
Creating, editing, and deleting adaptive cards templates for attestations	171
General main data for adaptive cards	173
Deploying and evaluating adaptive cards for attestations	173
Disabling adaptive cards	174
Approving attestation cases in the Manager	175
Displaying attestation cases of an attestor	175
Displaying information about attestation objects	176
Assigning extended properties to attestation cases	177
Displaying incomplete attestation runs	178
Canceling incomplete attestation runs	178
Displaying canceled attestation runs	179
Reports about attestations	180
Default attestations	181
Configuring withdrawal of entitlements	182
Attesting system entitlements	183
System role attestation	185
Application role attestation	188
Business role attestation	188
Configuring sample attestation of identities and their entitlements	189
User attestation and recertification	190
One Identity Manager users for attesting and recertifying users	190
Configuring user attestation and recertification	192
Attesting new users	193
Self-registration of new users in the Web Portal	193
Adding new identities using a manager or administrator for identities	195
Importing new identity main data	198
Scheduled attestation	199
Limiting attestation objects for certification	199
Recertifying existing users	201
Preparing for recertification	202
The recertification sequence	202
Limiting attestation objects for recertification	203
Certifying new roles and organizations	204
One Identity Manager users for certifying roles and organizations	205

Configuring certification of new departments	207
Configuring certification of new cost centers	207
Configuring certification of new locations	208
Configuring certification of new business roles	209
Configuring certification of new application roles	210
Mitigating controls for attestation policies	211
General main data of mitigating controls	211
Additional tasks for mitigating controls	212
Mitigating controls overview	212
Assigning attestation policies	212
Calculating mitigating controls for attestation policies	213
Setting up attestation in a separate database	214
Requirements for the central database	214
Setting up work databases	215
Setting up synchronization between central and work databases	217
Setting up and running attestations in the work database	218
Appendix: Configuration parameters for attestation	220
About us	236
Contacting us	236
Technical support resources	236
Index	237

Attestation and recertification

Managers or others responsible for compliance can use the One Identity Manager attestation feature to certify correctness of entitlements, requests, or exception approvals either scheduled or on demand. Recertification is the term generally used to describe regular certification of entitlements. One Identity Manager uses the same workflows for recertification and attestation.

There are attestation policies defined in One Identity Manager for carrying out attestations. Attestation policies specify which objects are attested when, how often, and by whom. Once an attestation is performed, One Identity Manager creates attestation cases that contain all the necessary information about the attestation objects and the attestor responsible. The attestor checks the attestation objects. They verify the correctness of the data and initiate any changes that need to be made if the data conflicts with internal rules.

Attestation cases record the entire attestation sequence. Each attestation step in the attestation case can be audit-proof reconstructed. Attestations are run regularly using scheduled tasks. You can also trigger single attestations manually.

Attestation is complete when the attestation case has been granted or denied approval. You specify how to deal with granted or denied attestations on a company basis.

TIP: One Identity Manager provides various default attestation procedures for different data situations and default attestation procedures. If you use these default attestation procedures, you can configure how you deal with denied attestations.

For more information, see [Configuring withdrawal of entitlements](#) on page 182.

To use attestation functionality

- In the Designer, set the **QER | Attestation** configuration parameter.

If you disable the configuration parameter at a later date, model components and scripts that are no longer required, are disabled. SQL procedures and triggers are still carried out. For more information about the behavior of preprocessor relevant configuration parameters and conditional compiling, see the *One Identity Manager Configuration Guide*.

One Identity Manager users for attestation

The following users are used for attestation.

Table 1: Users

User	Tasks
Administrators for attestation cases	<p>Administrators are assigned to the Identity & Access Governance Attestation Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Define attestation procedures and attestation policies. • Create approval policies and approval workflows. • Specify which approval procedure to use to find attestors. • Set up attestation case notifications. • Configure attestation schedules. • Enter mitigating controls. • Create and edit risk index functions. • Monitor attestation cases. • Manage application roles for attestation policy owners. • Maintain members of the chief approval team.
One Identity Manager administrators	<p>One Identity Manager administrator and administrative system users Administrative system users are not added to application roles.</p> <p>One Identity Manager administrators:</p> <ul style="list-style-type: none"> • Create customized permissions groups for application roles for role-based login to administration tools in the Designer as required. • Create system users and permissions groups for non role-based login to administration tools in the Designer as required. • Enable or disable additional configuration parameters in the Designer as required. • Create custom processes in the Designer as required. • Create and configure schedules as required.
Attestation policy	<p>Owners of attestation policies must be assigned to a child applic-</p>

User	Tasks
owners	<p>ation role of the Identity & Access Governance Attestation Attestation policy owners application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Are responsible for its content and handle the attestation policies assigned to it. • Assign the attestation procedure, approval policy, and calculation schedule. • Assign approvers, mitigating controls, and compliance frameworks. • Monitor attestation cases and attestation runs.
Attestors	<ul style="list-style-type: none"> • Check attestation objects in the Web Portal. • Confirm data correctness. • Initiate changes if data conflicts with internal rules. <p>Attestors in charge are determined through approval procedures.</p>
Compliance and security officer	<p>Compliance and security officers must be assigned to the Identity & Access Governance Compliance & Security Officer application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • View all compliance relevant information and other analysis in the Web Portal. This includes attestation policies, company policies and policy violations, compliance rules, and rule violations and risk index functions. • Edit attestation polices.
Auditors	<p>Auditors are assigned to the Identity & Access Governance Auditors application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • See the Web Portal all the relevant data for an audit.
Chief approval team	<p>The chief approver must be assigned to the Identity & Access Governance Attestation Chief approval team application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Approve using attestation cases. • Assign attestation cases to other attestors.

User	Tasks
Attestors for external users	<p>Attestors for external users must be assigned to the Identity & Access Governance Attestation Attestors for external users application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Attests new, external identities.

Attestation base data


The attestation framework and the objects to be attested are specified in the attestation policy. You require certain base data to define attestation policies.

Attestation types:	Attestation types on page 13
Approval policies:	Approval policies for attestations on page 69
Approval workflows:	Approval workflow for attestations on page 72
Approval procedures:	Setting up approval procedures on page 109
Attestation procedures:	Attestation procedure on page 15
Schedules:	Attestation schedules on page 24
Compliance frameworks:	Compliance frameworks on page 30
Mail templates:	Custom mail templates for notifications on page 60
Chief approval team:	Chief approval team on page 32
Standard reasons:	Standard reasons for attestation on page 34
Adaptive cards:	Creating, editing, and deleting adaptive cards for attestations on page 170

Attestation types

Attestation types are used to group attestation procedures. These make it easier to assign a matching attestation procedure to the attestation policies.

To edit attestation types

1. Select the **Attestation > Basic configuration data > Attestation types** category.
2. Select an attestation type in the result list and run the **Change main data** task.
– OR –
Click  in the result list.
3. Edit the attestation type main data.
4. Save the changes.

Default attestation types

You cannot edit default attestation types and their attestation procedure assignments.

One Identity Manager supplies attestation types by default. These attestation types are assigned to default attestation procedures. They are necessary for setting up attestation policies in the Web Portal.

To display default attestation types

- In the Manager, select the **Attestation > Basic configuration data > Attestation types > Predefined** category.

For more information about using default attestation types, see the *One Identity Manager Web Portal User Guide*.

Additional tasks for attestation types

After you have entered the main data, you can run the following tasks.

Overview of the attestation type

You can display the most important information about an attestation type on the overview form.

To obtain an overview of an attestation type

1. In the Manager, select the **Attestation > Basic configuration data > Attestation types** category.
2. Select the attestation type in the result list.
3. Select the **Attestation type overview** task.

Assigning attestation procedures

Use this task to assign the selected attestation type to all the attestation procedures that should be included in the group.


To assign attestation procedures to attestation types

1. In the Manager, select the **Attestation > Basic configuration data > Attestation types** category.
2. Select the attestation type in the result list.
3. Select the **Assign attestation procedure** task.

In the **Add assignments** pane, assign the attestation procedures.

TIP: In the **Remove assignments** pane, you can remove attestation procedure assignments.


To remove an assignment

- Select the attestation procedure and double-click .
4. Save the changes.

Attestation procedure

Attestation procedures specify the attestation base object. They define which attestation object properties are to be attested. Attestation object data can be provided in list or report form.

To edit an attestation procedure

1. In the Manager, select the **Attestation > Basic configuration data > Attestation procedures** category.
2. Select an attestation procedure in the result list and run the **Change main data** task.
 - OR -
 - Click  in the result list.
3. Edit the attestation procedure main data.
4. Save the changes.

General main data of an attestation procedure

Enter the following properties for an attestation procedure.

Table 2: General main data of an attestation procedure

Property	Description
Attestation procedure	Any name for the attestation procedure.
Attestation type	Criteria for grouping attestation procedures. Attestation types make it easier to assign a matching attestation procedure to the attestation policies.
Description	Text field for additional explanation.
Report	<p>Report for the attestor containing all the necessary information about the attestation objects.</p> <p>Predefined reports are supplied in a drop-down. If you do not want to assign a report, you can specify additional information about the attestation objects in the Property 1-4 (template) fields.</p> <p>NOTE: The report will be generated in the language given in the attestation guideline if there are translations available for it in the database. Otherwise, the default language is used, which is stored as a fallback variant in the database information.</p>
Snapshot content	<p>Contents of the snapshot created for an attestation object.</p> <p>If no report is specified, a snapshot of the object to be attested is created. You can configure the contents of the snapshot.</p> <ul style="list-style-type: none">• Attestation object: descriptive properties only<p>Only the descriptive properties of the attestation object itself are included in the snapshot. Referenced objects are not included.</p><p>Descriptive properties include mandatory columns, columns indexed for searching, or columns marked for logging data changes.</p>• Object references: only related objects 1-3<p>Only the object references specified in the Related objects 1-3 (Template) input fields are included in the snapshot. All other references objects are not included.</p><p>If the option is not set, all references objects are included in the snapshot.</p>• Object references: descriptive properties only<p>Only the descriptive properties of the referenced objects are included in the snapshot. Foreign keys are not included.</p><p>If the option is disabled, all properties of referenced objects, including all foreign keys and the X columns, are included in the snapshot.</p>

Property	Description
Table	<p>Database table in which the attestation objects are to be found (= attestation base object). All tables, which fulfill the following conditions, are available:</p> <ol style="list-style-type: none"> The table contains a XObjectKey column. The table type is Table, View, ReadOnly, or Proxy. The usage type is User data, Materialized data, or Read only data. It is not the basetree table. It is not an assignment table referencing basetree. Table belongs to the application data model. Table is not disabled. <p>For more information about table types and usage types, see the <i>One Identity Manager Configuration Guide</i>.</p>
Preprocessor condition	<p>Specifies the preprocessor configuration parameters on which the attestation procedure depends. Attestation procedures that are disabled through a preprocessor condition are not displayed in One Identity Manager.</p>

Detailed information about this topic



- [Attestation types](#) on page 13
- [Providing information about attestation objects](#) on page 19
- [Defining reports for attestation](#) on page 20
- [Defining snapshot content](#) on page 20
- [Templates for attestation procedures](#) on page 17
- [Displaying information about attestation objects](#) on page 176

Templates for attestation procedures

On the **Templates** tab, define the templates that supply additional information about the attestation objects displayed in the Web Portal or in reports.

Table 3: Attestation procedure templates

Property	Description
Grouping column 1-3 (template)	A value template for formatting the value used to group and filter pending attestation cases in the Web Portal.

Property	Description
	Enter a value template in dollar notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
Grouping column 1-3	Column headers for Grouping column 1-3 (template) . The columns are multi-language. To enter a translation, click  .
Grouping column 1-3 (text template)	Text template describing the facts of an attestation case when grouped according to the respective grouping column. The value of the grouping columns 1-3 can be included in the text template by using variables.
Property 1-4 (template)	Templates for formulating a value that supplies additional information about the attestation object. Use these fields to show additional information about the attestation object in the Web Portal. Enter a value template in dollar notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
Property 1-4	Column headers for Property 1-4 (template) . The columns are multi-language. To enter a translation, click  .
Risk index template	Template for formulating the value for the attestation case's risk index. Enter a value template in dollar notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
Text template	Text template describing the facts about a single attestation case. The value of the grouping columns 1-3 and properties 1-4 can be included in the text template by using variables. <ul style="list-style-type: none"> • Variables %StructureDisplay1% - StructureDisplay3%: for values of grouping columns 1-3 • Variables %PropertyInfo1% - %PropertyInfo4%: for values of properties1-4 <p>Example: Should the "%PropertyInfo1%" identity be assigned to the "%StructureDisplay2%" primary cost center?</p>
Related object 1-3 (template)	Template for formulating an object key for an object related to the attestation base object. Required for displaying pending attestation cases in the Web Portal. Enter a value template in dollar notation. This template can access the base object properties and the properties of all objects connected through foreign keys. Define the display value for this object in Grouping column 1-3 (template) .

Example

You want to attest Active Directory group memberships. Group the attestation cases by user account display value, Active Directory group display value, and the display value of associated identities. The Web Portal group's canonical name should be displayed with every group membership in the Active Directory. The attestation case's risk index can be determined from the group membership's risk index. The object key for the object relation can be found from the Active Directory user account. The information required about the attestation objects will be summarized in a report. To do this, enter the following data on the main data form.

Table 4: Example of an attestation case definition

Property	Value
Table	Database table ADSAccountInADSGroupTotal
Report	<report name>
Grouping column 1	\$UID_ADSSAccount[d]\$
Grouping column 2	\$UID_ADSSGroup[d]\$
Grouping column 3	\$FK(UID_ADSSAccount).UID_Person[d]\$
Property 1 (template)	\$FK(UID_ADSSGroup).CanonicalName\$
Risk index template	\$RiskIndexCalculated\$
Object relation 1	\$FK(UID_ADSSAccount).XObjectKey\$

Related topics

- [General main data of an attestation procedure](#) on page 15
- [Defining snapshot content](#) on page 20
- [Displaying information about attestation objects](#) on page 176

Providing information about attestation objects

To help attestors make their approval decisions, attestation cases must provide all necessary information about the attestation objects. This information can be provided either by a report or by a snapshot of the respective attestation object.

1. Report

Depending on the selected table, it is possible to choose between different default reports. To specify yourself what information the attestors are given, use the Report Editor to design a report.

2. Snapshot

If no report is specified, a snapshot of the object to be attested is created. This contains all object properties, objects referenced by foreign key, and their properties. The scope of the snapshot can be reduced.

Related topics

- [General main data of an attestation procedure](#) on page 15
- [Defining reports for attestation](#) on page 20
- [Defining snapshot content](#) on page 20
- [Displaying information about attestation objects](#) on page 176

Defining reports for attestation

Define attestation reports with the Report Editor. For more information about creating reports with the Report Editor, see the *One Identity Manager Configuration Guide*.

Note the following when you define a report for attestation:

- The base table for the report must be identical to the one for the attestation procedure.
- Enter **Attestation** as the report category. This ensures that the report is displayed in the **Report** menu of the attestation procedure.
- In order to create a report for each attestation object with the information relating exactly to the attestation object, define a `ObjectKeyBase` parameter for the attestation object in the report. Use the parameters in the data source definition for the report in **Condition** field.

Example: `XObjectKey = @ObjectKeyBase`

Default reports

One Identity Manager supplies some default reports for attestation. These are used in the default attestation procedures, amongst others.

TIP: Default reports cannot be changed. If you want to customize a default report, create a copy and edit it according to your requirements. Then assign the copy to the attestation procedure.

Related topics

- [Providing information about attestation objects](#) on page 19

Defining snapshot content

If no report is specified in the attestation procedure, the attestors receive all necessary information about the respective attestation object from a snapshot that is generated when

the attestation cases are created. The snapshot contains all object properties, the objects referenced by foreign key, and their properties. Therefore, a snapshot can contain a lot of information that is not necessarily required by attestation. Also, if the table containing the attestation objects has a lot of foreign key columns, generating the attestation operations can take a long time.

To speed up creating the snapshots and to limit their content to the required information, in the attestation procedures, it is possible to configure which object properties and object references are included in the snapshots. The contents of snapshots can be limited as follows:

- **Attestation object: descriptive properties only**

Only the descriptive properties of the attestation object itself are included in the snapshot. Referenced objects are not included.

Descriptive properties include mandatory columns, columns indexed for searching, or columns marked for logging data changes.

- **Object references: only related objects 1-3**

Only the object references specified in the **Related objects 1-3 (Template)** input fields are included in the snapshot. All other references objects are not included.

If the option is not set, all references objects are included in the snapshot.

- **Object references: descriptive properties only**

Only the descriptive properties of the referenced objects are included in the snapshot. Foreign keys are not included.

If the option is disabled, all properties of referenced objects, including all foreign keys and the X columns, are included in the snapshot.

If none of these options is selected, the snapshot contains:

- All the attestation object properties
- All objects references by foreign key
- All properties of the referenced objects

TIP: If the attestation cases are created, the ATT_GetAttestationObject script generated the snapshots for the attestation objects. If properties other than those determined in this way are to be displayed in the Web Portal, you can either override the script on a custom basis or enter a custom education rule in the AttestationCase.ReportContent column.

Related topics

- [Providing information about attestation objects](#) on page 19
- [General main data of an attestation procedure](#) on page 15
- [Templates for attestation procedures](#) on page 17

Default attestation procedures

One Identity Manager provides a default approval procedure for default attestation of new users and recertification of all identities stored in the One Identity Manager database. Moreover, default approval procedures are supplied through which the different roles, user accounts, and system entitlements mapped in the Unified Namespace can be attested. Using these default approval policies you can create attestation procedures easily in the Web Portal.

To display default attestation procedures

- In the Manager, select the **Attestation > Basic configuration data > Attestation procedures > Predefined** category.

For more information about using default attestation procedures, see the *One Identity Manager Web Portal User Guide*.

Related topics

- [User attestation and recertification](#) on page 190
- [Configuring withdrawal of entitlements](#) on page 182

Additional tasks for attestation procedures

After you have entered the main data, you can run the following tasks.

Overview of the attestation procedure

You can display the most important information about an attestation procedure on the overview form.

To obtain an overview of an attestation procedure

1. In the Manager, select the **Attestation > Basic configuration data > Attestation procedures** category.
2. Select the attestation procedure in the result list.
3. Select the **Attestation procedure overview** task.

Assigning approval policies to attestation procedures

Use this task to assign the selected attestation procedure to the approval policies that should be used in this attestation procedure. All approval policies permitted for the attestation base object are listed.


To assign approval policies to attestation procedures

1. In the Manager, select the **Attestation > Basic configuration data > Attestation procedures** category.
2. Select the attestation procedure in the result list.
3. Select **Assign approval policies** task.

In the **Add assignments** pane, assign the approval policies.

TIP: In the **Remove assignments** pane, you can remove approval policy assignments.

To remove an assignment

- Select the approval policy and double-click .
4. Save the changes.

Which approval policies are permitted depends on the approval procedures in use. Approval procedures dictate to which tables an approval procedure can be assigned.

Related topics

- [Specifying permitted approval procedures for tables](#) on page 114

Creating a copy

You can make copies of attestation procedures and those copies allow you to modify default attestation procedures.

To copy an attestation procedure

1. In the Manager, select the **Attestation > Basic configuration data > Attestation procedures** category.
2. Select the attestation procedure in the result list.
3. Select **Create copy** task.
4. Confirm the security prompt with **Yes**.
5. Decide whether the condition types should be copied for the attestation wizard in the Web Portal as well.

Condition types are required if attestation policies are created and edited with the attestation wizard in the Web Portal. For more information about this, see the *One Identity Manager Web Portal User Guide*.

6. Edit the attestation procedure copy and save the changes.

The attestation procedure copy is displayed on the main data form with the name **<Name of original attestation procedure>(copy)**. You can rename and edit this attestation policy.

Attestation schedules

Use schedules to automate attestation. These specify when and how often attestation cases are created. One Identity Manager supplies several default schedules for attestation.

To edit schedules

1. In the Manager, select the **Attestation > Basic configuration data > Schedules** category.

The result list shows all schedules configured for attestation policies (AttestationPolicy task).

2. Select a schedule in the result list and run the **Change main data** task.



- OR -

Click  in the result list.

3. Edit the schedule's main data.
4. Save the changes.

Enter the following properties for a schedule.

Table 5: Schedule properties

Property	Meaning
Name	Schedule ID. Translate the given text using the  button.
Description	Detailed description of the schedule. Translate the given text using the  button.
Table	Table whose data can be used by the schedule. Schedules for the attestation must refer to the AttestationPolicy table.
Enabled	Specifies whether the schedule is enabled. NOTE: Only active schedules are run. Enabled schedules are run automatically if the QBM Schedules configuration parameter is set.
Time zones	Unique identifier for the time zone that is used for running the schedule. Choose between Universal Time Code or one of the time zones in the

Property	Meaning
	<p>menu.</p> <p>NOTE:</p> <p>When you add a new schedule, the time zone is preset to that of the client from which you started the Manager.</p>
Start (date)	The day on which the schedule should be run for the first time. If this day conflicts with the defined interval type, the first run is on the next available day based on the start date.
Validity period	<p>Period within which the schedule is run.</p> <ul style="list-style-type: none"> • If the schedule will be run for an unlimited period, select the Unlimited duration option. • To set a validity period, select the Limited duration option and enter the day the schedule will be run for the last time in End (date).
Occurs	<p>Interval in which the task is run. Other settings may be required depending on the settings.</p> <ul style="list-style-type: none"> • Every minute: The schedule is run once a minute. The starting point is calculated from the rate of occurrence and the interval type. • Hourly: The schedule is run at defined intervals of a multiple of hours such as every two hours. <ul style="list-style-type: none"> • Under Repeat every, specify after how many hours the schedule is run again. • The starting point is calculated from the rate of occurrence and the interval type. • Daily: The schedule is run at specified times in a defined interval of days such as every second day at 6am and 6pm. <ul style="list-style-type: none"> • Under Start time, specify the times to run the schedule. • Under Repeat every, specify after how many days the schedule is run again. • Weekly: The schedule is run at a defined interval of weeks, on a specific day, at a specified time such as every second week on Monday at 6am and 6pm. <ul style="list-style-type: none"> • Under Start time, specify the times to run the schedule. • Under Repeat every, specify after how many weeks the schedule is run again. • Specify the set day of the week for running the schedule. • Weekly: The schedule is run at a defined interval of months, on a specific day, at a specified time such as every second month on the

Property	Meaning
----------	---------

1st and the 15th at 6am and 6pm.

- Under **Start time**, specify the times to run the schedule.
- Under **Repeat every**, specify after how many months the schedule is run again.
- Specify the days of the month (1st - 31st of the month).

NOTE: If the **Monthly** interval type with the sub interval **29, 30** or **31** does not exist in this month, the last day of the month is used.

Example:

A schedule that is run on the 31st day of each month is run on April 30th. In February, the schedule is run on the 28th (or 29th in leap year).

- **Yearly:** The schedule is run at a defined interval of years, on a specific day, at a specified time such as every year on the 1st, the 100th, and the 200th day at 6am and 6pm.

- Under **Start time**, specify the times to run the schedule.
- Under **Repeat every**, specify after how many years the schedule is run again.
- Specify the days of the year (1st - 366th day of the year).

NOTE: If you select the 366th day of the year, the schedule is only run in leap years.

- **Monday, Tuesday, Wednesday, Thursday, Friday, Saturday, Sunday:** The schedule is run on a defined day of the week, in specified months, at specified times such as every second Saturday in January and June at 10am.

- Under **Start time**, specify the times to run the schedule.
- Under **Repeat every**, specify after how many days of the month the schedule is run again. The values **1 to 4, -1** (last day of the week), and **-2** (last day but one of the week) are permitted.
- Specify in which month to run the schedule. The values **1 to 12** are permitted. If the value is empty, the schedule is run each month.

Start time	Fixed start time Enter the time in local format for the chosen time zone. If there is a list of start times, the schedule is started at each of the given times.
------------	--

Repeat every	Rate of occurrence for running the schedule within the selected time interval.
--------------	--

Last planned	Activation time calculated by the DBQueue Processor. Activation times are
--------------	---

Property	Meaning
run/Next planned run	recalculated whilst the schedule is running. The time of the next run is calculated from the interval type, rate of occurrence, and the start time. NOTE: One Identity Manager provides the start information in the time zone of the client where the program was started. Changes due to daylight saving are taken into account.

Related topics

- [Default schedules](#) on page 27
- [Assigning attestation policies](#) on page 28
- [Assigning policy collections](#) on page 28
- [Schedule overview](#) on page 29

Default schedules

One Identity Manager supplies the following attestation schedules by default:

Table 6: Default attestation schedules

Schedule	Description
Half-Yearly	Default schedules for any attestation.
Monthly	
Quarterly	
Weekly (Monday)	
Yearly	
Deactivated	Default schedule for default attestation policies. The schedule is disabled by default and should not be enabled. To run attestation, assign another schedule to the attestation policies and enable that one.
Daily	Default schedules for any attestation. This schedule is assigned to the New user certification attestation policy by default.

Related topics

- [Preparing for recertification](#) on page 202
- [Scheduled attestation](#) on page 199

Assigning attestation policies

Use this task to assign attestation policies to the selected schedule, which will runs them. If you double-click on one of the attestation policies you assign it to the current schedule.

To assign attestation policies to a schedule

1. In the Manager, select the **Attestation > Basic configuration data > Schedules** category.
2. Select the schedule in the result list.
3. Select the **Assign attestation polices** task.
4. In **Add assignments**, double-click the attestation policies that are to be assigned.
5. Save the changes.

To change an assignment

1. In the Manager, select the **Attestation > Basic configuration data > Schedules** category.
2. Select the schedule in the result list.
3. Select the **Assign attestation polices** task.
4. Select **Show objects already assigned to other objects** in the assignment form context menu.
This shows attestation policies that are already assigned in other schedules.
5. In the **Add assignments** pane, double-click on one of these attestation policies.
The attestation policy is assigned to the currently selected schedule.
6. Save the changes.

NOTE: Assignments cannot be removed. Attestation policies must be assigned a schedule. It is compulsory.

Related topics

- [Attestation schedules](#) on page 24
- [General main data of attestation policies](#) on page 38
- [Assigning policy collections](#) on page 28

Assigning policy collections

Use this task to assign policy collections to the selected schedule that will run them. The assignment form displays all the policy collections that are assigned to the selected schedule.

To assign policy collections to a schedule

1. In the Manager, select the **Attestation > Basic configuration data > Schedules** category.
2. Select the schedule in the result list.
3. Select the **Assign policy collections** task.
4. In the **Add assignments** pane, double-click the policy collections you want to assign.
5. Save the changes.

To change an assignment

1. In the Manager, select the **Attestation > Basic configuration data > Schedules** category.
2. Select the schedule in the result list.
3. Select the **Assign policy collections** task.
4. Select the **Show objects already assigned to other objects** menu item in the assignment form's context menu.
This displays policy collections that are already assigned to other schedules.
5. In the **Add assignments** pane, double-click on one of these policy collections.
The policy collection is assigned to the currently selected schedule.
6. Save the changes.

NOTE: Assignments cannot be removed. Schedule assignments are compulsory for policy collections.

Related topics

- [Attestation schedules](#) on page 24
- [General main data of policy collections](#) on page 57
- [Assigning attestation policies](#) on page 28

Schedule overview

You can display the most important information about a schedule on the overview form.

To obtain an overview of a schedule

1. In the Manager, select the **Attestation > Basic configuration data > Schedules** category.
2. Select the schedule in the result list.
3. Select the **Schedule overview** task.

Starting schedules immediately

NOTE: If a schedule is started, it starts attestation for all active attestation policies assigned with the schedule.

To start a schedule immediately

1. In the Manager, select the **Attestation > Basic configuration data > Schedules** category.
2. Select the schedule in the result list.
3. Select the **Start immediately** task.


A message appears confirming that the schedule was started.

Compliance frameworks

Compliance frameworks are used for classifying attestation policies, compliance rules, and company policies according to regulatory requirements.

Compliance frameworks can be organized hierarchically. To do this, assign a parent framework to the compliance frameworks.

To edit compliance frameworks

1. In the Manager, select the **Attestation > Basic configuration data > Compliance frameworks** category.
2. Select a Compliance Framework in the result list and run the **Change main data** task.
- OR -
Click  in the result list.
3. Edit the compliance framework main data.
4. Save the changes.

Enter the following properties for compliance frameworks.

Table 7: Compliance framework properties

Property	Description
Compliance framework	Name of the compliance framework.
Parent framework	Parent compliance framework in the framework hierarchy. Select an existing compliance framework in the drop-down for organizing compliance frameworks hierarchically.

Property	Description
Manager/supervisor	Application role whose members are allowed to edit all attestation policies assigned to this compliance framework
Description	Text field for additional explanation.

Additional tasks for compliance frameworks

After you have entered the main data, you can run the following tasks.

Compliance framework overview

You can display the most important information about a compliance framework on the overview form.

To obtain an overview of a compliance framework

1. In the Manager, select the **Attestation > Basic configuration data > Compliance Frameworks** category.
2. Select the compliance framework from the result list.
3. Select the **Compliance framework overview** task.

Assigning attestation policies

Use this task to assign attestation policies to the selected compliance framework.


To assign attestation policies to a compliance framework

1. In the Manager, select the **Attestation > Basic configuration data > Compliance frameworks** category.
2. Select the compliance framework from the result list.
3. Select the **Assign attestation polices** task.

Assign the attestation policies in **Add assignments**.

TIP: In the **Remove assignments** pane, you can remove attestation policy assignments.

To remove an assignment

- Select the approval policy and double-click .
4. Save the changes.

Chief approval team

Sometimes, approval decisions cannot be made for attestation cases because an attestor is not available or does not have access to One Identity Manager tools. To complete these attestations, you can define a chief approval team whose members are authorized to intervene in the approval process at any time.

There is a default application role in One Identity Manager for the chief approval team. Assign this application role to all identities who are authorized to approve, deny, cancel attestations in special cases, or to authorize other attestors. For more information about application roles, see the *One Identity Manager Authorization and Authentication Guide*.

Table 8: Default application role for chief approval team

User	Tasks
Chief approval team	<p>The chief approver must be assigned to the Identity & Access Governance Attestation Chief approval team application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Approve using attestation cases.• Assign attestation cases to other attestors.


To add members to the chief approval team

1. In the Manager, select the **Attestation > Basic configuration data > Chief approval team** category.
2. Select the **Assign identities** task.

In the **Add assignments** pane, assign the identities who are authorized to approve all attestations.

TIP: In the **Remove assignments** pane, you can remove assigned identities.

To remove an assignment

- Select the identity and double-click .
3. Save the changes.

Detailed information about this topic

- [Attesting by chief approval team](#) on page 143

Attestation policy owners

Default application roles for attestation policy owners are available in One Identity Manager. These owners are entitled to edit attestation policies. For more

information about application roles, see the *One Identity Manager Authorization and Authentication Guide*.

Table 9: Default application roles for attestation policy owners

User	Tasks
Attestation policy owners	<p>Owners of attestation policies must be assigned to a child application role of the Identity & Access Governance Attestation Attestation policy owners application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Are responsible for its content and handle the attestation policies assigned to it.• Assign the attestation procedure, approval policy, and calculation schedule.• Assign approvers, mitigating controls, and compliance frameworks.• Monitor attestation cases and attestation runs.
Direct owners	<p>Direct owners are all identities assigned to an attestation policy as an Owner (UID_PersonOwner column). Members of this application role are determined through a dynamic role.</p>
Owner role	<p>This application role or child application role can be assigned to attestation policies as an Owner (application role) (UID_AERoleOwner column) This allows you to specify groups of identities as owners for attestation policies. Identities are added as members to application roles by direct assignment.</p>


To add members to the owner role

1. In the Manager, select the **Attestation > Basic configuration data > Attestation policy owners > Owner role** category.
2. Select the **Assign identities** task.

In the **Add Assignments** pane, assign the identities that are allowed to edit an attestation policy.


TIP: In the **Remove assignments** pane, you can remove the assignment of identities.

To remove an assignment

- Select the identity and double-click .
3. Save the changes.

If you want to restrict owners' permissions to individual attestation policies, create child application roles.

To specify an owner role for an attestation policy

1. Log in to the Manager as an attestation administrator (**Identity & Access Governance | Attestation | Administrators** application role).
2. Select the **Attestation > Attestation policies** category.
3. Select the attestation policy in the result list.
4. Select the **Change main data** task.
5. In the **Owner (application role)** drop-down, select the owner role.
- OR -
Click  next to the drop-down to create a new application role.
 - a. Enter the application role name and assign the **Identity & Access Governance | Attestation | Attestation policy owners | Owner role** parent application role.
 - b. Click **OK** to add the new application role.
6. Save the changes.
7. Assign identities to this application role who are permitted to edit the attestation policy.

Related topics


- [General main data of attestation policies](#) on page 38

Standard reasons for attestation

For attestations, you can specify reasons in the Web Portal that explain the individual approval decisions. You can freely formulate this text. You also have the option to predefine reasons. The attestors can select a suitable text from these standard reasons in the Web Portal and store it with the attestation case.

Standard reasons are displayed in the attestation history.

To create or edit standard reasons

1. In the Manager, select the **Attestation > Basic configuration data > Standard reasons** category.
2. Select a standard reason in the result list and run the **Change main data** task.
- OR -
Click  in the result list.
3. Edit the main data of a standard reason.
4. Save the changes.

Enter the following properties for the standard reason.

Table 10: General main data of a standard reason

Property	Description
Standard reason	Reason text as displayed in the Web Portal and in the attestation history.
Description	Text field for additional explanation.
Automatic Approval	Specifies whether the reason text is only used for automatic approvals by One Identity Manager. This standard reason cannot be selected by manual approvals in the Web Portal. Do not set the option if the you want to select the standard reason in the Web Portal.
Additional text required	Specifies whether an additional reason should be entered in free text for the attestation.
Usage type	Usage type of standard reason. Assign one or more usage types to allow filtering of the standard reasons in the Web Portal.

Related topics

- [Predefined standard reasons for attestations](#) on page 35

Predefined standard reasons for attestations

One Identity Manager provides predefined standard reasons. These are added to the attestation case by One Identity Manager during automatic approval. You can use the usage type to specify which standard reasons can be selected in the Web Portal.

To change the usage type

1. In the Manager, select the **Attestation > Basic configuration data > Standard reasons > Predefined** category.
2. Select the standard reason whose usage type you want to change.
3. Select the **Change main data** task.
4. In the **Usage type** menu, set all the actions where you want to display the standard reason in the Web Portal.

Unset all the actions where you do not want to display the default reason.
5. Save the changes.


Related topics

- [Standard reasons for attestation](#) on page 34

Providing terms of use for attestation

Attestation policies can have terms of use stored with them that are presented to attestors as a PDF file. For example, this can be the current policies.

To add or edit terms of use

1. In the Manager select the **Attestation > Terms of use** category.
2. In the result list, select a terms of use and run the **Change main data** task.
- OR -
Click  in the result list.
3. Edit the terms of use main data.
 - **Terms of use:** Terms of use identifier.
 - **Description:** Text field for additional explanation.
 - **Content:** Description of the terms of use. The complete text is provided as a PDF file.
 - **Multifactor authentication required:** Specifies whether multifactor authentication via the configured provider is required by requests to accept the terms of use.
4. Save the changes.
5. Assign the terms of use to attestation policies.

Related topics


- [General main data of attestation policies](#) on page 38
- [Assigning files to terms of use](#) on page 36

Assigning files to terms of use

The full-text of the terms of use is provided as a PDF file in different languages. These PDF files are loaded into the One Identity Manager database and can be displayed when requesting and approving a product or for attestors in the Web Portal. The PDF file matching the user's login language is offered.

To load PDF files for the terms of use into the database

1. In the Manager select the **Attestation > Terms of use** category.
2. Select the terms of use in the result list.
3. Select the **Assign files** task.
4. Click **Add**.

5. In the **Language** drop-down, select the language you want the PDF file to be in.
All the languages that are configured as login languages in the One Identity Manager tools are provided.
6. Next to the **File** field, click .
7. In the **Open** dialog, select the PDF file and click **Open**.
8. To load other PDF files, click **Add** and repeat the step.
9. Save the changes.

To delete a PDF file of a terms of use from the database

1. In the Manager select the **Attestation > Terms of use** category.
2. Select the terms of use in the result list.
3. Select the **Assign files** task.
4. In the list, select a file and click **Remove**.
5. Save the changes.

Related topics

- [Providing terms of use for attestation](#) on page 36

Displaying the terms of use overview

You can display the most important information about a tag on the overview form.

To obtain an overview of the terms of use

1. In the Manager select the **Attestation > Terms of use** category.
2. Select the terms of use in the result list.
3. Select the **Terms of use overview** task.


Related topics

- [Providing terms of use for attestation](#) on page 36

Attestation policies

Attestation policies specify the concrete conditions for attestation. Use the main data form to enter the attestation procedure, approval policy and the schedule. You can use a WHERE clause to limit the attestation objects.



To edit attestation policies

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select an attestation policy in the result list and run the **Change main data** task.
- OR -
Click  in the result list.
3. Edit the main data of the attestation policy.
4. Save the changes.

General main data of attestation policies

Enter the following data for attestation policies.

Table 11: General main data of attestation policies

Property	Description
Attestation policy	Name of the attestation policy.
Attestation procedure	Attestation procedure used for attesting. Attestation procedures are displayed in a drop-down grouped by attestation type.
Approval policies	Approval policy for determining the attestor for the attestation objects.
Owner	Creator of the attestation policy. The name of the user logged in to One Identity Manager is entered here by default. This can be changed.
Owner (application role)	Application role whose members may edit the attestation policy. To create a new application role, click  . Enter the application role name and assign a parent application role.
Policy collection	Policy collection used to start the attestation. You can use policy collections to group together various attestation policies and run them collectively.
Sample	Sample that can be used for attestations. A sample can only be assigned to exactly one attestation policy. To create a new sample, click  . Enter the name of the sample and assign the table from which to take the data for the sample. You cannot assign samples to default attestation policies.
Time required (days)	Number of days within which a decision must be made over the attestation. Enter 0 if you do not want to specify a particular processing period.

Property	Description
	<p>Weekends and holidays are included by default when calculating the due date of attestation cases. If weekends and holidays should be treated as working days, set the QER Attestation UseWorkingHoursDefinition, QBM WorkingHours IgnoreHoliday, and QBM WorkingHours IgnoreWeekend configuration parameters. For more information about calculating working hours, see the <i>One Identity Manager Configuration Guide</i>.</p> <p>One Identity Manager does not stipulate which actions are carried out if processing times out. Define your own custom actions or evaluations to deal with this situation.</p>
Description	Text field for additional explanation.
Risk index	<p>Specifies the risk for the company if attestation for this attestation policy is denied. Use the slider to enter a value between 0 and 1.</p> <ul style="list-style-type: none"> • 0: No risk. • 1: The denied attestation is a problem. <p>This input field is only visible if the QER CalculateRiskIndex configuration parameter is activated.</p>
Risk index (reduced)	<p>Show the risk index taking mitigating controls into account. The risk index for an attestation policy is reduced by the Significance reduction value for all assigned mitigating controls.</p> <p>This input field is only visible if the QER CalculateRiskIndex configuration parameter is activated. The value is calculated by One Identity Manager and cannot be edited.</p>
Calculation schedule	<p>Schedule for running attestation. Attestation cases are started automatically at the times specified by the schedule.</p> <p>If a policy collection is assigned, the input field is disabled. The policy collection's schedule applies.</p>
Language	<p>Language in which the information to be attested is displayed.</p> <p>If a language is not specified, the information is generated in the same language as the device that started the attestation.</p>
Disabled	<p>Specifies whether the attestation policy is disabled or not.</p> <p>Attestation cases cannot be added to disabled attestation policies and, therefore, attestation is not carried out. Disabled attestation policies can be deleted.</p> <p>Closed attestation cases can be deleted once the attestation policy is disabled.</p>
Display objects	Specifies whether the objects affected by the attestation policy are calculated and displayed on the overview form in the Manager.

Property	Description
to be attested in the Manager	
No empty attestation runs	<p>Specifies whether to generate an empty attestation run if there can be no attestation object found when calculating the attestation case.</p> <p>Enabled: Does not generate an empty attestation run. This means that it is not possible to subsequently determine whether the attestation was started normally.</p> <p>Disabled: An attestation run is generated without an attestation case. This means it is possible that the attestation was started but no objects to attest were found.</p>
Always send notification of pending attestations	<p>Specifies whether to send adaptive cards or individual emails about pending attestations even if the QER Attestation MailTemplateIds RequestApproverByCollection configuration parameter is set.</p>
Close obsolete tasks automatically	<p>Specifies whether pending attestation cases are canceled if new ones are added.</p> <p>If attestation is started and this option is set, new attestation cases are created according to the condition. All pending, obsolete attestation cases for newly determined attestation objects of this attestation policy are stopped. Attestation cases for attestation objects that are not recalculated, remain intact.</p>
Obsolete tasks limit	<p>Specifies the maximum number of closed attestation cases for each attestation object that should remain in the database when closed attestation cases are deleted.</p> <ul style="list-style-type: none"> • 0: No attestation cases are deleted. • > 0: The given number of closed attestation cases for each attestation object to remain in the database. <p>The value can be edited only if the Delete attestation cases function is configured. For more information, see Deleting attestation cases on page 151.</p>
Terms of use	<p>Terms of use are presented to attestors as a PDF file. For example, this can be the current policies.</p>
Reason for decision	<p>Reason that is given if the Close obsolete tasks automatically option is set and pending attestation cases are automatically closed.</p>
Output format	<p>Format in which the report is generated.</p> <p>This drop-down is only visible if the QER Attestation AllowAllReportTypes configuration parameter is set. If the configuration parameter is not set, the default PDF format is used because it is the</p>

Property	Description
	only format that is version compatible.
Reason type on approval	<p>Specifies which type of reason is required when the attestation is granted approval.</p> <ul style="list-style-type: none"> • Optional: A reason can be provided if required. • Reason required (standard or free): A standard reason must be selected or a reason given with any text. • Free text required: A reason must be given with freely selected text.
Reason type on denial	<p>Specifies which type of reason is required when the attestation is denied approval.</p> <ul style="list-style-type: none"> • Optional: A reason can be provided if required. • Reason required (standard or free): A standard reason must be selected or a reason given with any text. • Free text required: A reason must be given with freely selected text.
Edit connection...	Starts the WHERE clause wizard. Use this wizard to create or edit a condition to determine the attestation objects from the database table specified in the attestation procedure.
Condition	<p>Data query for finding attestation objects.</p> <p>This shows the input field for new attestation policies.</p> <p>NOTE: For sample attestation, the condition must also query the sampling data. There is a template to help set up the condition. This condition can be changed if necessary.</p> <p>Example of attesting identities using a sample:</p> <pre> EXISTS (SELECT 1 FROM (SELECT ObjectKeyItem FROM QERPickedItem WHERE UID_QERPickCategory = '\$UID_QERPickCategory\$') as X WHERE X.ObjectKeyItem = Person.XObjectKey) </pre> <p>Example of attesting user accounts using a sample of identities:</p> <pre> EXISTS (SELECT 1 FROM (SELECT UID_Person FROM Person WHERE EXISTS (SELECT 1 FROM </pre>

Property	Description
	<pre> SELECT ObjectKeyItem FROM QERPickedItem WHERE UID_QERPickCategory = '\$UID_QERPick- Category\$') as X WHERE X.ObjectKeyItem = Person.XObjectKey)) as X WHERE X.UID_Person = UNSAccount.UID_Person) </pre> <p>To show the condition for existing attestation policies, run the Show condition task.</p>
Approval by multi-factor authentication	Attestation of this attestation policy requires multi-factor authentication.
Set certification status to "Certified"	Specifies whether the certification status of the attested object is set to Certified if the attestation case was approved in the end.
Set certification status to "Denied"	Specifies whether the certification status for the attested object is set to Denied if the attestation case was denied in the end.

NOTE: You can only edit attestation policies in the Web Portal that were created in the Web Portal. You will see a corresponding message on the main data form as to whether the attestation policy as created in the Web Portal.

If you want to edit attestation policies like this, create a copy in the Manager.

For more information about editing attestation policies in the Web Portal, see the *One Identity Manager Web Portal User Guide*.

Detailed information about this topic

- [Showing or hiding conditions](#) on page 48
- [Attestation schedules](#) on page 24
- [Disabling attestation policies](#) on page 49
- [Mitigating controls for attestation policies](#) on page 211
- [Setting up multi-factor authentication for attestation](#) on page 118
- [Copy attestation policies](#) on page 48
- [Attestation policy owners](#) on page 32
- [Using samples with attestation policies](#) on page 53
- [Grouping attestation policies](#) on page 55

Related topics

- [Deleting attestation policies](#) on page 49
- [General main data of samples](#) on page 51
- [Attestation by mail](#) on page 163
- [Adaptive cards attestation](#) on page 166
- [Requesting attestation](#) on page 154
- [Reminding attestors](#) on page 154
- [Providing terms of use for attestation](#) on page 36

Specifying risk indexes for attestation guidelines

You can use One Identity Manager to evaluate the risk of attestation cases. To do this, enter a risk index for the attestation policy. The risk index specifies the risk involved for the company in connection with the data to be attested. The risk index is given as a number in the range 0 .. 1. By doing this you specify whether data to be attested is considered not to be a risk (risk index = 0) or whether every denied attestation poses a problem (risk index = 1).

The risk that attestations will be denied approval can be reduced by using the appropriate mitigating controls. Enter these controls as mitigating controls in One Identity Manager. You reduce the risk by the value entered as the significance reduction on the mitigating control. This value is used to calculate the reduced risk index for the attestation policy.

You can create several reports with the Report Editor to evaluate attestation cases depending on the risk index. For more information, see the *One Identity Manager Configuration Guide*.

Risk assessments can be carried out when the **QER | CalculateRiskIndex** configuration parameter is enabled. For more information, see the *One Identity Manager Risk Assessment Administration Guide*.

Detailed information about this topic

- [Mitigating controls for attestation policies](#) on page 211

Default attestation policies

One Identity Manager provides default attestation policies for default attestation of new users and recertification of all identities stored in the One Identity Manager database. In addition to this, default attestation policies are provided through which various roles, memberships in roles, user accounts, and system entitlements mapped in the Unified Namespace can be attested.

To display default attestation policies

- In the Manager, select the **Attestation > Attestation policies > Predefined** category.

You can customize the following properties for default attestation policies:

- Approval policies (if several approval policies can be assigned)
- Owner
- Processing time
- Risk index
- Calculation schedule
- Deactivated
- Close obsolete tasks automatically
- Obsolete tasks limit
- Reason for decision
- Condition

NOTE: You can edit attestation policies, whose condition is stored as a definition (XML), in the Web Portal. The definition (XML) cannot be edited in the Manager. For more information, see the *One Identity Manager Web Portal User Guide*.

Additional tasks for attestation policies

After you have entered the main data, you can run the following tasks.

The attestation policy overview

You can display the most important information about an attestation policy on the overview form.

To obtain an overview of an attestation policy

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list.
3. Select **Attestation policy overview** task.

Assigning approvers to attestation policies

Use this task to assign identities that can be determined as approvers in an attestation case to the selected attestation policy.


To assign approvers to an attestation policy

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list.
3. Select the **Assign approver** task.

In the **Add assignments** pane, assign the approvers.

TIP: In the **Remove assignments** pane, you can remove approver assignments.

To remove an assignment

- Select the approver and double-click .
4. Save the changes.

Detailed information about this topic

- [Selecting attestors](#) on page 85

Assigning compliance frameworks to attestation policies

Use this task to specify which compliance frameworks are relevant for the selected attestation policy. Compliance frameworks are used for classifying attestation policies, compliance rules, and company policies according to regulatory requirements.


To assign compliance frameworks to an attestation policy

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list.
3. Select the **Assign compliance frameworks** task.

In the **Add assignments** pane, assign the compliance frameworks.

TIP: In the **Remove assignments** pane, you can remove compliance framework assignments.

To remove an assignment

- Select the compliance framework and double-click .
4. Save the changes.

Mitigating controls

Mitigating controls describe controls that are implemented if an attestation rule was violated. The attestation can be approved after the next attestation run, once controls have been applied.

To edit mitigating controls

- In the Designer, enable the **QER | CalculateRiskIndex** configuration parameter.

NOTE: If you disable the configuration parameter at a later date, model components and scripts that are no longer required, are disabled. SQL procedures and triggers are still carried out. For more information about the behavior of preprocessor relevant configuration parameters and conditional compiling, see the *One Identity Manager Configuration Guide*.

Detailed information about this topic

- [Mitigating controls for attestation policies](#) on page 211
- [Assigning mitigating controls](#) on page 46
- [Creating mitigating controls for attestation policies](#) on page 46

Assigning mitigating controls

Specify which mitigating controls apply to the selected attestation policy.


To assign mitigating controls to an attestation policy

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list.
3. Select the **Assign mitigating controls** task.

In the **Add assignments** pane, assign the mitigating controls.

TIP: In the **Remove assignments** pane, you can remove mitigating control assignments.

To remove an assignment

- Select the mitigating control and double-click .
4. Save the changes.

Creating mitigating controls for attestation policies

To create a mitigating control for attestation policies

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select an attestation policy in the result list.
3. Select the **Assign mitigating controls** task.
4. Select **Create mitigating controls** task.
5. Enter the main data of the mitigating control.
6. Save the changes.

7. Select the **Assign attestation policies** task.
8. In the **Add assignments** pane, double-click the attestation policies you want to assign.
9. Save the changes.

Detailed information about this topic

- [Mitigating controls for attestation policies](#) on page 211

Running attestation for single objects

Use this task to start attestations independently from a schedule. If you run the task, a separate window is opened. Select the objects to be attested now from a list of all attestation objects. The selection is one-off.

The **Close obsolete tasks automatically** option is not taken into account for the selected attestation objects.

If a sample is assigned to the attestation policy, you can select individual objects from the sampling data. The **Remove items after attestation run** option is not taken into account; the attestation data is not deleted after the attestation run.

To start attestation for the selected objects

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list. Select the **Change main data** task.
3. Select the **Run attestation cases for single objects...** task.

This opens a separate window.

4. In the **Attestation** column, select every object for which attestation is to be run.
5. Click **Run**.

Attestation cases are generated for the selected attestation objects. As soon as DBQueue Processor has processed the task, you will see the newly created attestation cases in the navigation view under the **Attestation runs > <attestation policy> > Attestation runs > <year> > <month> > <day> > Pending attestations** menu item.

6. Click **Close**.

Related topics

- [General main data of attestation policies](#) on page 38
- [General main data of samples](#) on page 51
- [Starting attestation](#) on page 145

Showing or hiding conditions

The condition for finding attestation objects can be viewed and edited in the Where Clause Wizard. The SQL query for this condition can be displayed on the main data form.

To show the condition for finding attestation objects on the main data form

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list and run the **Change main data** task.
3. Select the **Show condition** task.

This displays the **Condition** field on the main data form. The condition is written like a database query WHERE clause. You can edit it directly.

To hide the condition for finding attestation objects

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list and run the **Change main data** task.
3. Select the **Hide condition** task.

The **Condition** field is no longer displayed on the main data form.

Copy attestation policies

You can make copies of attestation policies and use them to modify default attestation policies, for example.

To copy an attestation policy

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list.
3. Select the **Create copy** task.
4. Confirm the security prompt with **Yes**.

The attestation policy copy is displayed on the main data form with the name **Copy of <Name of original attestation policy>**. You can edit this attestation policy.

Showing selected objects

To show a list of attestations found

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list and run the **Change main data** task.
3. Select **Show selected objects** task.

An additional **Result** tab is shown on the main data form. This displays a list of attestation objects found through the condition.

Deleting attestation policies

IMPORTANT: Do not delete attestation policies, for audit reasons.

Attestation policies may still be removed from the One Identity Manager database under specific conditions. Ensure that the attestation policy is archived when deleted.

For more information about data archiving, see the *One Identity Manager Configuration Guide*.

Prerequisite

- The attestation policy is disabled.

To delete an attestation policy

1. In the Manager, select the **Attestation > Attestation policies > Disabled policies** category.
2. Select the attestation policy in the result list and run the **Change main data** task.
3. Select **Delete attestation policy** task.
4. Confirm the security prompt with **Yes**.

The attestation policy is deleted. All associated attestation cases, approval workflows and the attestation history are deleted.

Related topics

- [Disabling attestation policies](#) on page 49

Disabling attestation policies

Attestations are run when the schedule assigned to an attestation policy is enabled. You can disabled attestation policies to prevent attestation cases being created for individual attestation policies.

IMPORTANT: All associated attestation cases are deleted. To be able to trace the changes later, configure how the data is logged. For more information, see [Deleting attestation cases](#) on page 151 and the *One Identity Manager Configuration Guide*.

TIP: Numerous default attestation policies are supplied with One Identity Manager. Check which of the default attestation policies are relevant for your data situation when you set up your database. Disable all unnecessary attestation policies.

To disable an attestation policy

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list and run the **Change main data** task.
3. Set **Disabled**.
4. Save the changes.

Related topics

- [Suspending attestation](#) on page 68
- [Disabling policy collections](#) on page 58

Sample attestation

Sample attestation provides a way to limit the set of attestation objects for an attestation. For example, this can be useful if attesting everyone in an audit would take too long. The sampling data can either be generated automatically or compiled manually.

The One Identity Manager provides a standard sample that is used to attest memberships in system entitlements after organizational changes.

Detailed information about this topic


- [Creating, editing, deleting samples](#) on page 50
- [Managing sampling data](#) on page 52
- [Generating sampling data automatically](#) on page 52
- [Using samples with attestation policies](#) on page 53
- [Displaying the sample overview](#) on page 54
- [Default sample for attesting memberships in system entitlements](#) on page 54

Creating, editing, deleting samples

To be prepare sample attestations:

- Create samples.
- Define the sampling data.
- Assign the samples to the attestation policies that will use them.


To create a sample

1. In the Manager, select the **Attestation > Samples** category.
2. Click  in the result list.
3. Edit the sample's main data.
4. Save the changes.

To edit a sample

1. In the Manager, select the **Attestation > Samples** category.
2. In the result list, select the sample and run the **Change main data** task.
3. Edit the sample's main data.
4. Save the changes.

To delete a sample

1. In the Manager, select the **Attestation > Samples** category.
2. In the result list, select the sample and click .
3. Confirm the security prompt with **Yes**.

Detailed information about this topic

- [General main data of samples](#) on page 51
- [Managing sampling data](#) on page 52
- [Using samples with attestation policies](#) on page 53

General main data of samples

Enter the following main data of a sample.

Table 12: General main data of a sample

Property	Description
Display name	Name of the sample.
Table	Table that contains the selected sampling data.
Manually selected	Specifies whether the sampling data is manually selected.
Remove items after attestation run	Specifies whether the sampling data is deleted from the sample after each attestation run. After each attestation of this sample, the sampling data must be regenerated. The option is not taken into account when attesting individually selected objects.

Related topics

- [Creating, editing, deleting samples](#) on page 50
- [Running attestation for single objects](#) on page 47

Managing sampling data

Sampling data can either be generated automatically or compiled manually. To set sampling data manually, assign sampling items to the samples.


To assign sampling items manually

1. In the Manager, select the **Attestation > Samples > Manually selected** category.
2. Select the sample in the result list.
3. Select the **Assign sampling items** task.

In the **Add assignments** pane, assign sampling items.

TIP: In the **Remove assignments** pane, you can remove the assigned sampling items.

To remove an assignment

- Select the sampling item and double-click .
4. Save the changes.

To display sampling items for automatically selected samples

1. In the Manager, select the **Attestation > Samples > Automatically selected** category.
2. Select the sample in the result list.
3. Select the **Assign sampling items** task.

Related topics

- [Sample attestation](#) on page 50
- [Creating, editing, deleting samples](#) on page 50
- [Generating sampling data automatically](#) on page 52

Generating sampling data automatically

One Identity Manager distinguishes between manual sampling and automatic sampling. Automatic sampling can trigger the generation of sampling data as follows:

- Event-based: All modified objects of an object class (table from which the sampling data is selected) are calculated.

Example: All user accounts whose risk index has increased since the previous attestation.

For the **Monthly organizational changes of identities** default sample, the sampling data are generated event-based.

Prerequisite

- In the sample, the **Manually selected** option is disabled.

To generate sampling data for an event-based sample

- In the Designer, create a process that is generated when changes are made to the table given in the sample. Use the Execute SQL process task from the SQLComponent process component.
 - Determine the value of the SQLStmt parameter with the following query:

```
Dim f As ISqlFormatter = Connection.SqlFormatter
Value = f.StoredProcedure(New SQLFunction("QER", "",
"PPickedItemInsert"), _
    f.FormatValue("<UID_QERPickCategory>", ValType.String, True), _
    f.FormatValue($"XObjectKey$", ValType.String, True) _
)
```

- UID_QERPickCategory: Unique identifier of the sample whose sampling data is to be generated.

For more information about defining processes, see the *One Identity Manager Configuration Guide*.

If the **Remove items after attestation run** option is set in the sample, the sampling data will be deleted as soon as an attestation run is completed. This way ensures that the sample always contains only those objects that have been changed since the previous attestation.


Related topics

- [Sample attestation](#) on page 50
- [General main data of samples](#) on page 51
- [Managing sampling data](#) on page 52

Using samples with attestation policies

To use sampling for attestation, assign a sample to the appropriate attestation policies. A sample can only be assigned to exactly one attestation policy.

To assign a sample to an attestation policy

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select an attestation policy in the result list and run the **Change main data** task.
3. In the **Sample** drop-down, select a sample.
 - To create a new sample, click . Enter the name of the sample and assign the table from which to take the data for the sample.
4. Save the changes.

Related topics

- [General main data of attestation policies](#) on page 38
- [Managing sampling data](#) on page 52
- [Sample attestation](#) on page 50

Displaying the sample overview

You can display the most important information about a sample on the overview form. You can display the attestation policy that is used with sample.

To obtain an overview of a sample

1. In the Manager, select the **Attestation > Samples** category.
2. Select the sample in the result list.
3. Select the **Sample overview** task .

Related topics

- [Sample attestation](#) on page 50
- [Creating, editing, deleting samples](#) on page 50
- [Managing sampling data](#) on page 52

Default sample for attesting memberships in system entitlements

A default sample is provided for attesting memberships in system entitlements after organizational changes. This sampling data is determined automatically. This identifies all individuals whose manager or primary department, cost center, or business role assignment has changed since the previous attestation. All memberships are attested whose user accounts are associated with these individuals.

To use attestation of memberships in system authorizations after organizational changes

1. In the Designer, set the **QER | Selections | PersonOrganizationalChanges** configuration parameter.
2. Create a schedule and assign it to the **System entitlement memberships after organizational changes** attestation policy. By doing this, you replace the schedule assigned by default.
 - Enable the schedule.

Once an attestation run is complete, the sampling data is deleted. As soon as an individual's organizational data changes, they are included in the sample. This ensures that the sample always includes only those individuals whose organizational data has changed since the previous attestation.

TIP: Sampling data is calculated by the QER_Person_Add_to_PickCategory_Organizational_Changes process. You can customize the generating condition of this process.

Related topics

- [General main data of attestation policies](#) on page 38
- [Attestation schedules](#) on page 24

Default sample for attesting identities

There is a default sample, **Individual selection of identities**, provided for attesting identities. This sample is used for the **Identity attestation** policy collection. The sampling data must be assigned manually.

Related topics

- [Managing sampling data](#) on page 52
- [Configuring sample attestation of identities and their entitlements](#) on page 189

Grouping attestation policies

Different attestation policies can be combined into a collection allowing the attestations to start simultaneously. For example, this can be used in the context of an audit, when different attestations are run that have related content.

Related attestation policies can be grouped together into policy collections. Policy collections must be assigned a schedule for running these attestation policies. Use a sample to limit the set of objects to attest for all assigned attestation policies.

The following applies:

- An attestation policy can be assigned to only one policy collection.
- Attestation policies that belong to a policy collection cannot be started separately.
- When samples are attested, the same sample is used for all the attestation policies that belong to one policy collection.

Example of a policy collection

The following properties of all identities in department D are going to be attested:

- Primary and secondary membership in business roles
- Linked user accounts
- Assigned system entitlements

These attestations must always be performed simultaneously.

The following objects must be created for this purpose:

1. Attestation procedure for the Person, PersonInOrg, UNSAccount, UNSAccountInUNSGroup tables
2. A schedule
3. A sample the find all identities assigned to department D
4. A policy collection that uses the schedule and sample
5. Attestation policies that use the attestation procedures and the policy collection


Related topics

- [Creating and editing policy collections](#) on page 56
- [Assigning policy collections to attestation policies](#) on page 58
- [General main data of policy collections](#) on page 57
- [General main data of attestation policies](#) on page 38
- [Sample attestation](#) on page 50
- [Disabling policy collections](#) on page 58
- [Deleting policy collections](#) on page 59

Creating and editing policy collections

To run different attestations together, create a policy collection and assign it to all the attestation policies that you want to start collectively.

To delete a policy collection

1. In the Manager, select the **Attestation > Policy collections** category.
2. Click  in the result list.
3. Edit the main data of the policy collection.
4. Save the changes.

To edit a policy collection

1. In the Manager, select the **Attestation > Policy collections** category.
2. In the result list, select the policy collection and run the **Change main data** task.
3. Edit the main data of the policy collection.
4. Save the changes.



Detailed information about this topic

- [General main data of policy collections](#) on page 57
- [Deleting policy collections](#) on page 59

General main data of policy collections

Enter the following main data for a policy collection.

Table 13: General main data of a policy collection

Property	Description
Policy collection	Name of the policy collection.
Description	Text field for additional explanation.
Owners	The policy collection owner. The name of the user logged in to One Identity Manager is entered here by default. This can be changed.
Owner (Application Role)	Application role whose members can edit the policy collection. To create a new application role, click  . Enter the application role name and assign a parent application role.
Sample	Sample that can be used for attestations. A sample can only be assigned to only one policy collection. It is transferred to all related attestation policies. To create a new sample, click  . Enter the name of the sample and assign the table from which to take the data for the sample.
Calculation	Schedule for running attestation. Attestation cases are started automat-

Property	Description
schedule	ically at the times specified by the schedule.
Disabled	Specifies whether the policy collection is disabled. If the option is enabled, all associated attestation policies are disabled. Thus, no attestations are carried out on the policy collection.

Related topics

- [Grouping attestation policies](#) on page 55

Assigning policy collections to attestation policies

To group attestation policies together, assign a policy collection to the attestation policies. An attestation policy can be assigned to only one policy collection.

To assign a policy collection to an attestation policy

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list and run the **Change main data** task.
3. Select the policy collection from the **Policy collection** drop-down.
4. Save the changes.

Related topics

- [General main data of attestation policies](#) on page 38
- [Grouping attestation policies](#) on page 55

Disabling policy collections

To prevent attestations being run for a policy collection, you can disable the policy collection. This also disables all associated attestation policies and deletes their attestation cases.

To disable a policy collection

1. In the Manager, select the **Attestation > Policy collections** category.
2. In the result list, select the policy collection and run the **Change main data** task.
3. Set **Disabled**.
4. Save the changes.

Detailed information about this topic

- [Disabling attestation policies](#) on page 49
- [Suspending attestation](#) on page 68


Deleting policy collections

When a policy collection is deleted, the calculation schedule from the policy collection is added to all attestation policies that have this policy collection assigned to them. This means that attestations for these policies will continue to be started at the usual rate.

NOTE: A policy collection cannot be deleted if attestation policies as well as a sample are assigned to it.

- Before you delete a policy collection, remove the assignment of the sample. Alternatively, you can remove assignment of the policy collection to attestation policies.

To delete a policy collection

1. In the Manager, select the **Attestation > Policy collections** category.
2. In the result list, select the policy collection and click .
3. Confirm the security prompt with **Yes**.

Related topics

- [General main data of attestation policies](#) on page 38
- [Creating and editing policy collections](#) on page 56
- [Assigning policy collections to attestation policies](#) on page 58

Default policy collections

One Identity Manager provides a default policy collection and default attestation policies for regular attestation of identities with all their entitlements and memberships.

To display default policy collections

- In the Manager, select the **Attestation > Policy collections > Predefined** category.

You can alter the following default policy collection properties to suit your company requirements.

- Calculation schedule
- Disabled

Related topics

- [Default attestation policies](#) on page 43
- [Default sample for attesting identities](#) on page 55
- [Configuring sample attestation of identities and their entitlements](#) on page 189


Custom mail templates for notifications

For more information about creating and editing mail template, see the *One Identity Manager Operational Guide*.

A mail template consists of general main data such as target format, importance, or mail notification confidentiality, and one or more mail definitions. Mail text is defined in several languages in the mail template. This ensures that the language of the recipient is taken into account when the email is generated.

Creating and editing attestation mail templates

To create and edit mail templates

1. In the Manager, select the **Attestation > Basic configuration data > Mail templates** category.
This shows all the mail templates that can be used for attestation cases in the result list.
2. Select a mail template in the result list and run the **Change main data** task.
- OR -
Click  in the result list.
This opens the mail template editor.
3. Edit the mail template.
4. Save the changes.



Detailed information about this topic

- [General properties of a mail template](#) on page 61
- [Creating and editing a mail definition](#) on page 62

General properties of a mail template

The following general properties are displayed for a mail template:

Table 14: Mail template properties

Property	Meaning
Mail template	Name of the mail template. This name will be used to display the mail templates in the administration tools and in the Web Portal. Translate the given text using the  button.
Base object	Mail template base object. A base object only needs to be entered if the mail definition properties of the base object are referenced. Use the <code>AttestationCase</code> or <code>AttestationHelper</code> base object for notifications about attestation.
Report (parameter set)	Report, made available through the mail template.
Description	Mail template description. Translate the given text using the  button.
Target format	Format in which to generate email notification. Permitted values are: <ul style="list-style-type: none">• HTML: The email notification is formatted in HTML. Text formats, for example, different fonts, colored fonts, or other text formatting, can be included in HTML format.• TXT: The email notification is formatted as text. Text format does not support bold, italics, or colored font, or other text formatting. Images displayed directly in the message are not supported.
Design type	Design in which to generate the email notification. Permitted values are: <ul style="list-style-type: none">• Mail template: The generated email notification contains the mail body in accordance with the mail definition.• Report: The generated email notification contains the report specified under Report (parameter set) as its mail body.• Mail template, report in attachment: The generated email notification contains the mail body in accordance with the mail definition. The report specified under Report (parameter set) is attached to the notification as a PDF file.
Importance	Importance for the email notification. Permitted values are Low , Normal , and High .
Confidentiality	Confidentiality for the email notification. Permitted values are Normal , Personal , Private , and Confidential .
Can unsubscribe	Specifies whether the recipient can unsubscribe email notification. If this option is set, the emails can be unsubscribed through the

Property	Meaning
	Web Portal.
Deactivated	Specifies whether this mail template is disabled.
Mail definition	Selects the mail definition in a specific language. NOTE: If the Common MailNotification DefaultCulture configuration parameter is set, when the template is opened, the mail definition is loaded and displayed in the email notifications default language.
Language	Language that applies to the mail template. The recipient's language preferences are taken into account when an email notification is generated.
Subject	Subject of the email message.
Mail body	Content of the email message.

Creating and editing a mail definition

Mail texts can be defined in these different languages in a mail template. This ensures that the language of the recipient is taken into account when the email is generated.

NOTE: If the **Common | MailNotification | DefaultCulture** configuration parameter is set, the mail definition is loaded in the default language for email notifications when the template is opened.

To create a new mail definition

1. In the Manager, select the **Attestation > Basic configuration data > Mail templates** category.
This shows all the mail templates that can be used for attestation cases in the result list.
2. Select a mail template in the result list and run the **Change main data** task.
3. In the result list, select the language for the mail definition in the **Language** drop-down.
All active languages are shown. To use another language, in the Designer, enable the corresponding countries. For more information, see the *One Identity Manager Configuration Guide*.
4. Enter the subject in **Subject**.
5. Edit the mail text in the **Mail definition** view with the help of the Mail Text Editor.
6. Save the changes.

To edit an existing mail definition

1. In the Manager, select the **Attestation > Basic configuration data > Mail templates** category.

This shows all the mail templates that can be used for attestation cases in the result list.

1. Select a mail template in the result list and run the **Change main data** task.
2. In the **Mail definition** drop-down, select the language for the mail definition.
3. Edit the mail subject line and the body text.
4. Save the changes.

Using base object properties

In the subject line and body text of a mail definition, you can use all properties of the object entered under **Base object**. You can also use the object properties that are referenced by foreign key relation.

To access properties use dollar notation. For more information about using dollar (\$) notation, see the *One Identity Manager Configuration Guide*.

Example:

An attestor should receive email notification of new attestations.

Table 15: Email notification properties

Property	Value
Base object	AttestationHelper
Subject	New attestations
Mail body	Dear \$FK(UID_PersonHead).Salutation[D]\$ \$FK(UID_PersonHead).LastName\$, There are new attestations pending for the attestation policy "\$FK(UID_AttestationCase).UID_AttestationPolicy[D]\$". Created: \$FK(UID_AttestationCase).PolicyProcessed:Date\$ You can display this request in the "One Identity Manager Self Service Portal". Best regards

Use of hyperlinks in the Web Portal

You can add hyperlinks to the Web Portal in the mail text of a mail definition. If the recipient clicks on the hyperlink in the email, the Web Portal opens on that web page and further actions can be carried out. In the default version, this method is implemented in attestations.

Prerequisites for using this method

- The **QER | WebPortal | BaseURL** configuration parameter is enabled and contains the URL to the API Server. You edit the configuration parameter in the Designer.

```
http://<server name>/<application>
```

with:

```
<server name> = name of server
```

```
<application> = path to the API Server installation directory
```

To add a hyperlink to the Web Portal in the mail text

1. Click the position in the mail text of the mail definition where you want to insert a hyperlink.
2. Open the **Hyperlink** context menu and enter the following information.
 - **Display text:** Enter a caption for the hyperlink.
 - **Link to:** Select the **File or website** option.
 - **Address:** Enter the address of the page in the Web Portal that you want to open.

NOTE: One Identity Manager provides a number of default functions that you can use to create hyperlinks in the Web Portal.
3. To accept the input, click **OK**.

Default functions for creating hyperlinks

Several default functions are available to help you create hyperlinks. You can use the functions directly when you add a hyperlink in the mail body of a mail definition or in processes

Direct function input

You can reference a function when you add a hyperlink in the **Address** field of the **Hyperlink** context menu.

Syntax

```
$Script(<Function>)$
```

Example:

```
$Script(VI_BuildAttestationLink_Approve)$
```

Default functions for requests

The `VI_BuildAttestationLinks` script contains a collection of default functions for composing hyperlinks to directly grant or deny approval of requests from email notifications.

Table 16: Functions of the `VI_BuildAttestationLinks` script

Function	Usage
<code>VI_BuildAttestationLink_Show</code>	Opens the attestation page in the Web Portal.
<code>VI_BuildAttestationLink_Approve</code>	Approves an attestation and opens the attestation page in the Web Portal.
<code>VI_BuildAttestationLink_Deny</code>	Denies an attestation and opens the attestation page in the Web Portal.
<code>VI_BuildAttestationLink_AnswerQuestion</code>	Opens the page for answering a question in the Web Portal.
<code>VI_BuildAttestationLink_Pending</code>	Opens the page with pending attestations in the Web Portal.

Customizing email signatures

Configure the email signature for mail templates using the following configuration parameters. Edit the configuration parameters in the Designer.

Table 17: Configuration parameters for email signatures

Configuration parameter	Description
Common MailNotification Signature	Data for the signature in email automatically generated from mail templates.
Common MailNotification Signature Caption	Signature under the salutation.
Common MailNotification Signature Company	Company name.
Common MailNotification Signature Link	Link to the company's website.

Configuration parameter	Description
Common MailNotification Signature LinkDisplay	Display text for the link to the company's website.

VI_GetRichMailSignature combines the components of an email signature according to the configuration parameters for use in mail templates.

Copying mail templates for attestation

To copy a mail template

1. In the Manager, select the **Attestation > Basic configuration data > Mail templates** category.
This shows all the mail templates that can be used for attestation cases in the result list.
2. Select the mail template that you want to copy in the result list and run the **Change main data** task.
3. Select the **Copy mail template** task.
4. Enter the name of the new mail template in the **Name of copy** field.
5. Click **OK**.


Displaying attestation mail templates previews

To display a mail template preview

1. In the Manager, select the **Attestation > Basic configuration data > Mail templates** category.
This shows all the mail templates that can be used for attestation cases in the result list.
2. Select a mail template in the result list and run the **Change main data** task.
3. Select the **Preview** task.
4. Select the base object.
5. Click **OK**.

Deleting mail templates for attestation

To delete a mail template

1. In the Manager, select the **Attestation > Basic configuration data > Mail templates** category.
This shows all the mail templates that can be used for attestation cases in the result list.
2. Select the template in the result list.
3. Click  in the result list.
4. Confirm the security prompt with **Yes**.

Custom notification processes

Set up customized processes to send more email notifications within an attestation case. You can use following events for generating processes.

Table 18: Events for the AttestationHelper object

Event	Triggered by
DecisionRequired	New attestation case created Move to the next approval level
Remind	Reminder interval expired

Table 19: Events for the AttestationCase object

Event	Triggered by
Granted	Approval granted for an approval step.
Dismissed	Approval denied for an approval step.
OrderGranted	Approval granted for an entire approval procedure.
FinalDismissed	Approval denied for an entire approval procedure.
QueryToPerson	Making a query
AnswerFromPerson	Answering a query
RecallQuery	Recalling a query
Escalate	Attestation case escalated.
Aborted	Attestation case canceled.
Canceled	Obsolete attestation case canceled.

For more information about creating processes, see the *One Identity Manager Configuration Guide*.

Suspending attestation

To suspend attestation you have two options.

1. Disable the schedule assigned to the attestation policy.

As long as the schedule is disabled, no new attestation cases will be generated. This applies to all attestation policies that have this schedule assigned to them.

For more information, see [Attestation schedules](#) on page 24.

2. Disable the attestation policy

Once an attestation policy is disabled, no new attestation cases are generated. In addition, all associated attestation cases are deleted. To avoid losing the attestation history in the process, you can configure how data changes are logged.

For more information, see [Disabling attestation policies](#) on page 49.

3. Disable the policy collection.

Once a policy collection is disabled, all associated attestation policies are disabled.

For more information, see [Disabling policy collections](#) on page 58.

Related topics

- [Deleting attestation cases](#) on page 151

Automatic attestation of policy violations

| NOTE: This functionality is only available if the Company Policies Module is installed.

Automatic recertification of the affected entitlements can be provided for policy violations. As a result of recertification, entitlements that should not be used anymore can be automatically deactivated or removed. This functionality is used by default in the context of Behavior Driven Governance. However, you can also use this functionality for your own company policies and related authorization checks.

For more information about how to configure attestation of policy violations, see *One Identity Manager Company Policies Administration Guide*. For more information about Behavior Driven Governance, see the *One Identity Manager Administration Guide for Behavior Driven Governance*.

Approval processes for attestation cases

All attestation cases are subject to a defined approval process. During this approval process, authorized identities grant or deny approval for attestation objects. You can configure this approval process in various ways, and therefore customize it to meet your company policies.

You define approval policies and approval workflows for approval processes. Specify the approval workflows to apply to the attestation cases in the approval policies. Use approval workflows to find out, which identities in which order, can grant or deny attestation. An approval workflow can contain several approval levels and several approval steps. A special approval procedure is used to determine the attestors in each approval step.


Detailed information about this topic

- [Approval policies for attestations](#) on page 69
- [Approval workflow for attestations](#) on page 72
- [Editing approval levels](#) on page 77
- [Default approval procedures](#) on page 86

Approval policies for attestations

One Identity Manager uses approval policies to determine the attestor for each attestation case.

To edit an approval policy

1. In the Manager, select the **Attestation > Basic configuration data > Approval policies** category.
2. Select an approval policy in the result list and run the **Change main data** task.
- OR -
Click  in the result list.

3. Edit the approval policy main data.
4. Save the changes.


Related topics

- [General main data of approval policies](#) on page 70
- [Validity checking](#) on page 71
- [Editing approval workflows](#) on page 71
- [Copying approval policies](#) on page 72

General main data of approval policies

Enter the following main data of an approval policy. If you add a new approval step, you must fill out the compulsory fields.

Table 20: General main data of approval policies

Property	Description
Approval policies	Approval step name.
Approval workflow	Workflow for finding attestors. Select any approval workflow from the drop-down or click  to set up a new approval workflow.
Mail templates	Mail template used to create email notifications for granting, denying, extending, unsubscribing, or canceling an attestation or for giving notice of its expiry.
Description	Text field for additional explanation.
Do not show	Specifies whether this approval policy is hidden in the Web Portal. When editing attestation policies in the Web Portal, this approval policy can only be selected if the option is disabled.

Detailed information about this topic

- [Setting up approval workflows](#) on page 76
- [Notifications in the attestation case](#) on page 153

Default approval policies

One Identity Manager provides a default approval policy for default attestation of new users and recertification of all identities stored in the One Identity Manager database. Moreover, default approval policies are supplied through which different roles and system entitlements mapped in the Unified Namespace can be attested. You can use default approval policies for creating attestation policies in the Web Portal.

To edit default approval policies

- In the Manager, select the **Attestation > Basic configuration data > Approval policies > Predefined** category.

For more information about using default approval policies, see the *One Identity Manager Web Portal User Guide*.

Related topics

- [User attestation and recertification](#) on page 190
- [Configuring withdrawal of entitlements](#) on page 182

Editing approval workflows

Here, you can edit the approval workflow assigned to the approval policy.

To edit the assigned approval workflow

1. Select **Attestation > Basic configuration data > Approval policies**.
2. Select the approval policy in the result list.
3. Select **1. Editing approval workflows**.

This opens the Workflow Editor.

Detailed information about this topic

- [Working with the Workflow Editor](#) on page 73

Validity checking

Once you have edited an approval policy, you need to test it. This checks whether the approval steps can be used in the approval workflows in this combination. Non-valid approval steps are displayed in the error window.

To test an approval policy

1. In the Manager, select the **Attestation > Basic configuration data > Approval policies** category.
2. Select the approval policy in the result list.
3. Select the **Validity check** task.

Copying approval policies

To customize pre-defined approval policies, you can copy approval policies and then edit them. All assigned approval workflows are copied as well.

To copy an approval policy

1. In the Manager, select the **Attestation > Basic configuration data > Approval policies** category.
2. Select an approval policy in the result list and run the **Change main data** task.
3. Select the **Copy approval policies** task.
4. Enter a name for the copy of the approval policy.
5. Enter names for the workflow copies.
6. Click **OK** to start copying.
- OR -
Click **Cancel** to cancel copying.
7. To edit the copy immediately, click **Yes**.
- OR -
To edit the copy later, click **No**.

Related topics


- [Approval policies for attestations](#) on page 69

Approval workflow for attestations

You need to allocate an approval workflow to the approval policies in order to find the attestors. In an approval workflow, you specify the approval procedures, the number of attestors and a condition for selecting the attestors.

Use the Workflow Editor to create and edit approval workflows.


To edit an approval workflow

1. In the Manager, select the **Attestation > Basic configuration data > Approval workflows** category.
2. Select the approval workflow in the result list and run the **Change main data** task.
- OR -
Click  in the result list.
This opens the Workflow Editor.
3. Edit the approval workflow main data.
4. Save the changes.

Working with the Workflow Editor

Use the Workflow Editor to create and edit approval workflows. The Workflow Editor allows approval levels to be linked together. Multi-step approval processes are clearly displayed in a graphical form.

Figure 1: Workflow Editor



Approval levels and approval steps belonging to the approval workflow are edited in the Workflow Editor using special control elements. The Workflow Editor contains a toolbox. The toolbox items are activated or deactivated depending on how they apply to the control. You can move the layout position of the control elements in the Workflow Editor with the mouse or these can be moved automatically.

Table 21: Entries in the toolbox

Control	Item	Meaning
Workflow	Edit	Edit the properties of the approval workflow.
	Layout automatically	The workflow elements are aligned automatically. The workflow layout is recalculated.
Approval levels	Add	A new approval level is added to the workflow.
	Edit	Edit the properties of the approval workflow.
	Delete	Deletes the approval level.
Approval steps	Add	Add a new approval step to the approval level.
	Edit	Edit the properties of the approval step.
	Delete	Deletes the approval step.
Assignments	Remove positive	The Approved connector for the selected approval level is deleted.
	Remove negative	The Deny connector for the selected approval level is deleted.
	Remove reroute	The Reroute connector for the selected approval level is deleted.
	Remove escalation	The Escalate connector for the selected approval level is deleted.

Each of the controls has a properties window for editing the data of the approval workflow, level, or step. To open the properties window, select the **Toolbox > <Control> > Edit** item.

To delete a control, select the element and then the **Toolbox > <Control> > Delete** item.

Individual elements are linked to each other with a connector. Activate the connection points with the mouse. The cursor changes into an arrow icon for this. Hold down the left mouse button and pull a connector from one connection point to the next.

Figure 2: Approval workflow connectors




Table 22: Approval workflow connectors





Connector	Meaning
Approve	Link to next approval level if the current approval level was granted approval.
Deny	Link to next approval level if the current approval level was not granted approval.
Reroute	Link to other approval levels to bypass the current approval.
Escalation	Connection to another approval level when the current approval level is escalated after timing out.

By default, a connection between workflow elements and level elements is created immediately when a new element is added. If you want to change the level hierarchy, drag a new connector to another level element.

Alternatively, you can release connectors between level elements using the **Toolbox > Assignments** items. To do this, mark the level element where the connector starts. Then add a new connector.

Different icons are displayed on the level elements depending on the configuration of the approval steps.

Table 23: Icons on the level elements

Icon	Meaning
	The approval decision is made by the system.
	The approval decision is made manually.
	The approval step contains a reminder function.
	The approval step contains a timeout.

Changes to individual elements in the workflow do not take place until the entire approval workflow is saved. The layout position in the Workflow Editor is saved in addition to the approval policies.

Setting up approval workflows

An approval workflow consists of one or more approval levels. An approval level can contain one approval step or several parallel approval steps. Within the attestation procedure, all of the approval steps for one approval level must be run before the next approval level is called. Use connectors to set up the sequence of approval levels in the approval workflow.

When you add a new approval workflow, the first thing to be created is a new workflow element.

To edit approval level properties

1. Open the Workflow Editor.
2. Select the **Toolbox > Workflow > Edit** item.
3. Edit the workflow properties.
4. Click **OK**.

Table 24: Approval workflow properties

Property	Meaning
Name	Approval workflow name.
System halt (days)	Number of days to elapse after which the approval workflow, and therefore the system, automatically halts the entire attestation procedure.
Description	Text field for additional explanation.

Detailed information about this topic

- [Halting an attestation case on timeout](#) on page 141

Editing approval levels

An approval level provides a method of grouping individual approval steps. All the approval steps in one approval level are run in parallel. All the approval steps for different approval levels are run one after the other. You use the connectors to specify the order.

Specify the individual approval steps in the approval levels. At least one approval step is required per level. Enter the approval steps first before you add an approval level.

To add an approval level

1. Select the **Toolbox > Approval levels > Add** item.
This opens the properties dialog for the first approval step.
2. Enter the approval step properties.
3. Save the changes.

You can edit the properties of an approval level as soon as you have added an approval level with at least one approval step.

To edit approval level properties

1. Select the approval level.
2. Select the **Toolbox > Approval levels > Edit** item.
3. Enter a display name for the approval level.
4. Save the changes.

NOTE: You can define more than one approval step for each approval level. In this case, the attestors of an approval level can make a decision about an attestation case in parallel rather than sequentially. The attestation case cannot be presented to the attestors at the next approval level until all approval steps in one approval level have been completed in the attestation procedure.

To add more approval steps to an approval level

1. Select the approval level.
2. Select the **Toolbox > Approval steps > Add** item.
3. Enter the approval step properties.
4. Save the changes.

Related topics

- [Properties of an approval step](#) on page 78
- [Editing approval steps](#) on page 78

Editing approval steps

To edit approval level properties

1. Select the approval step.
2. Select the **Toolbox > Approval steps > Edit** item.
3. Edit the approval step properties.
4. Save the changes.


Detailed information about this topic

- [Properties of an approval step](#) on page 78

Properties of an approval step

On the **General** tab, enter the data described below. On the **Mail templates** tab, select the mail templates for generating mail notifications. If you add a new approval step, you must fill out the required fields.

Table 25: General properties of an approval step

Property	Meaning
Single step	Approval step name.
Approval procedure	Procedure to use for determining the attestors.
Role	Hierarchical role from which to determine the attestors. The role is used in the OM and OR default approval procedures. Additionally, you can use the role if you use a custom approval procedure in the approval step.
Fallback approver	Application role whose members are authorized to approve attestation cases if an attestor cannot be determined through the approval procedure. Assign an application from the drop-down. To create a new application role, click  . Enter the application role name and assign a parent application role. For more information, see the <i>One Identity Manager Authorization and Authentication Guide</i> . NOTE: The number of approvers is not applied to the fallback approvers. The approval step is considered approved the moment as soon as one fallback approver has approved the request.
Condition	Condition for calculating the approval decision. The condition is used in the CD, EX, or WC default approval procedures. Additionally, you can use the role if you use a custom approval procedure in the approval step.

Property	Meaning
Number of approvers	<p>Number of attestors required to approve an attestation case. Use this number to further restrict the maximum number of approvers of the implemented approval procedure.</p> <p>If there are several identities allocated as attestors, then this number specifies how many identities from this group have to approve an attestation case. A request can only be passed up to next level afterwards.</p> <p>If you want approval decisions to be made by all the identities found using the applicable approval procedure, for example, all members of a role (default approval procedure OR), enter the value -1. This overrides the maximum number of attestors defined in the approval procedure.</p> <p>If not enough attestors can be found, the approval step is presented to the fallback approvers. The approval step is considered approved as soon as one fallback approver has approved the attestation case.</p> <p>If an approval decision is made by the chief approval team, it overrides the approval decision of just one regular attestor. This means, if three attestors must approve an approval step and the chief approval team one of the decision, two more are still required.</p> <p>The number of approvers defined in an approval step is not taken into account in the approval procedures CD, EX, or WC.</p>
Description	Text field for additional explanation.
Approval reason	<p>Reason entered in the attestation case if approval is automatically granted.</p> <p>This field is only shown for the approval procedures CD, EX, and WC.</p>
Reject reason	<p>Reason entered in the attestation case and the attestation history, if approval is automatically denied.</p> <p>This field is only shown for the approval procedures CD, EX, and WC.</p>
Reminder after	<p>Time interval after which the attestor is notified by mail that there are still pending attestation cases for attestation. The input is converted into working hours and displayed additionally.</p> <ul style="list-style-type: none"> From the drop-down, select the unit of time and enter an appropriate value. <p>The reminder interval is set to 30 minutes, by default. To change this interval, modify the Checks reminder interval and timeout of attestation cases schedule.</p> <p>NOTE: Ensure that a state, county, or both is entered into the identity's main data of determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more information about calculating identities' working hours, see the <i>One Identity Manager Identity Management Base Module</i></p>

Property	Meaning
----------	---------

Administration Guide.

TIP: Weekends and public holidays are taken into account when working hours are calculated. If you want weekends and public holidays to be dealt with in the same way as working days, set the **QBM | WorkingHours | IgnoreHoliday** or **QBM | WorkingHours | IgnoreWeekend** configuration parameter. For more information about this, see the *One Identity Manager Configuration Guide*.

If more than one attestor was found, each attestor will be notified. The same applies if an additional attestor has been assigned.

If an attestor delegated the approval, the time point for reminding the delegation recipient is recalculated. The delegation recipient and all the other attestors are notified. The original attestor is not notified.

If an attestor has made an inquiry, the time point for reminding the queried identity is recalculated. As long as the inquiry has not been answered, only this identity is notified.

Timeout	
---------	--

Time interval after which the approval step automatically handles the approval decision. The input is converted into working hours and displayed additionally.

- From the drop-down, select the unit of time and enter an appropriate value.

The timeout is checked every 30 minutes, by default. To change this interval, modify the **Checks reminder interval and timeout of attestation cases** schedule.

The working hours of the respective approver are taken into account when the time is calculated.

NOTE: Ensure that a state, county, or both is entered into the identity's main data of determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more information about calculating identities' working hours, see the *One Identity Manager Identity Management Base Module Administration Guide*.

TIP: Weekends and public holidays are taken into account when working hours are calculated. If you want weekends and public holidays to be dealt with in the same way as working days, set the **QBM | WorkingHours | IgnoreHoliday** or **QBM | WorkingHours | IgnoreWeekend** configuration parameter. For more information about this, see the *One Identity Manager Configuration Guide*.

If more than one approver was found, then an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.

Property	Meaning
	<p>If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.</p> <p>If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is not recalculated.</p> <p>If additional approvers are determined by recalculating the current approvers, then the automatic approval deadline is not extended. The additional approvers must approve within the time frame that applies to the current approver.</p>
Timeout behavior	<p>Action that is run if the timeout expires.</p> <ul style="list-style-type: none"> • Approved: The attestation case is approved in this approval step. The next approval level is called. • Deny: The attestation case is denied in this approval step. The approval level for denying is called. • Escalation: The attestation case is escalated. The escalation approval level is called. • Cancel: The approval step and, therefore, the entire attestation procedure, is canceled.
Reason type on approval	<p>Specifies which type of reason is required when granting approval to this approval step.</p> <ul style="list-style-type: none"> • Optional: A reason can be provided if required. • Reason required (standard or free): A standard reason must be selected or a reason given with any text. • Free text required: A reason must be given with freely selected text.
Reason type on denial	<p>Specifies which type of reason is required when denying approval to this approval step.</p> <ul style="list-style-type: none"> • Optional: A reason can be provided if required. • Reason required (standard or free): A standard reason must be selected or a reason given with any text. • Free text required: A reason must be given with freely selected text.
Additional approver possible	<p>Specifies whether a current attestor is allowed to instruct another identity as an attestor. This additional attestor has parallel authorization to make approvals for the current attestation case. The attestation case is not passed on to the next approval level until both attestors have made a decision.</p> <p>This option can only be set for approval levels with a single, manual</p>

Property	Meaning
	approval step.
Approval can be delegated	<p>Specifies whether a current attestor can delegate the attestation to another identity. This identity is added to the current approval step as the attestor and then makes the approval decision instead of the attestor who delegated.</p> <p>This option can only be set for approval levels with a single, manual approval step.</p>
Approval by affected identity	<p>Specifies whether the identity who is affected by the approval decision can also approve it. If this option is set, identities to be attested can attest themselves.</p> <p>If this option is not set, use the QER Attestation PersonToAttestNoDecide configuration parameter to define whether the identities to be attested can attest themselves.</p>
Do not show in approval history	<p>Specifies whether or not the approval step should be displayed in the attestation history. For example, this behavior can be applied to approval steps with the CD - calculated approval procedure, which are used only for branching in the approval workflow. It makes it easier to follow the attestation history.</p>
Escalate if no approver found	<p>Specifies whether the approval step is escalated if no attestor can be found and no fallback approver is assigned. In this case, the attestation case is neither canceled nor passed to the chief approval team.</p> <p>This option can only be enabled if an approval level is linked to escalation.</p>

Detailed information about this topic

- [Notifications in the attestation case](#) on page 153
- [Reminding attestors](#) on page 154
- [Escalating an attestation case](#) on page 137
- [Automatic approval on timeout](#) on page 140
- [Halting an attestation case on timeout](#) on page 141
- [Determining managers or members of a role as attestors](#) on page 97
- [Calculated approval](#) on page 106
- [Approvals to be made externally](#) on page 107
- [Waiting for further approval](#) on page 108
- [Prevent attestation by identity awaiting attestation](#) on page 119

Related topics

- [Selecting attestors](#) on page 85
- [Attestors cannot be established](#) on page 139

- [Attesting by chief approval team](#) on page 143

Connecting approval levels

When you set up an approval workflow with several approval levels, you have to connect each level with another. You may create the following links.

Table 26: Links to approval levels

Link	Description
Approve	Link to next approval level if the current approval level was granted approval.
Deny	Link to next approval level if the current approval level was not granted approval.
Reroute	<p>Link to another approval level to bypass the current approval.</p> <p>Attestors can pass the approval decision through another approval level, for example, if approval is required by a manager in an individual case. To do this, create a connection to the approval levels to which the approval can be rerouted. This way, approvals can also be rerouted to a previous approval level, for example, if an approval decision is considered not to be well-founded. Starting from one approval level, more than one reroute can lead to different approval levels. The attestors select, in the Web Portal, which of these approval levels to reroute the approval to.</p> <p>It is not possible to reroute approval steps with the approval procedures EX, CD, SB, or WC.</p>
Escalation	Link to another approval level when the current approval level is escalated after timing out.

If there are no further approval levels after the current approval level, the attestation case is considered approved if the approval decision was to grant approval. If approval is not granted, the attestation case is considered to be finally denied. The attestation procedure is closed in both cases.

Copying approval workflows

You can copy default approval workflows in order to customize them.

To copy an approval workflow


1. In the Manager, select the **Attestation > Basic configuration data > Approval workflows** category.
2. Select an approval workflow in the result list and run the **Change main data** task.

3. Select the **Copy workflow** task.
4. Enter a name for the copy.
5. Click **OK** to start copying.
- OR -
Click **Cancel** to cancel copying.
6. To edit the copy immediately, click **Yes**.
- OR -
To edit the copy later, click **No**.

Deleting approval workflows

The approval workflow can only be deleted if it is not assigned to an approval policy.

To delete an approval workflow

1. Remove all assignments to approval policies.
 - a. Check to which approval policies the approval workflow is assigned.
 - b. Go to the main data form for the approval policy and assign a different approval workflow.
2. In the Manager, select the **Attestation > Basic configuration data > Approval workflows** category.
3. Select an approval workflow in the result list.
4. Click .
5. Confirm the security prompt with **Yes**.

Detailed information about this topic

- [The approval workflow overview](#) on page 84
- [General main data of approval policies](#) on page 70

The approval workflow overview

To obtain an overview of an approval workflow

1. In the Manager, select the **Attestation > Basic configuration data > Approval workflows** category.
2. Select the approval workflow in the result list.
3. Select **Approval workflow overview**.

Default approval workflows

One Identity Manager provides a default approval workflow for default attestation of new users and recertification of all identities stored in the One Identity Manager database. Moreover, default approval workflows are supplied through which different roles and system entitlements mapped in the Unified Namespace can be attested. You can use default approval policies for creating attestation policies in the Web Portal.

To edit default approval workflows

- In the Manager, select the **Attestation > Basic configuration data > Approval workflows > Predefined** category.

For more information about using default approval workflows, see the *One Identity Manager Web Portal User Guide*.

Related topics

- [User attestation and recertification](#) on page 190
- [Configuring withdrawal of entitlements](#) on page 182

Selecting attestors

One Identity Manager can make approvals automatically in an attestation procedure or through attestors. An attestor is an identity or a group of identities who can grant or deny an attestation case within an attestation procedure. It takes several approval procedures to grant or deny approval. You specify in the approval step which approval procedure should be used.

If several people are determined to be approvers by an approval procedure, the number given in the approval step specifies how many people must approve the step. A request can only be passed up to next level afterwards. The attestation procedure is canceled if an approver cannot be found for an approval step.

One Identity Manager provides approval procedures by default. You can also define your own approval procedures.

The DBQueue Processor calculates which identity is authorized as an approver and in which approval level. Take into account the special cases for each approval procedure when setting up the approval workflows to determine those authorized to grant approval.

Related topics

- [Default approval procedures](#) on page 86
- [Setting up approval procedures](#) on page 109

- [Overview of approval procedures](#) on page 115
- [Determining the responsible attestors](#) on page 116

Default approval procedures

Default approval procedures are provided to help with selecting which attestors are responsible. These you can use to setup your own approval workflows.

To display default approval procedures

- In the Manager, select the **Attestation > Basic configuration data > Approval procedures > Predefined** category.

For more information about default approval procedures for attestation, see:

- AA - Attestor of the role from the role assignment to attest: [Determining attestors via attestation objects](#) on page 88
- AD - Attestor of the primary department of the identity to attest: [Determining attestors via the primary role of the identity to attest](#) on page 90
- AL - Attestor of the primary location of the identity to attest: [Determining attestors via the primary role of the identity to attest](#) on page 90
- AM - Manager of the linked identity: [Determining attestors via attestation object managers](#) on page 93
- AN - Attestor of the system entitlement or system role to attest: [Determining attestors using the service item of the attestation object](#) on page 92
- AO - Attestor of the primary business role of the identity to attest: [Determining attestors via the primary role of the identity to attest](#) on page 90
- AP - Attestor of the primary cost center of the identity to attest: [Determining attestors via the primary role of the identity to attest](#) on page 90
- AR - Attestor of the compliance rule to attest: [Determining attestors via attestation objects](#) on page 88
- AS - Approver of the attestation policy: [Determining owners or approvers of attestation policies](#) on page 105
- AT - Attestor of the role to attest: [Determining attestors via attestation objects](#) on page 88
- AY - Attestor of the company policy to attest: [Determining attestors via attestation objects](#) on page 88
- BA - Owner of the application: [Determining attestors via owners of the attestation objects](#) on page 102
- BE - Approver of the application entitlement: [Determining attestors via owners of the attestation objects](#) on page 102

- C6 - Proposed manager: [Determining attestors via attestation object managers](#) on page 93
- CD - Calculated approval: [Calculated approval](#) on page 106
- CM - Manager of the identity to attest: [Determining attestors via attestation object managers](#) on page 93
- CN - Challenge the approval decision: [Determining attested identities as attestors](#) on page 98
- CS - Identity themselves: [Determining attested identities as attestors](#) on page 98
- DM - Department manager of identity to attest: [Determining attestors via attestation object managers](#) on page 93
- EA - Identity of the user account to attest: [Determining identities linked to user accounts as attestors](#) on page 99
- ED - Department manager for system entitlement attestation: [Determining attestors via attestation object managers](#) on page 93
- EM - Identity's manager for system entitlement attestation: [Determining attestors via attestation object managers](#) on page 93
- EN - Target system manager of the system entitlement to attest: [Determining target system managers as attestors](#) on page 99
- EO - Product owner of the system entitlement to attest: [Determining attestors via product owners](#) on page 101
- EX - Approvals to make externally: [Approvals to be made externally](#) on page 107
- KA - Product owner and additional owner of the Active Directory group: [Determining attestors via product owners](#) on page 101
- LM - Location manager of identity to attest: [Determining attestors via attestation object managers](#) on page 93
- MD - Department manager of the linked identity: [Determining attestors via attestation object managers](#) on page 93
- MO - Business role manager of the identity to attest: [Determining attestors via attestation object managers](#) on page 93
- OA - Product owner: [Determining attestors via product owners](#) on page 101
- OM - Manager of a specific role: [Determining managers or members of a role as attestors](#) on page 97
- OP - Owner of a privileged object: [Determining attestors via owners of the attestation objects](#) on page 102
- OR - Members of a certain role: [Determining managers or members of a role as attestors](#) on page 97
- OS - Target system manager of a PAM appliance: [Determining target system managers as attestors](#) on page 99
- OT - Attestor of the service item to assign: [Determining attestors using the service item of the attestation object](#) on page 92

- PA - Additional owner of the Active Directory group: [Determining attestors via owners of the attestation objects](#) on page 102
- PM - Cost center manager of identity to attest: [Determining attestors via attestation object managers](#) on page 93
- PO - Proposed owner: [Determining attestors via owners of the attestation objects](#) on page 102
- PW - Owner of the attestation policy: [Determining owners or approvers of attestation policies](#) on page 105
- RE - Manager of the system role to attest: [Determining attestors via attestation object managers](#) on page 93
- RM - Role manager for membership attestation: [Determining attestors via attestation object managers](#) on page 93
- RR - Role manager for role and role assignment attestation: [Determining attestors via attestation object managers](#) on page 93
- SO - Target system manager of the system entitlement to attest (all target systems): [Determining target system managers as attestors](#) on page 99
- SP - Owner of service principals: [Determining attestors via owners of the attestation objects](#) on page 102
- WC - Waiting for further approval: [Waiting for further approval](#) on page 108
- XM - Manager of the identity for all attestations: [Determining attestors via attestation object managers](#) on page 93

Related topics

- [Setting up approval procedures](#) on page 109
- [Determining the responsible attestors](#) on page 116

Determining attestors via attestation objects

An **Attestors** application role can be assigned to different objects in One Identity Manager. Different approval procedures can be used to identify members of this application role as attestors when these objects are attested.

AA - Attestor of the role from the role assignment to attest

Installed modules: Target System Base Module, System Roles Module

Attestation base objects:

- System entitlements assignments to departments, locations, cost centers, business roles, or IT Shop structures (such as <BaseTree>HasUNSGroupB, <BaseTree>HasADSGroup, <BaseTree>HasEBSResp)
- System role assignments to departments, locations, cost centers, business roles, or IT Shop structures (<BaseTree>HasESet)

Attestors:

- Members of the **Identity Management | Organizations | Attestors** application role assigned to the department, cost center, location to attest.
- Members of the **Identity Management | Business roles | Attestors** application role assigned to the department, cost center, location to attest.
- Members of the **Request & Fulfillment | IT Shop | Attestors** application role assigned to the IT Shop structure or IT Shop template to attest.

AT - Attestor of the role to attest

Attestation base objects:

- Departments (Department)
- Locations (Locality)
- Cost centers (ProfitCenter)
- Business roles (Org)
- IT Shop Structures (ITShopOrg)
- IT Shop Templates (ITShopSrc)

Attestors:

- Members of the **Identity Management | Organizations | Attestors** application role assigned to the department, cost center, location to attest.
- Members of the **Identity Management | Business roles | Attestors** application role assigned to the department, cost center, location to attest.
- Members of the **Request & Fulfillment | IT Shop | Attestors** application role assigned to the IT Shop structure or IT Shop template to attest.

AR - Attestor of the compliance rule to attest

Installed modules: Compliance Rules Module

Attestation base objects:

- Rules (ComplianceRule)
- Rule violations (PersonInNonCompliance)

Attestors:

- Members of the **Identity & Access Governance | Identity Audit | Attestor** application role assigned to the compliance rule or rule violation to attest.

AY - Attestor of the company policy to attest

Installed modules: Company Policies Module

Attestation base objects:

- Company policies (QERPolicy)
- Policy violations (QERPolicyHasObject)

Attestors:

- Members of the **Identity & Access Governance | Company policies | Attestors** application role assigned to the compliance rule or rule violation to attest.

For the **AT** and **AA** approval procedures the following also applies:

Attestors of the parent roles/IT Shop structures are determined if

- the role or IT Shop structure is not directly assigned an attestor
- the assigned application role has no members.

If still no attestor can be determined, the attestation case is presented to the attestors of the associated role class for approval.

Attestors of child business roles are determined if

- the attestation object is a business role or the assignment to a business role and
- the associated role class inheritance is bottom-up and
- the business role is not directly assigned an attestor or
- the assigned application role has no members.

Related topics

- [Default approval procedures](#) on page 86

Determining attestors via the primary role of the identity to attest

You can assign an **Attestors** application role to hierarchical roles. When attesting identities, different approval procedures are available to determine which members of this application role are attestors.

AD - Attestor of the primary department of the identity to attest

Attestation base objects:

- Identities (Person)
- Requests (PersonWantsOrg)

Attestors:

- Members of the **Identity Management | Organizations | Attestors** application role assigned to the primary department of the identity to attest. The primary department of the request recipient is used to attest the request.

AD - Attestor of the primary location of the identity to attest

Attestation base objects:

- Identities (Person)
- Requests (PersonWantsOrg)

Attestors:

- Members of the **Identity Management | Organizations | Attestors** application role assigned to the primary location of the identity to attest. The primary location of the request recipient is used to attest the request.

AO - Attestor of the primary business role of the identity to attest

Installed modules: Business Roles Module

Attestation base objects:

- Identities (Person)
- Requests (PersonWantsOrg)

Attestors:

- Members of the **Identity Management | Organizations | Attestors** application role assigned to the primary business role of the identity to attest. The primary business role of the request recipient is used to attest the request.

AD - Attestor of the primary cost center of the identity to attest

Attestation base objects:

- Identities (Person)
- Requests (PersonWantsOrg)

Attestors:

- Members of the **Identity Management | Organizations | Attestors** application role assigned to the primary cost center of the identity to attest. The primary cost center of the request recipient is used to attest the request.

The following applies for all named approval procedures: Attestors of parent roles are determined if

- the primary role is not directly assigned an attestor or
- the assigned application role does not have any members.

If still no attestor can be determined, the attestation case is presented to the attestors of the associated role class for approval.

The following applies for the **AO** approval procedure: Attestors of child business roles are determined if

- business role inheritance is bottom-up and
- the primary business role is not directly assigned an attestor or
- the assigned application role does not have any members.

Related topics

- [Default approval procedures](#) on page 86

Determining attestors using the service item of the attestation object

You can assign an **Attestors** application role to service items and service categories. Different approval procedures can be used to identify members of this application role as attestors when objects are attested that have service items assigned to them.

AN - Attestor of the attested system entitlement or system role

Installed modules: Target System Base Module, System Roles Module

Attestation base objects:

- System entitlements assignments to departments, locations, cost centers, business roles, or IT Shop structures (such as <BaseTree>HasUNSGroupB, <BaseTree>HasADSGroup, <BaseTree>HasEBSResp)
- System role assignments to departments, locations, cost centers, business roles, or IT Shop structures (<BaseTree>HasESet)

Attestors:

- Members of the **Request & Fulfillment | IT Shop | Attestors** application role assigned to the service item associated with the attested system entitlement or system role.

OT - Attestor of assigned service item

Attestation base objects:

- Service items (AccProduct)
- System entitlements (UNSGroup)
- User accounts: system entitlement assignments (UNSAccountInUNSGroup)
- Account definitions (TSBAccountDef) and identity assignments (PersonHasTSBAccountDef)
- System roles (ESet) and identity assignments (PersonHasESet)
- Subscribable reports (RPSReport) and identity assignments (PersonHasRPSReport)
- Resources (QERRResource) and identity assignments (PersonHasQERRResource)
- Multi-requestable resources (QERRReuse)
- Multi requestable/unsubscribable resources (QERRReuseUS)
- Assignment resources (QERAssign)
- Software (Application) and software assignment (PersonHasApp)
- PAM User accounts: user group assignments (PAGUserInUsrGroup)
- Disabled Microsoft Entra ID service plans (AADDeniedServicePlan) and Microsoft Entra ID user accounts: disabled Microsoft Entra ID service plans (AADUserHasDeniedService)

Attestors:

- Members of the application role **Request & Fulfillment | IT Shop | Attestors** assigned to the service item associated with the attestation object.

If there is no attestor directly assigned to the service item or the assigned application role does not have any members, attestors are taken from the associated service category.

Related topics

- [Default approval procedures](#) on page 86

Determining attestors via attestation object managers

Managers can be assigned to identities, hierarchical roles, and system roles. Different approval procedures can be used to identify managers as attestors when these objects are attested. If user accounts are linked with identities, their managers can attest these user accounts.

C6 - Proposed manager

If an identity is not yet assigned to a manager, it can propose a manager. The manager then confirms that they will take on this task. The approval procedure is used by default to assign managers to identities that do not have a manager assigned to them (**Attestation of initial manager assignment** attestation policy).

Attestation base objects:

- Identities (Person)

Attestors:

- Identity proposed as manager for the identity to attest.

CM - Manager of the identity to attest

Attestation base objects:

- Identities (Person)
- Identities: memberships in application roles (PersonInAERole)
- Identities: department memberships (PersonInDepartment)
- Identities: location memberships (PersonInLocality)
- Identities: cost center memberships (PersonInProfitCenter)
- Identities: business role memberships (PersonInOrg)
- Identities: system role assignments (PersonHasESet)
- Account definition assignments (PersonHasTSBAccountDef)

Attestors:

- Manager of the identity to attest or with memberships or assignments to attest.

DM - Department manager of identity to attest

Attestation base objects:

- Identities (Person)
- Identities: department memberships (PersonInDepartment)

Attestors:

- Manager, deputy manager, and all additional managers of the primary department of the identity to attest if identities are being attested.
- Manager, deputy manager, and all additional managers of the department to attest, if secondary memberships in departments are being attested.

ED - Department manager for system entitlement attestation

Installed modules: Target System Base Module

Attestation base objects:

- Assignments of user account to system entitlements, ADSAccountInADSGroup for example.

Attestors:

- Manager, deputy manager, and all additional managers of the primary department of the identity linked to the user account.

MD - Department manager of account's person

Installed modules: Target System Base Module

Attestation base objects:

- User accounts (UNSAccount)

Attestors:

- Manager, deputy manager, and all additional managers of the primary department of the identity linked to the user account.

EM - Identity manager for system entitlement attestation

Installed modules: Target System Base Module

Attestation base objects:

- User accounts: system entitlement assignments (UNSAccountInUNSGroup)
- PAM user accounts: user group assignments (PAGUserInUsrGroup)
- OneLogin user accounts: application assignments (OLGUserHasOLGApplication)

Attestors:

- Identity's department manager to whom the user account is connected.

AM - Manager of account's person

Installed modules: Target System Base Module

Attestation base objects:

- All target system user accounts; for example, **Microsoft Entra ID user accounts** (AADUser) or **User accounts** (UNSAccountB)

Attestors:

- Identity's department manager to whom the user account is connected.

LM - Location manager of identity to attest

Attestation base objects:

- Identities (Person)
- Identities: location memberships (PersonInLocality)

Attestors:

- Manager, deputy manager, and all additional managers of the primary location of the identity to attest if identities are being attested.
- Manager, deputy manager, and all additional managers of the location to attest, if secondary memberships in locations are being attested.

MO - Business role manager of the identity to attest

Installed modules: Business Roles Module

Attestation base objects:

- Identities (Person)
- Identities: business role memberships (PersonInOrg)

Attestors:

- Manager, deputy manager, and all additional managers of the primary business role of the identity to attest if identities are being attested.
- Manager, deputy manager, and all additional managers of the business role to attest, if secondary memberships in business roles are being attested.

PM - Cost center manager of identity to attest

Attestation base objects:

- Identities (Person)
- Identities: department memberships (PersonInDepartment)

Attestors:

- Manager, deputy manager, and all additional managers of the primary cost center of the identity to attest if identities are being attested.
- Manager, deputy manager, and all additional managers of the cost center to attest, if secondary memberships in cost centers are being attested.

RE - Manager of the system role to attest

Installed modules: System Roles Module

Attestation base objects:

- System roles (ESet)
- Identities: system role assignments (PersonHasESet)
- Departments: system role assignments (DepartmentHasESet)
- Business roles: system role assignments (OrgHasESet)
- IT Shop structures: system role assignments (ITShopOrgHasESet)
- IT Shop templates: system role assignments (ITShopSrcOrgHasESet)
- Cost centers: system role assignments (ProfitCenterHasESet)
- Locations: system role assignments (LocalityHasESet)

Attestors:

- Manager of the system role to attest or with assignment to identities or hierarchical roles to attest.

RM - Role manager for membership attestation

Attestation base objects:

- Identities: memberships in application roles (PersonInAERole)
- Identities: department memberships (PersonInDepartment)
- Identities: location memberships (PersonInLocality)
- Identities: cost center memberships (PersonInProfitCenter)
- Identities: business role memberships (PersonInOrg)
- Identities: IT Shop structure memberships (PersonInITShopOrg)

Attestors:

- Manager, deputy manager, and all additional managers of the role with memberships to attest.

RR - Role manager for role and role assignment attestation

Attestation base objects:

- Departments (Department)
- IT Shop Structures (ITShopOrg)
- Locations (Locality)
- Business roles (Org)
- Cost centers (ProfitCenter)
- IT Shop Templates (ITShopSrc)
- Application roles (AERole)
- All assignments of system entitlements or system roles to hierarchical roles, ITShopOrgHasAADSubSku or LocalityHasESet for example

Attestors:

- Manager, deputy manager, and all additional managers of the role to attest or with assignments to attest.

XM - Manager of the identity for all attestations

Attestation base objects:

- Identities (Person)
- Identities: memberships in application roles (PersonInAERole)
- Identities: department memberships (PersonInDepartment)
- Identities: location memberships (PersonInLocality)
- Identities: cost center memberships (PersonInProfitCenter)
- Identities: business role memberships (PersonInOrg)
- Identities: system role assignments (PersonHasESet)
- User accounts (UNSAccount)
- User accounts: system entitlement assignments (UNSAccountInUNSGroup)

Attestors:

- Manager of the identity to attest or with memberships or linked user accounts to attest.

Related topics

- [Default approval procedures](#) on page 86
- [Determining attested identities as attestors](#) on page 98

Determining managers or members of a role as attestors

A hierarchical role can be assigned to an approval step. Different approval procedures can be used to determine members and managers of this role as attestors.

OM - Manager of a specific role

Attestation base objects:

- Departments (Department)
- Cost centers (ProfitCenter)
- Locations (Locality)
- Business roles (Org)

Attestors:

- Manager, deputy manager, and all additional managers of the role specified in the approval step.

OR - Members of a certain role

Attestation base objects:

- Departments (Department)
- Cost centers (ProfitCenter)
- Locations (Locality)
- Business roles (Org)
- Application roles (AERole)

Attestors:

- All members of the role specified in the approval step.

Related topics

- [Default approval procedures](#) on page 86
- [Properties of an approval step](#) on page 78

Determining attested identities as attestors

Attested identities can themselves be determined as attestors and thus influence the approval sequence. The following approval procedures can be used for this:

CS - Identity themselves

An identity can attest to the correctness of their own main data to confirm that it has been entered correctly, for example. The approval procedure is used by default to assign managers to identities that do not have a manager assigned to them (**Attestation of initial manager assignment** attestation policy).

Attestation base objects:

- Identities (Person)

Attestors:

- Identity to attest.

CN - Challenge the approval decision

Approval procedure used to challenge denied attestations. For example, affected identities can prevent necessary entitlements being removed. For more information, see [Setting up the challenge phase](#) on page 124.

Attestation base objects:

- Identities: memberships in application roles (PersonInAERole)
- Identities: department memberships (PersonInDepartment)
- Identities: location memberships (PersonInLocality)

- Identities: cost center memberships (PersonInProfitCenter)
- Identities: business role memberships (PersonInOrg)
- Identities: system role assignments (PersonHasESet)
- All target system user accounts; for example, **Microsoft Entra ID user accounts** (AADUser) or **User accounts** (UNSAccountB)
- User account assignments to system entitlements in all target systems; for example, **User accounts: system entitlement assignments** (UNSAccountInUNSGroup)

Attestors:

- Identity with assignments to attest or that is connected to the user account to attest.

Related topics

- [Default approval procedures](#) on page 86
- [Determining attestors via attestation object managers](#) on page 93

Determining identities linked to user accounts as attestors

If user accounts are linked with identities, the identities can attest these user accounts.

EA - Identity of the user account to attest

Installed modules: Target System Base Module

Attestation base objects:

- User accounts (UNSAccount)
- OneLogin User accounts: application assignments (OLGUserHasOLGApplication)

Attestors:

- Identity linked to the user account.

Related topics

- [Default approval procedures](#) on page 86

Determining target system managers as attestors

Target system managers are given the task of attesting system entitlements, assigned user accounts and assignments of system entitlements to hierarchical roles. All identities that are assigned to the associated application role are determined as attestors. In addition, members of all the parent application roles are determined as attestors. The following approval procedures can be used for this:

EN - Target system manager of the system entitlement to attest

Installed modules: Target System Base Module

Attestation base objects:

- System entitlements (UNSGroup)
- System entitlements: system entitlements assignments (UNSGroupInUNSGroup)
- Groups (UNSGroupB)
- Groups: group assignments (UNSGroupBInUNSGroupB)
- Departments: system entitlements assignments (DepartmentHasUNSGroup)
- Business roles: system entitlements assignments (OrgHasUNSGroup)
- Cost centers: system entitlements assignments (ProfitCenterHasUNSGroup)
- Locations: system entitlements assignments (LocalityHasUNSGroup)
- OneLogin user accounts: application assignments (OLGUserHasOLGApplication)

Attestors:

- Target system manager of the target system that has this system entitlement.

SO - Target system manager of the system entitlement to attest (all target systems)

Installed modules: Target System Base Module

Attestation base objects:

- All target system user accounts; for example **Microsoft Entra ID user accounts** (AADUser) or **User accounts** (UNSAccountB)
- All target system entitlements; for example **SAP structural profiles** (SAPHRP) or **Cloud groups** (CSMGroup)
- User account assignments to system entitlements in all target systems; for example, **User accounts: system entitlement assignments** (UNSAccountInUNSGroup)

Attestors:

- Target system manager of the target system that has this system entitlement or user account.

OS - Target system owner of a PAM appliance

Installed modules: Privileged Account Governance Module

Attestation base objects:

- PAM account groups (PAGAccGroup)
- PAM appliances (PAGAppliance)
- PAM assets (PAGAsset)
- PAM asset accounts (PAGAstAccount)
- PAM asset groups (PAGAstGroup)

- PAM directory accounts (PAGDirAccount)
- PAM user accounts (PAGUser)
- PAM access options (PAGUserAttestation)
- PAM user groups (PAGUsrGroup)

Attestors:

- Target system managers of the PAM appliance that belongs to the attestation object.

Related topics

- [Default approval procedures](#) on page 86
- [Determining attestors via owners of the attestation objects](#) on page 102

Determining attestors via product owners

An application role for product owners can be assigned to the service items of objects that can be requested from the IT Shop. Different approval procedures can be used to determine members of this application role as attestors.

Prerequisites:

- A service item must be assigned to the attestation objects.
To attest Microsoft Teams teams or Microsoft Teams team memberships, a service item must be assigned to the Microsoft 365 group associated with a team.
- There must be an application role for product owners assigned to the service item.

OA - Product owner

Attestation base objects:

- Service items (AccProduct)
- System entitlements, AADGroup for example.
If there is a requirement to attest Microsoft Teams teams or Microsoft Teams team memberships, the approval procedure finds the product owner of the Microsoft 365 groups that are associated with the teams to attest.
- Assignments of system entitlements to system entitlements, ADSSGroupInADSSGroup for example.
- Assignments of user account to system entitlements, UNSAccountInUNSSGroup for example.
- System role assignment to identities (PersonHasESet).

Attestors:

- All members of the application role assigned for product owners

EO - Product owner of the system entitlement to attest

Installed modules: Target System Base Module, System Roles Module

Attestation base objects:

- System roles: assignments (ESetHasEntitlement)
- All user account assignments to system entitlements; for example, **User accounts: system entitlement assignments** (UNSAccountInUNSGroup) or **SAP user accounts: assignments to roles** (SAPUserInSAPRole)
- All system entitlement or system role assignments to roles; for example **Roles and organizations: Active Directory group assignments** (BaseTreeHasADSGroup) or **Locations: EBS entitlement assignments** (LocalityHasEBSResp)

Attestors:

- Product owner of the service item to which the system entitlement or system role is assigned.

KA - Product owner and additional owner of the Active Directory group

Installed modules: Active Roles Module

Attestation base objects:

- Active Directory groups (ADSGroup)
- Active Directory user Accounts: assignments Group (ADSAccountInADSGroup)
- User accounts: system entitlement assignments (UNSAccountInUNSGroup)
- System entitlements (UNSGroup)

Attestors:

- Product owner of the service item to which the system entitlement or system role is assigned.
- Product owner and additional owner of the Active Directory group.

If the groups were added automatically to the IT Shop, the account managers are identified as product owners. The additional owners of the Active Directory groups are determined only if the **TargetSystem | ADS | ARS_SSM** configuration parameter is enabled. For more information about these functions, see the *One Identity Manager Administration Guide for One Identity Active Roles Integration*.

Related topics

- [Default approval procedures](#) on page 86
- [Zusätzlicher Besitzer einer Active Directory Gruppe als Attestierer ermitteln](#)

Determining attestors via owners of the attestation objects

Special owners are assigned to various objects in One Identity Manager. Different approval procedures can be used to determine these owners as attestors.

PO - Proposed owner

In the Web Portal, owners can be assigned to devices or system entitlements. In the context of an attestation, the selected owner can confirm that this assignment is correct. For more information about this, see the *One Identity Manager Web Portal User Guide*.

Attestation base objects:

- Devices (Hardware)
- System entitlements (UNSGroup)

Attestors:

- Proposed owner

OP - Owner of a privileged object

An **Owners** application role can be assigned to privileged objects of a Privileged Account Management system. If privileged objects are attested, it is possible to determine members of these application roles as attestors. The owners attest the possible user access to these privileged objects.

Installed modules: Privileged Account Governance Module

Attestation base objects:

- PAM account groups (PAGAccGroup)
- PAM appliances (PAGAppliance)
- PAM assets (PAGAsset)
- PAM asset accounts (PAGAstAccount)
- PAM asset groups (PAGAstGroup)
- PAM directory accounts (PAGDirAccount)
- PAM access options (PAGUserAttestation)
- PAM user groups (PAGUsrGroup)

Attestors:

- Members of the **Privileged Account Governance | Asset and account owners** application role or a child application role with the attestation object assigned to it.

PA - Secondary owner of Active Directory group

If Active Directory is connected via the Active Roles connector and memberships in Active Directory groups can be requested in IT Shop, additional owners can be assigned to the Active Directory groups. These additional owners can be determined as attestors. For more information about these functions, see the *One Identity Manager Administration Guide for One Identity Active Roles Integration*.

Installed modules: Active Roles Module

Prerequisites:

The **TargetSystem | ADS | ARS_SSM** configuration parameter is set. The column **Additional owners** is only available in this case.

Attestation base objects:

- Active Directory groups (ADSGroup)
- Active Directory user accounts: group assignments (ADSAccountInADSGroup)

Attestors:

- Additional owners of the Active Directory group

Identities are determined that are:

- A member in the assigned Active Directory group through their Active Directory user account
- Linked to the assigned Active Directory user account

SP - Owner of service principals

An **Owners** application role can be assigned to Microsoft Entra ID service principals. If service principals are attested, members of these application roles are determined as attestors.

Installed modules: Microsoft Entra ID Module

Attestation base objects:

- Microsoft Entra ID service principals (AADServicePrincipal)

Attestors:

- Members of the **Target systems | Microsoft Entra ID | Owner of service principals** application role or a child application role that is assigned to the attestation object.

BA - Owner of the application

Owners can be assigned to applications in the Application Governance Module. When attesting application entitlements, owners of the applications under which the application entitlements are provided can be determined as attestors. For more information about applications and application entitlements, see the *One Identity Manager Application Governance User Guide*.

Installed modules: Application Governance Module

Attestation base objects:

- Application entitlements (AOB Entitlement)

Attestors:

- Members of the **Application Governance | Owners** application role or child application role assigned to the application that is provided under the application entitlement to attest.

BE - Approver of the application entitlement

In the Application Governance Module, approvers can be assigned to applications and application entitlements. When attesting application entitlements, approvers of applications under which the application entitlements are provided and the additional approvers of the application entitlements can be determined as attestors. For more information about applications and application entitlements, see the *One Identity Manager*

Application Governance User Guide.

Installed modules: Application Governance Module

Attestation base objects:

- Application entitlements (AOB Entitlement)

Attestors:

- Members of the **Application Governance | Approvers** application role or a child application role assigned to the application that is provided under the application entitlement to attest.
- Members of the application role or business role assigned to the application entitlement to attest as an additional approver.

Related topics

- [Default approval procedures](#) on page 86
- [Determining attestors via product owners](#) on page 101
- [Determining target system managers as attestors](#) on page 99

Determining owners or approvers of attestation policies

Both single identities as well as application roles can be assigned as owners to attestation policies. You can also assign any identity to the attestation policies as approver. The owners and approvers can be determined as attestors for attesting any property.

AS - Approver for attestation policy

Attestation base objects:

- Any

Attestors:

- All identities assigned as approvers to the attestation policy being run.

PW - Owner of the attestation policy

Attestation base objects:

- Any

Attestors:

- All members of the owner (application role) and the identity assigned directly as owner of the attestation policy being run.

The **PW** approval procedure is used to carry out an additional test step in approval processes. In doing so, the attestation policy owners have the opportunity to review the details of the attestation run. For more information, see [Phases of attestation](#) on page 121.

Related topics

- [Default approval procedures](#) on page 86
- [Assigning approvers to attestation policies](#) on page 44

Calculated approval

NOTE: Only one approval step can be defined with the **CD** approval procedure per approval level.

If you want to make attestation dependent on specific conditions, use the **CD** approval procedure. This procedure does not determine an attestor. One Identity Manager makes the decision depending on the condition that is formulated in the approval step.

You can use the procedure for any attestation base objects. You create a condition in the approval step. If the condition returns a result, the approval step is approved through One Identity Manager. If the condition does not return a result, the approval step is denied by One Identity Manager. If there are no further approval steps, the approval procedure is either finally granted or denied.

To enter a condition for the CD approval procedure

1. Edit the approval step properties.
For more information, see [Editing approval levels](#) on page 77.
2. In the **Condition** input field, enter a valid WHERE clause for database queries. You can enter the SQL query directly or with a wizard.

Example of a simple approval workflow with the CD approval procedure:

External identities should be attestation by their managers. If no manager is assigned, the members of a designated application role must attest the identities.

You can find all external identities, who have managers assigned to them by using the **CD** approval procedure and the following condition.

```
EXISTS
(SELECT 1 FROM
  (SELECT xobjectkey FROM Person WHERE (IsExternal = 1)
   AND (EXISTS
    (SELECT 1 FROM(SELECT UID_Person FROM Person WHERE 1 = 1) as X
    WHERE X.UID_Person = Person.UID_PersonHead) )) as X
 WHERE X.xobjectkey = AttestationCase.ObjectKeyBase)
```

If the condition is fulfilled, the external identity's manager can attest the identity. To do this, add an approval step in the positive approval path with the **CM** approval procedure.

If the condition is not fulfilled, the identity is attested by the member of a designated application role. To do this, add an approval step in the negative approval path with the **OR** approval procedure and assign the application role.

Related topics

- [Default approval procedures](#) on page 86

Approvals to be made externally

Use external approvals (**EX** approval procedure) if an attestation needs to be approved as soon as a defined event from outside One Identity Manager takes place. You can also use this procedure to reach attestors with no access to One Identity Manager.

Specify an event in the approval step that triggers an external approval. The event triggers a process that initiates the external approval for the attestation case and evaluates the result of the approval decision. The approval process waits for the external decision to be passed to One Identity Manager. Define the subsequent approval steps depending on the result of the external approval.

To use an approval procedure

1. In the Designer, define your own processes that:
 - Triggers an external approval.
 - Analyzes the results of the external approval.
 - Grants or denies approval in the subsequent external approval step in One Identity Manager.
2. Defines an event that starts the process for external approval. Enter the result in **Result** in the approval step.

If the external event occurs, the approval step status in One Identity Manager must be changed. Use the `CallMethod` process task with the `MakeDecision` method for this. Pass the following parameters to the process task:

MethodName: Value = "MakeDecision"

ObjectType: Value = "AttestationCase"

Param1: Value = "sa"

Param2: Value = <approval> ("true" = granted; "false" = denied)

Param3: Value = <reason for approval decision>

Param4: Value = <standard reason>

Param5: Value = <number approval steps> (PWODecisionStep.SubLevelNumber)

WhereClause: Value = "UID_AttestationCase = '& \$UID_AttestationCase\$ &'"

Use these parameters to specify which attestation case is to be approved by external approval (WhereClause). Param1 specifies the attestor. The attestor is always the **sa** system user. Param2 passes down the approval decision. If the attestation was granted, a value of **True** must be returned. If the attestation was denied, a value of **False** must be returned. Use Param3 to pass a reason text for the approval decision; use Param4 to pass a predefined standard reason. If more than one external approval steps have been defined in an

approval level, use Param5 to pass the approval step count. This ensures the approval is aligned with the correct approval step.

Example for using the EX approval procedure

All compliance rules should be checked and attested by an external assessor. The attestation object data should be made available as a PDF on an external share. The assessor should save the result of the attestation in a text file on the external share. Use the **EX** approval procedure to make external approvals and define:

- A P1 process that saves a PDF report with data about the attestation object data and the attestation procedure on an external share
- An E1 event that starts the P1 process

In the approval step, enter E1 in the **Event** field, and enter P1 in the process as the trigger for the external decision.

- A P2 process that checks the share for new text files, evaluates the content, and calls the One Identity Manager CallMethod process task the method MakeDecision method
- An E2 event that starts the P2 process
- A schedule that starts the E2 event on a regular basis

For more information about creating processes, see the *One Identity Manager Configuration Guide*. For more information about setting up schedules, see the *One Identity Manager Operational Guide*.

Related topics

- [Default approval procedures](#) on page 86
- [Properties of an approval step](#) on page 78

Waiting for further approval

NOTE: Only one approval step can be defined with the **WC** approval procedure per approval level.

If you want to ensure that a specific data state exists in One Identity Manager before an attestation case is finally approved, then use the **WC** approval procedure. Use a condition to specify which prerequisites have to be fulfilled so that attestation can take place. The condition is evaluated as a function call, which must accept the attestation case UID as a parameter (AttestationCase.UID_AttestationCase). You use this UID to reference the attestation object. The function must define three return values as integer values. One of the following actions is carried out depending on the function's return value.

Table 27: Return value for deferred approval

Return value	Action
Return value > 0	The condition is fulfilled. Deferred approval has completed successfully. The next approval step (in case of success) is carried out.
Return value = 0	The condition is not yet fulfilled. Approval is rolled back and is retested the next time DBQueue Processor runs.
Return value < 0	The condition is not fulfilled. Deferred approval has failed. The next approval step (in case of failure) is carried out.

To use an approval procedure

1. Create a database function which tests the condition for the attestation.
2. Create an approval step with the WC approval procedure. Enter the function call in **Condition**.
Syntax: dbo.<function name>
3. Specify an approval step in the case of success. Use the approval procedure with which One Identity Manager can determine the attestors.
4. Specify an approval step in the case of failure.


Related topics

- [Default approval procedures](#) on page 86

Setting up approval procedures

You can create your own approval procedures if the default approval procedures for finding the responsible attestors do not meet your requirements. The condition used to determine the attestors is formulated as a database query. Several queries may be combined into one condition.

To set up an approval procedure

1. In the Manager, select the **Attestation > Basic configuration data > Approval procedures** category.
2. Click  in the result list.
3. Edit the approval procedure main data.
4. Save the changes.

To edit an approval procedure

1. In the Manager, select the **Attestation > Basic configuration data > Approval procedures > Predefined** category.
2. Select an approval procedure from the result list and run the **Change main data** task.
3. Edit the approval procedure main data.
4. Save the changes.

To edit the condition

1. In the Manager, select the **Attestation > Basic configuration data > Approval procedures > Predefined** category.
2. Select an approval procedure from the result list.
3. Select **Change queries for approver selection**.

Related topics

- [General main data of an approval procedure](#) on page 110
- [Queries for finding attestors](#) on page 111
- [Specifying permitted approval procedures for tables](#) on page 114
- [Copying an approval procedure](#) on page 115
- [Deleting approval procedures](#) on page 116

General main data of an approval procedure

Enter the following main data of an approval procedure.

Table 28: General main data of an approval procedure

Property	Description
Approval procedure	Descriptor for the approval procedure (maximum two characters).
Short description	Short phrase to describe the approval procedure.
DBQueue Processor task	Approvals can either be made automatically through a DBQueue Processor calculation task or by specified approvers. Assign a custom DBQueue Processor task if the approval procedure should make an automatic approval decision. You cannot assign a DBQueue Processor task if there is a query pending to determine attestors.
Max. approvers	Maximum number of attestors to be determined by the approval procedure. Specify how many identities must really make approval decisions in the approval steps used by this approval

Property	Description
	procedure.
Sort order	<p>Value for sorting approval procedures in the drop-down.</p> <ul style="list-style-type: none"> Specify the value 10 to display this approval procedure at the top of the drop-down when you set up an approval step. To hide the approval procedure in the drop-down, define a negative value. These approval procedures are displayed in the Manager under the Hidden in Workflow Editor filter. <p>TIP: It is also possible to change the order for default approval procedures. Move more frequently used approval procedures to the top; hide unused approval procedures.</p>
Description	Detailed description of the approval procedure.

Related topics

- [Properties of an approval step](#) on page 78
- [Setting up approval procedures](#) on page 109
- [Default approval procedures](#) on page 86

Queries for finding attestors

The condition used to determine the attestors is formulated as a database query. Several queries may be combined into one condition. This adds all identities determined by single queries to the group of attestors.

To edit the condition

1. In the Manager, select the **Attestation > Basic configuration data > Approval procedures > Predefined** category.
2. Select an approval procedure from the result list.
3. Select **Change queries for approver selection**.

To create single queries

1. Click **Add**.
This inserts a new row in the table.
2. Mark this row. Enter the query properties.
3. Add more queries if required.
4. Save the changes.

To edit a single query

1. Select the query you want to edit in the table. Edit the query's properties.
2. Save the changes.

To remove single queries

1. Select the query you want to remove in the table.
2. Click **Delete**.
3. Save the changes.

Table 29: Query properties

Property	Description
Approver selection	Query identifier that determines the attestors.
Query	<p>Database query for determining the attestors.</p> <p>The database query must be formulated as a select statement. The column selected by the database query must return a UID_Person. Every query must return a value for UID_PWORulerOrigin. The query returns one or more identities to whom the attestation case is presented for approval. If the query fails to return a result, the attestation procedure is canceled.</p> <p>A query contains exactly one select statement. To combine several select statements, create several queries.</p> <p>If a DBQueue Processor task is assigned, you cannot enter a query to determine attestors.</p>
Query for recalculating	Database query to determine attestation transactions that require recalculation of their attestors.

You can, for example, determine predefined attestors with the query (example 1). The attestor can also be found dynamically depending on the attestation case to approve. To do this, within the database query, using the @UID_AttestationCase variable to access the attestation case (example 2).

Example 1

The attestation cases should be approved by a specific attestor.

Query:

```
select UID_Person, null as UID_PWORulerOrigin from Person where InternalName='User, JB'
```

Example 2

All active compliance rules should be attested by the respective rule supervisor.

Query:

```
select pia.UID_Person, null as UID_PWORulerOrigin from AttestationCase ac
  join ComplianceRule cr on cr.XObjectKey = ac.ObjectKeyBase and cr.IsWorkingCopy
= '0'
  join PersonInBaseTree pia on pia.UID_Org = cr.UID_OrgResponsible and pia.XOrigin
> 0
where ac.UID_AttestationCase = @UID_AttestationCase
```

Taking delegation into account

To include delegation when determining attestors, use the query to also determine the identities to whom a responsibility has been delegated. If the managers of hierarchical roles are to make the approval decision, determine the attestors from the `HelperHeadOrg` table. This table groups together all managers, deputy managers, and all other hierarchical role managers as well as their deputies and the identities to whom a responsibility has been delegated.

If the members of business or application roles are to make the approval decision, determine the approvers from the `PersonInBaseTree` table. This table groups together all hierarchical role members and identities to whom a responsibility has been delegated.

To exclude deactivated identities, check the `XOrigin` column for a value greater than 0. For more information about values in the `XOrigin` column, see the *One Identity Manager Identity Management Base Module Administration Guide*.

Determine the `UID_PWORulerOrigin` in order to notify delegators when the recipient of the delegation has made a decision on an attestation case and thus allow the Web Portal to show if the attestor was originally delegated.

To determine the `UID_PWORulerOrigin` of the delegation

- Determine the `UID_PersonWantsOrg` of the delegation and copy this value as `UID_PWORulerOrigin` to the query. Use the `dbo.QER_FGIPWORulerOrigin` table function to do this.

```
select dbo.QER_FGIPWORulerOrigin(XObjectKey) as UID_PWORulerOrigin
```

To include all active managers and their deputies

- Check the `XOrigin` column for a value greater than 0.

Modified query from example 2:

```
select pia.UID_Person, dbo.QER_FGIPWORulerOrigin(pia.XObjectKey) as UID_PWORulerOrigin
from AttestationCase ac
  join ComplianceRule cr on cr.XObjectKey = ac.ObjectKeyBase and cr.IsWorkingCopy
```

```
= '0'  
  join PersonInBaseTree pia on pia.UID_Org = cr.UID_OrgResponsible and pia.XOrigin  
> 0  
  where ac.UID_AttestationCase = @UID_AttestationCase
```

Related topics

- [Setting up approval procedures](#) on page 109
- [Overview of approval procedures](#) on page 115

Specifying permitted approval procedures for tables

You can only assign selected approval policies to attestation procedures. Which approval policies are permitted depends on:

- The approval procedures that will be used in the approval policies
- The table that forms the attestation base object for an attestation procedure

You specify which tables are permitted for use with custom approval procedures.

If you want to use custom tables with the default approval procedures AS, CD, EX, OM, OR, or WC then assign these table to the approval procedures.


To specify the tables that permit this approval procedure

1. In the Manager, select the **Attestation > Basic configuration data > Approval procedures** category.
2. Select an approval procedure from the result list.
3. Select the **Assign tables** task.

In the **Add assignments** pane, assign the tables that can be used with the approval procedure.

TIP: In the **Remove assignments** pane, you can remove table assignments.

To remove an assignment

- Select the table and double-click .
4. Save the changes.

You can display which tables allow an approval procedure on the approval procedure overview form.

Related topics

- [Assigning approval policies to attestation procedures](#) on page 23
- [Overview of approval procedures](#) on page 115

Overview of approval procedures

An approval procedure overview form provides you with the following information:

- Overview of all queries that determine attestors
- List of tables that can use the approval procedure when they are attested
- Overview of all approval workflows and approval steps that use the approval procedure

To obtain an overview of an approval procedure

1. In the Manager, select the **Attestation > Basic configuration data > Approval procedures** category.
2. Select an approval procedure from the result list.
3. Select the **Approval procedure overview** task.

Related topics

- [Queries for finding attestors](#) on page 111
- [Specifying permitted approval procedures for tables](#) on page 114

Copying an approval procedure

You can copy default approval procedures in order to customize them.

To copy an approval procedure

1. In the Manager, select the **Attestation > Basic configuration data > Approval procedures** category.
2. Select an approval procedure in the result list. Select the **Change main data** task.
3. Select the **Create copy** task.
4. Confirm the security prompt with **Yes**.
5. Enter the short name for the copy.
The short name for an approval procedure consists of a maximum of two characters.
6. Click **OK** to start copying.

- OR -


Click **Cancel** to cancel copying.

Related topics

- [Setting up approval procedures](#) on page 109

Deleting approval procedures

To delete an approval procedure

1. Remove all assignments to approval steps.
 - a. On the approval procedure overview form, check which approval steps are assigned to the approval procedure.
 - b. Switch to the approval workflow and assign another approval procedure to the approval step.
2. In the Manager, select the **Attestation > Basic configuration data > Approval procedures > Predefined** category.
3. Select an approval procedure from the result list.
4. Click .
5. Confirm the security prompt with **Yes**.

Related topics

- [Overview of approval procedures](#) on page 115

Determining the responsible attestors

The DBQueue Processor calculates which identity is authorized as an approver and in which approval level. Once an attestation is triggered, the attestors are determined for every approval step of the workflow to be processed. Changes to responsibilities may lead to an identity no longer being authorized as an approver for an attestation that is not yet finally approved. In this case, the attestors must be recalculated. The following changes can trigger recalculation of pending attestations:

- Approval policy, workflow, step, or procedure changes.
- An authorized approver loses their responsibility in One Identity Manager, for example, if a change is made to the department manager, attestation policy approver, or target system manager.
- An identity obtains responsibilities in One Identity Manager and therefore is authorized as an approver, for example as the manager of the identity to be attested.
- An identity authorized as an approver is deactivated.

Once an identity's responsibilities have changed in One Identity Manager, a task for recalculating the attestors is queued in the DBQueue. All approval steps of the pending attestation cases are also recalculated by default. Approval steps that have already been approved remain approved, even if their attestor has changed. Recalculating attestors may take a long time depending on the configuration of the system environment and the amount of data to be processed. To optimize this processing time, you can specify the approval steps for which the attestors are to be recalculated.

NOTE: The attestation recalculation task is set for approval steps that implement default approval procedures. Approval steps with customized approval procedures are not recalculated automatically.

To configure recalculation of the attestors

- In the Designer, set the **QER | Attestation | ReducedApproverCalculation** configuration parameter and select one of the following options as the value.

Table 30: Options for recalculating attestors

Option	Description
No	<p>All approval steps are recalculated. This behavior also applies if the configuration parameter is not set.</p> <p>Advantage: All valid attestors are displayed in the approval process. The rest of the approval sequence is transparent.</p> <p>Disadvantage: Recalculating attestors may take a long time.</p>
CurrentLevel	<p>Only the attestors for the approval level that is currently to be edited are recalculated. Once an approval level has been approved, the attestors are determined for the next approval level.</p> <p>Advantage: The number of approval levels to calculate is lower. Calculating the attestors may be faster.</p> <p>TIP: Use this option if performance problems occur in your environment in connection with the recalculation of attestors.</p> <p>Disadvantage: The originally calculated attestors are still displayed in the approval sequence for each subsequent approval step, even though they may no longer have approval authorization. The rest of the approval sequence is not correctly represented.</p>
NoRecalc	<p>No recalculation of attestors. The previous attestors remain authorized to approve the current approval level. Once an approval level has been approved, the attestors are determined for the next approval level.</p> <p>Advantage: The number of approval levels to calculate is lower. Calculating the attestors may be faster.</p> <p>TIP: Use this option if performance problems occur in your environment in connection with the recalculation of attestors,</p>

Option	Description
	<p data-bbox="504 264 1118 293"> even though the CurrentLevel1 option is used.</p> <p data-bbox="504 315 1390 510">Disadvantage: The originally calculated attestors are still displayed in the approval sequence for each subsequent approval step, even though they may no longer have approval authorization. The rest of the approval sequence is not correctly represented. Identities that are no longer authorized can approve the current approval level.</p> <p data-bbox="504 533 1390 663">In the worst-case scenario, the only attestors originally calculated here now have no access to One Identity Manager, for example, because they have left the company. The approval level cannot be approved.</p> <p data-bbox="504 685 1139 714">To see approval steps of this type through</p> <ul data-bbox="555 736 1390 954" style="list-style-type: none"> <li data-bbox="555 736 1390 797">• Define a timeout and timeout behavior when you set up the approval workflows on the approval steps. <li data-bbox="555 819 660 848">- OR - <li data-bbox="555 871 1390 954">• When setting up the attestation, assign members to the chief approval team. These members can access pending attestation cases at any time.

Related topics

- [Properties of an approval step](#) on page 78
- [Chief approval team](#) on page 32
- [Modifying approval workflows for pending attestation cases](#) on page 149

Setting up multi-factor authentication for attestation

You can set up additional authentication for particularly security critical attestations, which requires every attestor to additionally authenticate themselves for attestation. In your attestation policies, define which attestation policies require this authentication.

One Identity Manager uses OneLogin for multi-factor authentication. Usable authentication modes are determined through the OneLogin user accounts linked to the identities.

Prerequisites

In OneLogin:

- At least one authentication method is configured on all user accounts that are going to use multi-factor authentication.

In One Identity Manager:

- The OneLogin Module is installed.
- Synchronization with a OneLogin domain is set up and has been run at least once.
- Identities linked to OneLogin user accounts.
- The API Server and the web application are configured as required.

For more information about setting up multi-factor authentication, see the *One Identity Manager Authorization and Authentication Guide*.

To use multi-factor authentication for attesting

1. In the Manager, select the attestation policies to which you want to apply multi-factor authentication.
2. Enable the **Approval by multi-factor authentication** option.

Multi-factor authentication cannot be used for default attestation policies.

Once the **Approval by multi-factor authentication** option is enabled on an attestation policy, additional authentication is requested in each approval step of the approval process. Attestors can select any one of the authentication methods assigned to their OneLogin user accounts.

IMPORTANT: An attestation cannot be sent by email if multi-factor authentication is configured for the attestation policy. Attestation emails for such attestations produce an error message.

For more information about multi-factor authentication, see the *One Identity Manager Web Portal User Guide*.

Related topics

- [General main data of attestation policies](#) on page 38
- [Attestation by mail](#) on page 163

Prevent attestation by identity awaiting attestation

The attestation object can also be determined as the attestor in an attestation case, which means the identities to be attested can attest themselves. To prevent this, set the **QER | Attestation | PersonToAttestNoDecide** configuration parameter.

NOTE:

- Changing the configuration parameter only affects new attestation cases. Attestors are not recalculated for existing attestation cases.
- The configuration parameter setting also applies for fallback approvers; it does not apply to the chief approval team.
- If the **Approval by affected identity** option is set on an approval step, this configuration parameter has no effect.

To prevent identities from attesting themselves

- In the Designer, set the **QER | Attestation | PersonToAttestNoDecide** configuration parameter.

This configuration parameter affects all attestation cases in which identities included in the attestation object or in object relations, are attestors at the same time. The following identities are removed from the group of attestors.

- Identities included in `AttestationCase.ObjectKeyBase`
- Identities included in `AttestationCase.UID_ObjectKey1`, `ObjectKey2`, or `ObjectKey3`
- Identities' main identities
- All subidentities of these main identities

If the configuration parameter is not set or if the approval step has **Approval by affected identity** enabled, these identities can attest themselves.

Related topics

- [Properties of an approval step](#) on page 78
- [Automatic acceptance of attestation approvals](#) on page 120

Automatic acceptance of attestation approvals

An attestor might be authorized to approve several levels of an approval workflow. By default, the attestation case is presented to them again at each approval level. To prevent this attestor from having to approve the attestation case several times, you can allow automatic approval. This passes on an approval decision that has been granted once already, to the next approval step irrespective of how any approval steps in between were approved.

NOTE: Automatic approvals apply to all fallback approvers but not to the chief approval team.

To attain automatic acceptance of an attestor's approval decisions in subsequent approval levels

- In the Designer, set the **QER | Attestation | ReuseDecision** configuration parameter.

If the attestor has granted approval to the attestation case in a previous approval step, the approval is carried over. If the attestor has not granted approval to the attestation case in a previous approval step, the approval is presented to the approver again.

Related topics

- [Attestors cannot be established](#) on page 139
- [Attesting by chief approval team](#) on page 143
- [Prevent attestation by identity awaiting attestation](#) on page 119

Phases of attestation

When performing attestations, it can be helpful to check in advance that the correct attestation objects are generated and the appropriate approvers are found. This determines whether the approval process can be deployed as defined and used for attestation or if it requires customizing. A staging phase like this can be added to the beginning of the approval procedure.

If entitlements are withdrawn because attestation was denied, affected identities can be given the opportunity to challenge the denial and thereby prevent the entitlements being withdrawn. A challenge phase like this can be placed at the end of the approval procedure. Depending on the outcome of the challenge, entitlements can subsequently be withdrawn automatically or manually.

Thus, approval procedures can be divided into four phases:

1. (Optional) Staging

Those responsible for attestations, specifically the owners of the respective attestation policy, are given the opportunity here to review the details of an attestation run. This allows the scope and sequence of attestation to be assessed before attestation is carried out. If errors are detected in the generated attestation cases, the affected attestation cases can be canceled, the errors corrected, and attestation restarted.

The staging phase can be integrated into the approval processes of any attestation objects.

2. Attestation

Attestation is run according to the defined approval workflow.

3. (Optional) Challenge

If an attestation is finally denied, the identities affected can be given the opportunity to challenge this decision. This allows attested identities to register their legitimate interests before entitlements are withdrawn. For example, this prevents entitlements that are needed at short notice from being withdrawn by a scheduled attestation and then having to reassign them again with additional effort.

It is possible to challenge if attesting user accounts, memberships in roles and organizations, or memberships in system entitlements.

4. (Optional) Automatically withdraw entitlements

If an attestation is denied in the end, the denied entitlements can be removed immediately. To do this, an automatic approval step with external approval is added to the end of the approval workflow.

For all four phases, appropriate approval levels are defined in the approval workflows.

Detailed information about this topic

- [Setting up the staging phase](#) on page 122
- [Setting up approval workflows](#) on page 76
- [Setting up the challenge phase](#) on page 124
- [Setting up withdrawal of entitlements](#) on page 125

Setting up the staging phase

A staging phase is when an approval level is inserted at the beginning of the approval workflow, which identifies the attestation policy owners as approvers. All attestation cases in an attestation run are thus submitted to a single identity (`AttestationPolicy.UID_PersonOwner`) or a group of identities (`AttestationPolicy.UID_AERoleOwner`) for review.

For example, a staging phase can be set up when the attestation policy or its components (attestation procedures, approval workflow, and so on) have been newly created and need to be tested to see if they deliver the expected results.

To set up a staging phase

1. In the Manager, create a new approval workflow or edit an existing approval workflow.
2. Add a new approval level at the beginning of the workflow and enter the approval step properties.
 - Approval procedure: **PW - owner of the attestation policy.**
3. Drag the **Approval** connector from the decision level for testing to the next decision level.
4. Save the changes.
5. Assign an approval policy to the approval workflow.

6. Assign an attestation policy to the approval policy.
7. Assign a single owner or an application role as owner to the attestation policy.
8. (Optional) Edit the main data of the attestation case assigned to attestation policy.
 - On the **Template** tab, in the **Text template** field, enter a text to describe the reviewers' and attestors' task.

Example:

```
For reviewer: Does the attestation case contain the correct
data for the attestation object and will the correct
attestors be identified?
For attestors: Is the attestation object data correct and
up-to-date?
```

9. Save the changes.

This workflow configuration starts the attestation phase once the attestation policy owners has approved staging. If the approval step is denied, attestation for the current attestation case is finally denied and the necessary corrections can be made.

Detailed information about this topic

- [Setting up approval workflows](#) on page 76
- [Editing approval levels](#) on page 77
- [General main data of approval policies](#) on page 70
- [General main data of attestation policies](#) on page 38
- [Templates for attestation procedures](#) on page 17

Related topics

- [Phases of attestation](#) on page 121
- [Criteria for the Staging phase](#) on page 123
- [Running attestation for single objects](#) on page 47

Criteria for the Staging phase

In the staging phase, at the beginning of each attestation run of the attestation policy, the generated attestation cases are checked for correctness. Staging criteria can be:

- Attestation scope
 - Will too many or too few attestation cases be created?
 - > Does the condition of the attestation policy need to be worded differently?
- Attestation sequence

Will the correct attestors be identified in the correct order?

-> Must the application workflow be changed?

- Details of the attestation objects that the attestors see
 - Is too much or too little detailed information displayed?
 - > Does the report on attestation procedure or the content of the snapshot need to be changed?
 - Is incorrect information shown?
 - > Must the attestation object's main data need to be corrected?

If errors are found only in individual attestation cases, you can deny these attestations and make the necessary corrections to the attestation objects. All other attestation cases can be approved and continue down the approval process.

If fundamental issues are found with the attestation policy, the attestation procedure, or the approval workflow used, you can flag all pending attestation procedures, deny them all together, and then make the necessary corrections.

Related topics

- [Phases of attestation](#) on page 121
- [Setting up the staging phase](#) on page 122

Setting up the challenge phase

If an attestation is finally denied, the identities affected can be given the opportunity to challenge this decision. The challenge may be particularly useful if entitlements are to be automatically withdrawn following denied attestations. Those affected can prevent this in the final instance.

To set up the challenge phase

1. In the Manager, edit an approval workflow and add a new approval level at the end of the workflow.
2. Enter the approval step properties.
 - Approval procedure: **CN - Challenge the decision**If the workflow includes an approval level for automatically withdrawing attested entitlements, the challenge approval level must be inserted directly before it.
3. Drag the **Deny** connector from the previous approval level to the challenge approval level.
4. (Optional) Drag the **Deny** connector from the challenge approval level to the approval level for automatically withdrawing entitlements.
5. Save the changes.
6. Assign an approval policy to the approval workflow.

7. Assign an attestation policy to the approval policy.
A challenge is possible if attesting user accounts, memberships in roles and organizations, or memberships in system entitlements.
8. (Optional) Edit the main data of the attestation case assigned to attestation policy.
 - On the **Template** tab, in the **Text template** field, enter a text to describe the attestors task.
9. Save the changes.

If those affected deny this approval step, the attestation is finally denied approval. If automatic withdrawal of entitlements is configured, the attested assignment is then automatically removed. If those affected approve this approval step, the attestation is finally granted approval.

Detailed information about this topic

- [Setting up approval workflows](#) on page 76
- [Editing approval levels](#) on page 77
- [General main data of approval policies](#) on page 70
- [General main data of attestation policies](#) on page 38
- [Templates for attestation procedures](#) on page 17

Related topics

- [Phases of attestation](#) on page 121
- [Setting up withdrawal of entitlements](#) on page 125

Setting up withdrawal of entitlements

If an attestation is denied in the end, the denied entitlements can be removed immediately. To do this, an automatic approval step with external approval is added to the end of the approval workflow.

To setup automatic withdrawal of entitlements

1. In the Manager, edit an approval workflow and add a new approval level at the end of the workflow.
2. Enter the approval step properties.
 - Approval procedure: **EX - Approvals to be made externally**
 - Event: **AUTOREMOVE**
3. Drag the **Deny** connector from the previous approval level to the approval level for automatically withdrawing entitlements.
4. Save the changes.

5. Assign an approval policy to the approval workflow.
6. Assign an attestation policy to the approval policy.
Automatic withdrawal of entitlements is possible if attesting memberships or assignments to application roles, business role, system roles, or system entitlements.
7. Save the changes.
8. In the Designer, set the **QER | Attestation | AutoRemovalScope** configuration parameter and the configuration subparameters.
9. If the entitlements were obtained through IT Shop, specify whether these requests should be unsubscribed or canceled. To do this, set the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter and select a value.

- **Abort:** Requests are canceled. In this case, they do not go through a cancellation workflow. The requested entitlements are withdrawn without additional checks.
- **Unsubscribe:** Requests are unsubscribed. They go through the cancellation workflow defined in the approval policies. Withdrawal of the entitlement can thus be subjected to an additional check.

If the cancellation is denied, the entitlement is not withdrawn even though the attestation has been denied.

If the configuration parameter is not set, the requests are canceled.

Detailed information about this topic

- [Setting up approval workflows](#) on page 76
- [Editing approval levels](#) on page 77
- [General main data of approval policies](#) on page 70
- [General main data of attestation policies](#) on page 38

Related topics

- [Phases of attestation](#) on page 121
- [Configuring withdrawal of entitlements](#) on page 182

Attestation by peer group analysis

Using peer group analysis, approval for attestation cases can be granted or denied automatically. For example, a peer group might be all identities in the same department. Peer group analysis assumes that these identities require the same system entitlements or secondary memberships. For example, if the majority of identities belonging to a

department have a specific system entitlement, assignment to another identity in the department can be approved automatically. This helps to accelerate approval processes.

Peer group analysis can be used during attestation of the following assignments or memberships:

- Assignments of system entitlements to user accounts (UNSAccountInUNSGroup table) if the user account is linked to an identity
- Secondary memberships in roles and organizations (PersonInBaseTree table and its derivatives)

Peer groups contain all identities with the same manager or belonging to the same primary or secondary department as the identity linked to the attestation object (= identity to be attested). Configuration parameters specify which identity belong to the peer group. At least one of the following configuration parameters must be set.

- **QER | Attestation | PeerGroupAnalysis | IncludeManager:** Identities with the same manager as the identity being attested
- **QER | Attestation | PeerGroupAnalysis | IncludePrimaryDepartment:** Identities that belong to the same primary department as the identity being attested
- **QER | Attestation | PeerGroupAnalysis | IncludeSecondaryDepartment:** Identities whose secondary department corresponds to the primary or secondary department of the identity being attested

The number of identities in a peer group that must already own the assignment or membership to be attested is set by a threshold in the **QER | Attestation | PeerGroupAnalysis | ApprovalThreshold** configuration parameter. The threshold specifies the ratio of the total number of identities in the peer group to the number of identities in the peer group who already own this assignment or membership.

You can also specify that identities are not permitted to own cross-functional assignments or memberships, which means, if the assignment or membership and the identity being attested belong to different functional areas, the attestation case should be denied approval. To include this check in peer group analysis, set the **QER | Attestation | PeerGroupAnalysis | CheckCrossfunctionalAssignment** configuration parameter.

Whether an assignment or a membership is cross-functional or not can only be verified if the following conditions are fulfilled:

- The identity being attested and the member of the peer group requested the assignment or membership in the IT Shop.
- The identity being attested is assigned to a primary department and this department is assigned to a functional area.
- The service item to which the assignment or membership is assigned, is assigned to a functional area.

Attestation cases are automatically approved for fully configured peer group analysis, if both:

- The membership being attested is not cross-functional
- The number of identities in the peer group who already own this membership equal or exceeds the given threshold

If this is not the case, attestation cases are automatically denied.

To use this functionality, One Identity Manager provides the `QER_PersonWantsOrg_PeerGroupAnalysis` process and the `PeerGroupAnalysis` event. The process is run using an approval step with the EX approval procedure.

Detailed information about this topic

- [Configuring peer group analysis for attestations](#) on page 128

Configuring peer group analysis for attestations

To configure peer groups

1. In the Designer, set the **QER | ITShop | PeerGroupAnalysis** configuration parameter.
2. Set at least one of the following subparameters:
 - **QER | Attestation | PeerGroupAnalysis | IncludeManager**: Identities with the same manager as the identity linked to the attestation object.
 - **QER | Attestation | PeerGroupAnalysis | IncludePrimaryDepartment**: Identities that belong to the same primary department as the identity linked to the attestation object.
 - **QER | Attestation | PeerGroupAnalysis | IncludeSecondaryDepartment**: Identities whose secondary department corresponds to the primary or secondary department of the identity linked to the attestation object.

This allows you to specify which identities belong to the peer group. You can also set two or all of the configuration parameters.

3. To specify a threshold for the peer group, set the **QER | Attestation | PeerGroupAnalysis | ApprovalThreshold** configuration parameter and specify a value between 0 and 1.

The default value is 0.9. That means, at least 90 percent of the peer group members must already have the membership to be attested in order for the attestation case to be approved.

4. (Optional) To check whether the membership to be attested is cross-functional, enable the **QER | Attestation | PeerGroupAnalysis | CheckCrossfunctionalAssignment** configuration parameter.

- Ensure that the following conditions are met:
 - The identity being attested and the member of the peer group requested the assignment or membership in the IT Shop.
 - The identity being attested is assigned to a primary department and this department is assigned to a functional area.
 - The service item to which the assignment or membership is assigned, is assigned to a functional area.

Only functional areas that are primary assigned service items are taken into account.

For more information about editing service items, see the *One Identity Manager IT Shop Administration Guide*. For more information about functional areas, see the *One Identity Manager Identity Management Base Module Administration Guide*.

5. In the Manager, create an approval workflow with at least one approval level. For the approval step, enter at least the following data:

- Single step: **EXWithPeerGroupAnalysis**.
- Approval procedure: **EX**
- Event: **PeerGroupAnalysis**

The event starts the ATT_AttestationCase_Peer_group_analysis process, which runs the ATT_PeerGroupAnalysis_for_Attestation script.

The script runs automatic approval and sets the approval step type to **Grant** or **Deny**.

Detailed information about this topic

- [Attestation by peer group analysis](#) on page 126

Related topics

- [Approvals to be made externally](#) on page 107

Approval recommendations for attestations

A way to accelerate the approval process by making automatic attestation approval decisions, is with approval recommendations. This process uses different criteria to determine whether attestation is more likely to be granted or denied approval. Based on the recommendation, attestations can be automatically granted approval. If denying approval is recommended or a clear recommendation cannot be made, the attestations must be submitted to additional attestors. These attestors are shown the approval recommendation and the recommendation details so that they can use this information to make an approval decision.

Detailed information about this topic

- [Criteria for approval recommendations for attestation](#) on page 130
- [Configuring approval recommendations for attestation](#) on page 133
- [Attestation by peer group analysis](#) on page 126

Criteria for approval recommendations for attestation

Various criteria are evaluated for approval recommendations. Which criteria can be applied depends on the object to be attested. For example, the last time a user account logged in to the target system can only be evaluated when attesting user accounts or assigning user accounts to system entitlements. This criterion is not applicable to other attestation objects. Non-applicable criteria do not affect the outcome of the recommendation.

The following criteria are evaluated when determining recommendations for approving attestation cases.

1. Peer group factor

The peer group factor assumes that all members of a peer group require the same system entitlements or secondary memberships. For example, if the majority of identities belonging to a department have a certain system entitlement, assignment to another identity in the department can be approved.

The number of identities in a peer group that must already own the assignment or membership to be attested is set by a threshold in the **QER | Attestation | Recommendation | PeerGroupThreshold** configuration parameter. The threshold specifies the ratio of the total number of identities in the peer group to the number of identities in the peer group who already own this assignment or membership.

Peer groups contain all identities with the same manager or belonging to the same primary or secondary department as the identity linked to the attestation object (= identity to be attested). Configuration parameters specify which identity belong to the peer group. At least one of the following configuration parameters must be set.

- **QER | Attestation | PeerGroupAnalysis | IncludeManager**: Identities with the same manager as the identity being attested
- **QER | Attestation | PeerGroupAnalysis | IncludePrimaryDepartment**: Identities that belong to the same primary department as the identity being attested
- **QER | Attestation | PeerGroupAnalysis | IncludeSecondaryDepartment**: Identities whose secondary department corresponds to the primary or secondary department of the identity being attested

This criterion is evaluated only for the following attestations:

- Assignments of system entitlements to user accounts (UNSAccountInUNSGroup table) if the user account is linked to an identity
- Secondary memberships in roles and organizations (PersonInBaseTree table and its derivatives)

2. Assigned functional area

This evaluates whether the assignment to attest and the primary department of the identity to attest are assigned to the same functional area. If this is not the case, the assignment or membership is considered cross-functional. Whether an assignment or a membership is cross-functional or not can only be verified if the following conditions are fulfilled:

- The identity being attested and the member of the peer group requested the assignment or membership in the IT Shop.
- The identity being attested is assigned to a primary department and this department is assigned to a functional area.
- The service item to which the assignment or membership is assigned, is assigned to a functional area.

This criterion is evaluated only for the following attestations:

- Assignments of system entitlements to user accounts (UNSAccountInUNSGroup table) if the user account is linked to an identity
- Secondary memberships in roles and organizations (PersonInBaseTree table and its derivatives)

3. Compliance rule violations

This evaluates whether the attestation object may violate existing compliance rules if the attestation were granted approval. Once a rule violation is detected, denying the attestation is recommended.

This criterion is evaluated for all attestation objects.

4. Risk factor

This calculates the risk factor of the attestation object. If this risk index exceeds the specified threshold, denying approval is recommended. The threshold is specified in the **QER | Attestation | Recommendation | RiskIndexThreshold** configuration parameter.

This criterion is evaluated for all attestation objects that have a risk index (RiskIndex or RiskIndexCalculated column).

5. Approval rate

This determines the proportion of approvals for this attestation object in previous attestations. For this, all approval procedures with manual approval that are also used in the currently running approval workflow are determined in the approval sequence (AttestationHistory). The proportion of approvals for the same attestation object is determined from the entries in the approval sequence.

If the approval rate exceeds the specified threshold, granting approval is recommended. The threshold is specified in the **QER | Attestation | Recommendation | ApprovalRateThreshold** configuration parameter.

This criterion is evaluated for all attestation objects that were already attested.

6. Assignment rate

This determines the number of company resource assignments to the attested identity (PersonHasObject) and compares it to the average number per identity. If the assignment rate is less than the average per identity, denying approval is recommended.

This criterion is evaluated only when identities are being attested (Person table).

7. Last log in time

This determines the last time the user account logged in (from UNSAccount.LastLogon). If the login was more than a defined number of days in the past, denying approval is recommended. The number of days is set in the **QER | Attestation | Recommendation | UnusedDaysThreshold** configuration parameter.

This criterion is evaluated only when attesting user accounts (such as the UNSAccount table) or system entitlement assignments to user accounts (UNSAccountInUNSGroup table) if the LastLogin column exists in the user account table.

Recommendation for granting approval

All applicable criteria are fulfilled. That means:

- The peer group has members and the peer group factor is higher than the threshold (**PeerGroupThreshold**).
- The attestation object and the primary department of the attested identity belong to the same functional area. Therefore the attestation object is not cross-functional.
- There are not rule violations.
- The risk index of the attestation object is lower than the threshold (**RiskIndexThreshold**).
- The approval rate is higher than the threshold (**ApprovalRateThreshold**).
- The assignment rate is higher than average.
- The last login was less than the specified number of days ago (**UnusedDaysThreshold**) and a time for the last login is entered.

Recommendation for denying approval

At least one of the following criteria applies.

- The peer group has no members or the peer group factor is lower than the threshold (**PeerGroupThreshold**).
- There is at least one rule violation.
- The assignment rate is less than average.

If at least two of the following applicable criteria hold, denying approval is also recommended.

- The product is cross-functional.
- The risk index of the attestation object is higher than the threshold (**RiskIndexThreshold**).
- The approval rate is lower than the threshold (**ApprovalRateThreshold**).
- The last login was longer than the specified number of days ago (**UnusedDaysThreshold**) or there is no time entered for the last login.

In all other cases, no recommendation is given.

Related topics

- [Approval recommendations for attestations](#) on page 129
- [Configuring approval recommendations for attestation](#) on page 133

Configuring approval recommendations for attestation

To use approval recommendations, add an additional approval level to the approval workflows and configure the thresholds. Based on the recommendation, attestations can be automatically granted approval. If denying approval is recommended or a clear recommendation cannot be made, the attestations must be submitted to additional attestors. If requests are not approved automatically, also define a manual approval level in case the recommendation is to grant approval.

The attestors are shown the approval recommendation. They can follow the recommendation or make their own approval decision independently.

TIP: One Identity Manager provides the **Attestation by the identity's manager (with approval recommendation)** sample workflow for approval recommendations with automatic approval. You can use this approval workflow as a template and adjust to suit your requirements. To do this, copy the workflow and add approval levels with manual approval steps.

To configure approval recommendations

1. In the Designer, set the **QER | ITShop | PeerGroupAnalysis** configuration parameter.
2. Set at least on of the following subparameters:
 - **QER | Attestation | PeerGroupAnalysis | IncludeManager:** Identities with the same manager as the identity linked to the attestation object.

- **QER | Attestation | PeerGroupAnalysis | IncludePrimaryDepartment:** Identities that belong to the same primary department as the identity linked to the attestation object.
- **QER | Attestation | PeerGroupAnalysis | IncludeSecondaryDepartment:** Identities whose secondary department corresponds to the primary or secondary department of the identity linked to the attestation object.

This allows you to specify which identities belong to the peer group. You can also set two or all of the configuration parameters.

3. Specify the threshold for the peer group factor in the **QER | Attestation | Recommendation | PeerGroupThreshold** configuration parameter. Enter a value between **0** and **1**.

The default value is **0.9**. That means, at least 90 percent of the peer group members must already have the attestation object so that the granting approval can be recommended.

4. Set the threshold for the risk factor in the **QER | Attestation | Recommendation | RiskIndexThreshold** configuration parameter. Enter a value between **0** and **1**.

The default value is **0.5**. That means, the attestation object's risk index must be less than 0.5 for granting approval to be recommended.

5. Set the approval rate threshold in the **QER | Attestation | Recommendation | ApprovalRateThreshold** configuration parameter. Enter a value between **0** and **1**.

The default value is **0.5**. That means, if more than 50% of all previous attestation cases of this attestation object were approved using the same approval procedure, granting approval is recommended.

6. Specify the number of days after which user accounts are considered unused in the **TargetSystem | UNS | UnusedUserAccountThresholdInDays** configuration parameter.

The default value is **90**. That means, if the time of the last login with a user account is less than 90 day ago, granting approval is recommended.

7. Create an approval workflow in the Manager and insert an approval step with the following data as the first approval level:

- Approval procedure: **EX**
- Event: **RecommendationAnalysis**

The event starts the `ATT_AttestationCase_Recommendation` process, which runs the `ATT_AttestationCase_Recommendation` script. The script runs automatic approval.

8. Add an approval level to manual approval.
9. In case denying approval might be recommended or no recommendation can be made, connect this approval level to the deny connection point at the first approval level.
10. (Optional) If the request is not to be approved automatically, connect the connection point for granting approval at the first approval level to an approval level for manual

approval as well. This means that attestation cases have to be approved manually even if granting approval is recommended.

11. Create an approval policy and assign it to the approval workflow.
 - Use this approval policy for attesting.

Related topics

- [Approval recommendations for attestations](#) on page 129
- [Criteria for approval recommendations for attestation](#) on page 130

Managing attestation cases

During attestation, you may find it necessary to assign someone else as default attestor responsible for the attestation because, for example, the actual attestor is absent. You may require additional information about an attestation object. One Identity Manager offers different possibilities to intervene in an pending attestation case.

Getting more information

An attestor has the option to gather more information about an attestation case. This ability does not, however, replace the granting or denying approval of an attestation case. There is no additional approval step required in the approval workflow to obtain the information.

Attestors can request information from any identity. The attestation case is put on hold while the query is pending. Once the identity requested has supplied the required information and the attestors have made an decision on the approval step, hold status is revoked. Attestors can recall a pending query at any time. The request is taken off hold. The query and answer are logged in the approval sequence and made available to the attestors.

NOTE: Hold status is revoked if the attestor who asked a question is removed as an approver. The queried identity does not have to answer and the attestation case proceeds.

Email notification to the identities involved can be sent using unanswered inquiries.

For more information about queries, see the *One Identity Manager Web Portal User Guide*.

Detailed information about this topic

- Email notification: [Notifications with questions](#) on page 161

Appointing other attestors

Once an approval level in the approval workflow has been reached, the attestors at this level can appoint another identity to handle the approval. To do this, you have the options described below:

- Rerouting approvals

The attestor appoints another approval level to carry out attestations. To do this, set up a connection to the approval level in the approval workflow to which an approval decision can be rerouted.

- Appointing additional attestors

The attestor appoints another identity to carry out the attestation. The other attestor must make an approval decision in addition to the known attestors. To do this, enable the **Additional approver possible** option in the approval step.

The additional attestor can reject the approval and return the attestation case to the original attestor. The original attestor is informed about this by email. The original attestor can appoint another additional attestor.

- Delegate approval

The attestor appoints another identity to carry out the attestation. This identity is added to the current approval step as the attestor and then makes the approval decision instead of the attestor who delegated. To do this, enable the **Approval can be delegated** option in the approval step.

The current attestor can reject the approval and return the attestation case to the original attestor. The original attestor can withdraw the delegation and delegate a different identity, for example, if the other attestor is not available.

Email notifications can be sent to the original attestors and the others.

Detailed information about this topic

- [Connecting approval levels](#) on page 83
- [Editing approval levels](#) on page 77
- [Properties of an approval step](#) on page 78

Related topics

- Email notification: [Delegating attestations](#) on page 160
- Email notification: [Rejecting approvals](#) on page 160
- Email notification: [Notifications from additional attestors](#) on page 161
- Email notification: [Scheduling attestation requests](#) on page 156

Escalating an attestation case

Approval steps can be escalated under the following conditions:


- Automatic escalation when a given time limit is exceeded.
- Manual escalation by the approver in the Web Portal

This presents the attestation case to another approval body. The attestation case is then further processed in the normal approval workflow.

To configure escalation of an approval step

1. Open the approval workflow in the Workflow Editor.
2. Add an additional approval level with one approval step for escalation.
3. Connect the approval step that is going to be escalated when the time period is exceeded with the new approval step. Use the connection point for escalation to do this.

Figure 3: Example of an approval workflow with escalation



4. Configure the behavior for the approval step to be escalated when it times out.

Table 31: Properties for escalation on timeout

Property	Meaning
Timeout (minutes)	Time interval after which the approval step automatically handles the approval decision. The input is converted into working hours and displayed additionally. <ul style="list-style-type: none">• From the drop-down, select the unit of time and enter an appropriate value.

Property	Meaning
----------	---------

The timeout is check every 30 minutes, by default. To change this interval, modify the **Checks reminder interval and timeout of attestation cases** schedule.

The working hours of the respective approver are taken into account when the time is calculated.

NOTE: Ensure that a state, county, or both is entered into the identity's main data of determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more information about calculating identities' working hours, see the *One Identity Manager Identity Management Base Module Administration Guide*.

TIP: Weekends and public holidays are taken into account when working hours are calculated. If you want weekends and public holidays to be dealt with in the same way as working days, set the **QBM | WorkingHours | IgnoreHoliday** or **QBM | WorkingHours | IgnoreWeekend** configuration parameter. For more information about this, see the *One Identity Manager Configuration Guide*.

If more than one approver was found, then an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.

If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.

If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is not recalculated.

If additional approvers are determined by recalculating the current approvers, then the automatic approval deadline is not extended. The additional approvers must approve within the time frame that applies to the current approver.

Timeout behavior

Action that is run if the timeout expires.

- **Escalation:** The attestation case is escalated. The escalation approval level is called.

5. (Optional) If the approval step still needs to be escalated but no attestor be found and no fallback approver is assigned, set the **Escalate if no approver found** option.

In this case, the attestation case is escalated instead of being canceled or passed to the chief approval team.

In the event of an escalation, email notifications can be sent to the new approvers and other identities.

Related topics

- Email notification: [Requesting attestation](#) on page 154
- Email notification: [Escalation of attestation cases](#) on page 160

Attestors cannot be established


You can specify a fallback approver if attestation cases cannot be approved because no attestors are available. An attestation case is then always assigned to the fallback approver for attestation if no attestor can be found in an approval step in the specified approval procedure.

To specify fallback approvers, define application roles and assign these to an approval step. Different attestation groups in the approval steps may also require different fallback approvers. Specify different application role for this, to which you can assign identities who can be determined as fallback approvers in the approval process. For more information, see the *One Identity Manager Authorization and Authentication Guide*.

To specify fallback approvers for an approval step

- Enter the following data for the approval step.

Table 32: Approval step properties for fallback approvers

Property	Meaning
Fallback approver	<p>Application role whose members are authorized to approve attestation cases if an attestor cannot be determined through the approval procedure. Assign an application from the drop-down.</p> <p>To create a new application role, click . Enter the application role name and assign a parent application role. For more information, see the <i>One Identity Manager Authorization and Authentication Guide</i>.</p> <p>NOTE: The number of approvers is not applied to the fallback approvers. The approval step is considered approved the moment as soon as one fallback approver has approved the request.</p>

Attestation sequence with fallback approvers

1. No attestor can be found for an approval step in an approval process. The attestation is assigned to all members of the fallback approver application role.
2. Once a fallback approver has approved an attestation case, it is presented to the attestors at the next approval level.

NOTE: You can specify in the approval step how many attestors are required for approval in this step. This limit is NOT valid for the chief approval team. The approval step is considered to be approved as soon as ONE fallback approver has approved the attestation.

3. The attestation case is canceled if no fallback approver can be found.

Fallback approvers can make approval decisions on attestation cases for all manual approval steps. Fallback approvals are not permitted for approval steps using the CD, EX, and WC approval procedures.

Related topics

- [Editing approval levels](#) on page 77
- [Selecting attestors](#) on page 85
- [Attesting by chief approval team](#) on page 143
- [Escalating an attestation case](#) on page 137

Automatic approval on timeout

Attestation cases can be automatically granted or denied approval once a specified time period has been exceeded.

To configure automatic approval if the timeout expires

- Enter the following data for the approval step.
 - **Timeout (minutes):**

Time interval after which the approval step automatically handles the approval decision. The input is converted into working hours and displayed additionally.

 - From the drop-down, select the unit of time and enter an appropriate value.

The timeout is checked every 30 minutes, by default. To change this interval, modify the **Checks reminder interval and timeout of attestation cases** schedule.

The working hours of the respective approver are taken into account when the time is calculated.

NOTE: Ensure that a state, county, or both is entered into the identity's main data of determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more information about calculating identities' working hours, see the *One Identity Manager Identity Management Base Module Administration Guide*.

TIP: Weekends and public holidays are taken into account when working hours are calculated. If you want weekends and public holidays to be dealt

with in the same way as working days, set the **QBM | WorkingHours | IgnoreHoliday** or **QBM | WorkingHours | IgnoreWeekend** configuration parameter. For more information about this, see the *One Identity Manager Configuration Guide*.

If more than one approver was found, then an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.

If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.

If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is not recalculated.

If additional approvers are determined by recalculating the current approvers, then the automatic approval deadline is not extended. The additional approvers must approve within the time frame that applies to the current approver.

- **Timeout behavior:**

Action, which is run if the timeout expires.

- **Approved:** The attestation case is approved in this approval step. The next approval level is called.
- **Deny:** The attestation case is denied in this approval step. The approval level for denying is called.

When the approval decision for an attestation case is made automatically, other people can be notified by email.

Related topics

- Email notification: [Granting or denying attestation cases](#) on page 157
- [Editing approval levels](#) on page 77

Halting an attestation case on timeout

Attestation cases can be automatically halted once a specified time period has been exceeded. The action halts when either a single approval step or the entire approval process has exceeded the timeout.

To configure halting after the timeout of a single approval step has been exceeded

- Enter the following data for the approval step.

- **Timeout (minutes):**

Time interval after which the approval step automatically handles the approval decision. The input is converted into working hours and displayed additionally.

- From the drop-down, select the unit of time and enter an appropriate value.

The timeout is checked every 30 minutes, by default. To change this interval, modify the **Checks reminder interval and timeout of attestation cases** schedule.

The working hours of the respective approver are taken into account when the time is calculated.

NOTE: Ensure that a state, county, or both is entered into the identity's main data of determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more information about calculating identities' working hours, see the *One Identity Manager Identity Management Base Module Administration Guide*.

TIP: Weekends and public holidays are taken into account when working hours are calculated. If you want weekends and public holidays to be dealt with in the same way as working days, set the **QBM | WorkingHours | IgnoreHoliday** or **QBM | WorkingHours | IgnoreWeekend** configuration parameter. For more information about this, see the *One Identity Manager Configuration Guide*.

If more than one approver was found, then an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.

If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.

If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is not recalculated.

If additional approvers are determined by recalculating the current approvers, then the automatic approval deadline is not extended. The additional approvers must approve within the time frame that applies to the current approver.

- **Timeout behavior:**

Action that runs if the timeout expires.

- **Cancel:** The approval step and, therefore, the entire attestation procedure, is canceled.

To configure halting on timeout for the entire approval process

- Enter the following data for the approval workflow.
 - **System halt (days):**
Number of days to elapse after which the approval workflow, and therefore the system, automatically halts the entire attestation procedure.

When an attestation case is halted, other people can be notified by email.

Related topics

- Email notification: [Canceling attestation cases](#) on page 159
- [Editing approval levels](#) on page 77
- [Setting up approval workflows](#) on page 76

Attesting by chief approval team

Sometimes, approval decisions cannot be made for attestation cases because an attestor is not available or does not have access to One Identity Manager tools. To complete these attestations, you can define a chief approval team whose members are authorized to intervene in the approval process at any time.

The chief approval team is authorized to approve, deny, or cancel attestations in special cases or to appoint other attestors.

IMPORTANT:

- The four-eye principle can be broken like this because chief approval team members can make approval decisions for attestation cases at any time. Specify, on a custom basis, in which special cases the chief approval team may intervene in the approval process.
- The chief approval team is authorized to attest its own members. The configuration parameter setting **QER | Attestation | PersonToAttestNoDecide** does not apply to the chief approval team.
- In the approval step, you can specify how many attestors must make a decision on this approval step.
 - If an approval decision is made by the chief approval team, it overrides the approval decision of just one regular attestor. This means, if three attestors must approve an approval step and the chief approval team one of the decision, two more are still required.
 - The number of approvers is not taken into account when the attestation is assigned to fallback approvers. The chief approval team can also attest in this case. The approval decision is considered to be made as soon as one member of the chief approval team has made an approval decision about the attestation.

- If a regular attestor has added an additional attestor, the chief approval team can approve for both the regular and the additional attestors. If both approvals are pending, a chief approver first replaces the regular attestor's approval only. Only a second approval of the chief approval team can replace the approval of the additional attestor.

The chief approval team can approve attestations for all manual approval steps. The following applies:

- Chief approval team decisions are not permitted for approval steps using the CD, EX, and WC approval procedures.
- If a member of the chief approval team is also named as a regular attestor for an approval step, they can only make an approval decision for this step as a regular attestor.
- The chief approval team can also make an approval decision if a regular attestor has submitted a query and the attestation is in hold status.


To add members to the chief approval team

1. In the Manager, select the **Attestation > Basic configuration data > Chief approval team** category.
2. Select the **Assign identities** task.

In the **Add assignments** pane, assign the identities who are authorized to approve all attestations.

TIP: In the **Remove assignments** pane, you can remove assigned identities.

To remove an assignment

- Select the identity and double-click .
3. Save the changes.

Related topics

- [Chief approval team](#) on page 32
- [Escalating an attestation case](#) on page 137

Attestation sequence

Once attestation is automatically or manually started, One Identity Manager creates an attestation run. This attestation run contains an attestation case for each attestation object. Attestation cases record the entire attestation sequence. Each attestation step in the attestation case can be audit-proof reconstructed. The attestation cases for a policy collection are combined in one attestation run.

You can display **attestation runs** in the navigation view under the menu item **Attestation runs**. This is where you can monitor the status of the attestation cases. Attestation cases that were not yet subject to approval are grouped under **Pending attestations**. You can display the attestation cases that have been closed by attestors or One Identity Manager grouped under **Closed attestations**. The status of pending attestation cases is checked regularly by the DBQueue Processor. The **Attestation check** starts the check.

NOTE: Attestation cases are edited in the Web Portal. For more information about this, see the *One Identity Manager Web Portal User Guide*.

Attestation closes when the attestation case has been granted or denied approval. You specify how to deal with granted or denied attestations on a company basis.

TIP: One Identity Manager provides various default attestation procedures for different data situations and default attestation procedures. If you use these default attestation procedures, you can configure how you deal with denied attestations.

For more information, see [Configuring withdrawal of entitlements](#) on page 182.

Starting attestation

There are two ways for you to add attestation cases in the One Identity Manager. You can trigger attestation through a scheduled task or start selected objects individually.

Prerequisite

- The attestation policy for this attestation is set.

To start attestation using a scheduled task

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list and run the **Change main data** task.
3. Enable the schedule entered in the **Calculation schedule** field.
 - a. In the navigation view, select the **Basic configuration data > Schedules** category.
 - b. Select the schedule in the result list and run the **Change main data** task.
 - c. Set the **Enabled** option.
 - d. Save the changes.

To start attestation for the selected objects

1. In the Manager, select the **Attestation > Attestation policies** category.
2. Select the attestation policy in the result list. Select the **Change main data** task.
3. Select the **Run attestation cases for single objects...** task.

This opens a separate window.

4. In the **Attestation** column, select every object for which attestation is to be run.
5. Click **Run**.

Attestation cases are generated for the selected attestation objects. As soon as DBQueue Processor has processed the task, you will see the newly created attestation cases in the navigation view under the **Attestation runs > <attestation policy> > Attestation runs > <year> > <month> > <day> > Pending attestations** menu item.

6. Click **Close**.

NOTE: Under certain circumstances, old, closed attestation cases are deleted from the One Identity Manager database when new attestation cases are added.

For more information about configuring schedules, see the *One Identity Manager Operational Guide*.

TIP: If it takes longer than 48 hours to generate new attestation cases, the process is canceled. You can adjust the timeout for generating attestation cases to suit your requirements. To do this, in Designer, change the value of the **QER | Attestation | PrepareAttestationTimeout** configuration parameter.

Detailed information about this topic

- [General main data of attestation policies](#) on page 38
- [Attestation schedules](#) on page 24

Related topics

- [Running attestation for single objects](#) on page 47
- [Determining the responsible attestors](#) on page 116

- [Deleting attestation cases](#) on page 151
- [Suspending attestation](#) on page 68

Attestation case overview

The overview form supplies you with the most important information about an attestation case. Here you can see the time by which an attestation case will be processed, depending on the processing time. One Identity Manager does not stipulate which actions are carried out if processing times out. Define your own custom actions or evaluations to deal with this situation.

To obtain an overview of an attestation case

1. In the Manager, select the category
 - **Attestation > Attestation runs > Attestation policies > <attestation policy> > Attestation runs > <year> > <month> > <day>** - OR -
 - **Attestation > Attestation run > Policy collections > <policy collection> > Attestation runs > <year> > <month> > <day>**.
2. Select the **Pending attestations** or the **Closed attestations** filter.
3. Select an attestation case from the result list.
4. Select **Attestation case overview**.

Related topics

- [Assigning extended properties to attestation cases](#) on page 177

Approval sequence

Once you have started attestation for an attestation policy, you can monitor the attestation case in One Identity Manager.

For pending attestation cases, see the current status of the approval process. The approval sequence is shown as soon as the DBQueue Processor has determined the attestors for the first approval step. In the approval workflow, you can view the approval sequence, the results of each approval step, and the attestors found. If the approval procedure could not find an attestor, the attestation case is canceled by the system.

To display the approval sequence of a pending attestation case

1. In the Manager, select the category
 - **Attestation > Attestation runs > Attestation policies > <attestation policy> > Attestation runs > <year> > <month> > <day> > Pending attestations** - OR -
 - **Attestation > Attestation run > Policy collections> <policy collection> > Attestation runs > <year> > <month> > <day> > Pending attestations.**
2. Select an attestation case from the result list.
3. Select the **Approval sequence** task.

Each approval level of an approval workflow is represented by a special control. The attestors responsible for a particular approval step are shown in a tooltip. Pending attestation questions are also shown in tooltips. These elements are shown in color, the color code reflecting the current status of the approval level.

Table 33: Meaning of the colors in an approval sequence (in order of decreasing importance)

Color	Meaning
Blue	This approval level is currently being processed.
Green	This approval level has been granted approval.
Red	This approval level has been denied approval.
Yellow	This approval level has been deferred due to a question.
Gray	This approval level has not (yet) been reached.

Attestation history

The attestation history displays each step of an attestation case. Here you can follow all the approvals in the approval process in a chronological sequence. The attestation history is displayed for pending and closed attestations.

To display an attestation case in the attestation history

1. In the Manager, select the category
 - **Attestation > Attestation runs > Attestation policies > <attestation policy> > Attestation runs > <year> > <month> > <day>** - OR -
 - **Attestation > Attestation run > Policy collections > <policy collection> > Attestation runs > <year> > <month> > <day>.**
2. Select the **Pending attestations** or the **Closed attestations** filter.

3. Select an attestation case from the result list.
4. Select the **Attestation history** report.

These elements are colored. The color code reflects the status of the approval steps.

Table 34: Meaning of colors in the attestation history

Color	Meaning
Yellow	Attestation case set up.
Green	Attestor has approved.
Red	Attestor has denied. Attestation has been escalated. Attestor has recalled the approval decision
Gray	Attestation has been canceled. Case has been assigned to an extra attestor. Additional attestor has withdrawn approval decision. Approval has been delegated. New attestor has withdrawn the delegation.
Orange	Attestor has a question. The query has been answered. Query was canceled due to change of approver.
Blue	Attestor has rerouted approval. The approval step was reset automatically.

Modifying approval workflows for pending attestation cases

When approval workflows are changed, a decision must be made as to whether these changes should be applied to pending attestation cases. Configuration parameters are used to define the desired procedure.

Scenario: Another approval workflow was stored with the approval policy

The newly stored workflow is only used in new requests. If changes have been made to the approval workflow in an approval policy, any pending approval processes are continued by default with the original workflow. The newly stored workflow is only used in new attestation cases. You can configure different behavior.

To specify how to handle pending attestation cases

- In the Designer, enable the **QER | Attestation | OnWorkflowAssign** configuration parameter and select one of the following values.
 - **CONTINUE**: Ongoing approval processes are continued with the originally applicable workflow. The newly stored workflow is only used in new attestation cases.

This behavior also applies if the configuration parameter is not set.
 - **RESET**: In ongoing approval processes, all approval decisions already taken are reset. The approval processes are restarted with the newly stored workflow. The attestation cases are run through the approval process again.
 - **ABORT**: Ongoing approval processes are stopped. All pending attestation cases are closed. The next automatic or manual start of the attestation uses the new approval workflow.

A working copy of the originally applicable workflow is saved. The working copy is retained as long as it is used in ongoing approval processes. All unused working copies are regularly deleted using the **Maintenance approval workflows** schedule.

Scenario: A change was made to an approval workflow in use

If changes have been made to an approval workflow that is being used in pending attestation cases, any pending approval processes are continued by default with the original workflow. The changes to the approval workflow are only implemented for new attestation cases. You can configure different behavior.

To specify how to handle pending attestation cases

- In the Designer, enable the **QER | Attestation | OnWorkflowUpdate** configuration parameter and select one of the following values.
 - **CONTINUE**: Ongoing approval processes are continued with the originally applicable approval workflow. The changes to the approval workflow are only implemented for new attestation cases.

This behavior also applies if the configuration parameter is not set.
 - **RESET**: In ongoing approval processes, all approval decisions already taken are reset. The approval processes are restarted with the changed approval workflow. The attestation cases are run through the approval process again.
 - **ABORT**: Ongoing approval processes are stopped. All pending attestation cases are closed. The next automatic or manual start of the attestation uses the changed approval workflow.

A working copy of the approval workflow that contains the original version is saved. This working copy is retained as long as it is used in ongoing approval processes. All unused working copies are regularly deleted using the **Maintenance approval workflows** schedule.

Related topics

- [Determining the responsible attestors](#) on page 116

Closing attestation cases for deactivated identities

Pending attestation cases must still be processed even if they have permanently deactivated in the meantime. This is not required very often because the affected identity may have, for example, left the company. In this case, you can use the option to close an identity's pending attestation cases automatically, if the identity is permanently disabled.

To close attestation cases automatically

- In the Designer, set the **QER | Attestation | AutoCloseInactivePerson** configuration parameter.

The configuration parameter only applies if the identity to be attested is deactivated after the attestation case was created.

The configuration parameter does not apply if the identity is temporarily deactivated.

TIP: Write a corresponding condition for finding the attestation object on the attestation policies to prevent attestation cases being created for deactivated identities. For more information, see [General main data of attestation policies](#) on page 38.

Deleting attestation cases

The AttestationCase table expands very quickly when attestation is performed regularly. To limit the number of attestation cases in the One Identity Manager database, you can delete obsolete, closed attestation cases from the database. The attestation case properties are logged and then the attestation cases are deleted. The same number of attestation cases remain in the database as are specified in the attestation policy. For more information about logging data changes tags, see the One Identity Manager Configuration Guide.

NOTE: Ensure that the logged request procedures are archived for audit reasons. For more information about the archiving method, see the One Identity Manager Data Archiving Administration Guide.

Prerequisites

- The **Common | ProcessState | PropertyLog** configuration parameter is enabled.
- The attestation policy is enabled.

To delete attestation cases automatically

1. Set the **Log changes when deleting** option on at least three columns in the **AttestationCase** table.
 - a. In the Designer, select the **Database schema > Tables > AttestationCase** category.
 - b. Select the **Show table definition** task.
This opens the Schema Editor.
 - c. Select a column in the Schema Editor.
 - d. In the edit view of the schema editor, select the **More** tab.
 - e. Set the option **Log changes when deleting**.
 - f. Repeat steps (c) to (e) for all columns that are to be recorded on deletion. There must be at least three.
 - g. Click on **Commit to database** and save the changes.
The changes take effect as soon as the DBQueue Processor has performed the calculation tasks.
2. Set the **Log changes when deleting** option on at least three columns in the **AttestationHistory** table.
 - a. In the Designer, select the **Database schema > Tables > AttestationHistory** category.
 - b. Repeat the steps 1(b) to 1(h) for the **AttestationHistory** table.
3. Enter the number of obsolete cases in the attestation policies.
 - a. In the Manager, select the **Attestation > Attestation policies** category.
 - b. Select the attestation policy in the result list whose attestation cases should be deleted.
 - c. Select the **Change main data** task.
 - d. In the **Obsolete tasks limit** field, enter a value greater than 0.
 - e. Save the changes.

TIP: If you want to prevent attestation cases being deleted for certain attestation policies, enter the value **0** for the obsolete task limit for these attestation policies.

Attestation cases are deleted as soon as a new attestation is started for an attestation policy.

One Identity Manager tests how many closed attestation cases exist in the database for each attestation object of this attestation policy. If the number is more than the number of obsolete attestation cases:

- The attestation case properties and their approval sequence are recorded.
All columns are recorded, which are marked for logging on deletion.
- The attestation cases are deleted.

The same number of attestation cases remain in the database as are specified in the obsolete tasks limit.

If the **Common | ProcessState | PropertyLog** configuration parameter is disabled later or not enough columns are marked with the **Record on delete** option, the value for **Number of obsolete processes** has no effect.

Notes for disabling attestation policies

- Disabling an attestation policy always deletes all attestation cases.
- The number of obsolete cases is not taken into account.
- The attestation case are also deleted if the **Common | ProcessState | PropertyLog** configuration parameter is disabled. In this case, the deleted attestation cases are not logged.

Related topics

- [General main data of attestation policies](#) on page 38
- [Suspending attestation](#) on page 68

Notifications in the attestation case

In an attestation case, various email notifications can be sent to attestors and other identities. The notification procedure uses mail templates to create notifications. The mail text in a mail template is defined in several languages. This ensures that the language of the recipient is taken into account when the email is generated. Mail templates are supplied in the default installation with which you can configure the notification procedure.

Messages are not sent to the chief approval team by default. Fallback approvers are only notified if not enough approvers could be found for an approval step.

To use email notifications

1. Ensure that the email notification system is configured in One Identity Manager. For more information, see the *One Identity Manager Installation Guide*.
2. In the Designer, set the **QER | Attestation | DefaultSenderAddress** configuration parameter and enter the sender address used to send the email notifications.
3. Ensure that all identities have a default email address. Notifications are sent to this address. For more information, see the *One Identity Manager Identity Management Base Module Administration Guide*.
4. Ensure that a language can be determined for all identities. Only then can they receive email notifications in their own language. For more information, see the *One Identity Manager Identity Management Base Module Administration Guide*.
5. Configure the notification procedure.

Related topics

- [Custom mail templates for notifications](#) on page 60

Requesting attestation

When a new attestation case is made, the attestor is notified by mail. Requests for attestation can be configured separately for each approval step.

Prerequisite

- The **QER | Attestation | MailTemplateIdents | RequestApproverByCollection** configuration parameter is not set.
- OR -
Always send notification of pending attestations is set on the attestation policy.

To set up the notification procedure

- On the **Mail templates** tab of the approval step, enter the following data:
Mail template request: Attestation - approval required
TIP: To allow approval by email, select the **Attestation - approval required (by email)** mail template.

NOTE: You can schedule requests for attestation to send a general notification if there are attestations pending. This replaces single requests for attestation at each approval step.

Related topics

- Email notification: [Scheduling attestation requests](#) on page 156
- [Attestation by mail](#) on page 163
- [Editing approval steps](#) on page 78
- [General main data of attestation policies](#) on page 38

Reminding attestors

If an attestor has not made a decision by the time the reminder timeout expires, notification can be sent by email as a reminder. The attestors working hours are taken into account when the time is calculated.

Prerequisite

- The **QER | Attestation | MailTemplateIdents | RequestApproverByCollection** configuration parameter is not set.

To set up the notification procedure

- Enter the following data for the approval step.

- **Reminder after (minutes):**

Time interval after which the attestor is notified by mail that there are still pending attestation cases for attestation. The input is converted into working hours and displayed additionally.

- From the drop-down, select the unit of time and enter an appropriate value.

The reminder interval is set to 30 minutes, by default. To change this interval, modify the **Checks reminder interval and timeout of attestation cases** schedule.

NOTE: Ensure that a state, county, or both is entered into the identity's main data of determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more information about calculating identities' working hours, see the *One Identity Manager Identity Management Base Module Administration Guide*.

TIP: Weekends and public holidays are taken into account when working hours are calculated. If you want weekends and public holidays to be dealt with in the same way as working days, set the **QBM | WorkingHours | IgnoreHoliday** or **QBM | WorkingHours | IgnoreWeekend** configuration parameter. For more information about this, see the *One Identity Manager Configuration Guide*.

If more than one attestor was found, each attestor will be notified. The same applies if an additional attestor has been assigned.

If an attestor delegated the approval, the time point for reminding the delegation recipient is recalculated. The delegation recipient and all the other attestors are notified. The original attestor is not notified.

If an attestor has made an inquiry, the time point for reminding the queried identity is recalculated. As long as the inquiry has not been answered, only this identity is notified.

- **Mail template reminder:** Select the **Attestation - remind approver** mail template.

TIP: To allow approval by email, select the **Attestation - remind approver (by email)** mail template.

NOTE: You can schedule requests for attestation to send a general notification if there are attestations pending. This replaces single requests for attestation at each approval step.

Related topics

- Email notification: [Notifications with questions](#) on page 161
- Email notification: [Scheduling attestation requests](#) on page 156
- [Attestation by mail](#) on page 163
- [Editing approval steps](#) on page 78

Scheduling attestation requests

Attestors can be regularly notified of attestation cases that are pending. These regular notifications replace the individual prompts and attestation reminders that are configured in the approval step.

To send regular notifications about pending attestations

1. Enable the **QER | Attestation | MailTemplateIdents | RequestApproverByCollection** configuration parameter in the Designer.

By default, a notification is sent with the **Attestation - pending requests for approver** mail template.

TIP: To use something other than the default mail template for these notifications, change the value of the configuration parameter in the Designer.

2. In the Designer, configure and enable the **Inform approver about pending attestations** schedule.

For more information about this, see the *One Identity Manager Operational Guide*.

Reminding attestors about attestation objects

The hierarchical role manager and those responsible for system entitlements or system roles can view all pending attestation cases for this object in the Web Portal. If necessary, they can also send reminders to attestors of selected attestation objects.

To send notification about a specific attestation object

- In the Designer, set the **QER | Attestation | MailTemplateIdents | RemindApproverByObject** configuration parameter.

By default, notification is sent using the **Attestation - remind approver of all open object attestations** template.

TIP: To use something other than the default mail template for these notifications, change the value of the configuration parameter in the Designer.

Use the Web Portal to send notifications. For more information about this, see the *One Identity Manager Web Portal User Guide*.

Granting or denying attestation cases

When an attestation case is granted approval or denied it, other identities receive notification. Notification may occur after approval or denial of a single approval step or once the entire approval procedure is complete. You can specify the recipient of the notification as required by the company.

Attestation cases can be automatically granted or denied approval once a specified time period has been exceeded. Notification is sent in the same way in this case.

To set up the notification procedure

1. Create custom mail templates for sending notification if attestation cases have been granted or denied approval.
2. Create company-specific processes for notifications.
3. If notification should be sent immediately after an approval decision is made for a single approval step, enter the following data on the **Mail templates** tab of the approval step.

Table 35: Properties of the approval step for notification

Property	Meaning
Mail template approved	Mail template to be used for email notification when an approval step is approved.
Mail template denied	Mail template to be used for email notification when an approval step is denied.

- OR -

If notification should be sent after the entire approval procedure is complete, enter the following data in the approval policy.

Table 36: Properties of an approval policy for notifications

Property	Meaning
Mail template approved	Mail template to be used for email notifications when an attestation case is approved.
Mail template denied	Mail template to be used for email notifications when an attestation case is denied.

Detailed information about this topic

- [Custom mail templates for notifications](#) on page 60
- [Custom notification processes](#) on page 67
- [Editing approval steps](#) on page 78
- [Approval policies for attestations](#) on page 69

Notifying delegates

If required, a delegator can receive notifications if the deputy or recipient of the single delegation has made an approval decision in an attestation case. A notification is sent once an identity has been determined as an attestor due to delegation and has made an approval decision for the attestation case.

To send a notification when the identity who was delegated an approval approves or denies the attestation.

- In the Designer, set the **QER | ITShop | Delegation | MailTemplateIdents | InformDelegatorAboutDecisionAttestation** configuration parameter.

By default, a notification is sent with the **Delegation - inform delegator about decided attestation** mail template.

TIP: To use custom mail templates for emails of this type, change the value of the configuration parameter.

Delegations are taken into account in the following default approval procedures.

Table 37: Delegation relevant default approval procedures

Delegation of	Approval procedure
Department responsibilities	DM, ED
Cost center responsibilities	PM
Location responsibilities	LM
Business role responsibilities	MO, OM, RM, RR
Identity responsibilities	CM, EM
Memberships in business roles	OR
Memberships in application roles	AA, AD, AL, AN, AO, AP, AR, AS, AT, AY, EN, EO, OA, SO

Example

Jan User3 is responsible for the R1 business role. They delegate their responsibility for the business role to Jo User1. Jo User1 is themselves responsible for R2 business role.

A member of R1 business role is to be attested. In the attestation procedure, Jan User3 is established as an attestor through the **OM - Manager of a specific role** approval procedure. The attestation case is assigned to Jo User1 for approval through delegation. Jan User3 is notified as soon as Jo User1 has made their approval decision about the attestation case.

A member of R2 business role is to be attested. In the attestation procedure, Jo User1 is established as an attestor through the **OM - Manager of a specific role** approval procedure. No notification is sent because Jo User1 does not make the approval decision due to delegation.

For more information about delegating responsibilities, see the *One Identity Manager IT Shop Administration Guide*.

Related topics

- [Default approval procedures](#) on page 86
- [Notifications from additional attestors](#) on page 161

Canceling attestation cases

Email notifications can be sent to other identities when an attestation case is canceled. You can specify the recipient of the notification as required by the company.

To set up the notification procedure

1. Create custom mail templates for sending notification if attestation cases have been canceled.
2. Create company-specific processes for notifications.
3. Enter the following data for the approval policy:

Mail template stopped: Mail template to be used for email notifications when an attestation case is canceled.

Detailed information about this topic

- [Custom mail templates for notifications](#) on page 60
- [Custom notification processes](#) on page 67

Escalation of attestation cases

Email notifications can be sent to the attestation policy's owner when an attestation case is escalated.

To set up the notification procedure

1. On the **Mail templates** tab of the approval step, enter the following data:
Mail template escalation: Attestation - Escalation
2. Assign an owner to the attestation policies.

Related topics

- [Escalating an attestation case](#) on page 137
- [General main data of attestation policies](#) on page 38
- [Editing approval steps](#) on page 78

Delegating attestations

If, in an approval step, other attestors can be authorized to make the approval decision, the additional attestors can be prompted to approve by email. The same applies if the attestation can be delegated.

To set up the notification procedure

- On the **Mail templates** tab of the approval step, enter the following data:
Mail template delegation: Attestation - Delegated/additional approval
TIP: To enable approval by email, select the **Attestation - delegated/additional approval (by email)** mail template.

Related topics

- [Attestation by mail](#) on page 163
- [Appointing other attestors](#) on page 136
- [Editing approval steps](#) on page 78

Rejecting approvals

The original attestor must be notified if an additional attestor or identity to whom an attestation has been delegated refuses the approval decision.

To set up the notification procedure

- On the **Mail templates** tab of the approval step, enter the following data:
Mail template rejection: Attestation - Reject approval
TIP: If you allow approval by email, select the mail template **Attestation - reject approval (by mail)**.

Related topics

- [Attestation by mail](#) on page 163
- [Appointing other attestors](#) on page 136
- [Editing approval steps](#) on page 78

Notifications with questions

Identities can be notified when a question about an attestation is asked. Similarly, the attestors can also be notified as soon as the question is answered.

To send a notification when an attestor asks a question

- In the Designer, enable the **QER | Attestation | MailTemplateIds | QueryFromApprover** configuration parameter.
A notification is sent by default with the **Attestation - question** mail template.

To send a notification to the attestor when the queried identity answers a question

- In the Designer, set the **QER | Attestation | MailTemplateIds | AnswerToApprover** configuration parameter.
A notification is sent by default with the **Attestation - answer** mail template.

TIP: To use custom mail templates for emails of this type, change the value of the configuration parameter.

Notifications from additional attestors

The original attestor can be notified when an additional attestor or an identity who has been delegated an attestation has granted or denied the attestation. This mail is sent the moment the approval step has been decided.

To send a notification when the additional attestor approves or rejects the attestation

- In the Designer, set the **QER | Attestation | MailTemplateIdents | InformAddingPerson** configuration parameter.

A notification is sent by default with the **attestation - approval of added step** mail template.

To send a notification when the identity who was delegated an approval approves or denies the attestation.

- In the Designer, set the **QER | Attestation | MailTemplateIdents | InformDelegatingPerson** configuration parameter.

A notification is sent by default with the **attestation - approval of delegated step** mail template.

TIP: To use custom mail templates for emails of this type, change the value of the configuration parameter.

Link for verifying new external users

If a new user logs in to the Web Portal or new external identities need to be certified, they receive an email containing a link to the Password Reset Portal. Using the link, identities verify their contact email address, set a password and password questions.

To send notification with a verification link

- In the Designer, set the **QER | Attestation | MailTemplateIdents | NewExternalUserVerification** configuration parameter.

By default, notification is sent using the **Attestation - new external user verification link** mail template.

TIP: To use something other than the default mail template for these notifications, change the value of the configuration parameter in the Designer.

Detailed information about this topic

- [User attestation and recertification](#) on page 190
- [Self-registration of new users in the Web Portal](#) on page 193
- [Adding new identities using a manager or administrator for identities](#) on page 195

Default mail templates

One Identity Manager supplies mail templates by default. These mail templates are available in English and German. If you require the mail body in other languages, you can

add mail definitions for these languages to the default mail template.

To edit a default mail template

- In the Manager, select the **Attestation > Basic configuration data > Mail templates > Predefined** category.

Related topics

- [Custom mail templates for notifications](#) on page 60

Attestation by mail

To provide attestors who are temporarily unable to access One Identity Manager tools with the option of making attestation case decisions, you can set up attestation by email. In this process, attestors are notified by email when an attestation case is pending their approval. Approvers can use the links in the email to make approval decisions without having to connect to the Web Portal. This generates an email that contains the approval decision and in which attestors can state the reasons for their approval decision. This email is sent to a central mailbox. One Identity Manager checks this mailbox regularly, evaluates the incoming emails and updates the status of the attestation cases correspondingly.

IMPORTANT: An attestation cannot be sent by email if multi-factor authentication is configured for the attestation policy. Attestation emails for such attestations produce an error message.

Prerequisites

- If you use a Microsoft Exchange mailbox, configure the Microsoft Exchange with:
 - Microsoft Exchange Client Access Server version 2007, Service Pack 1 or higher
 - Microsoft Exchange Web Service .NET API Version 1.2.1, 32-bit
- If you use an Exchange Online mailbox, register an application in your Microsoft Entra ID tenant in the Microsoft Azure Management Portal. For example, One Identity Manager <Approval by mail>.

For more information about how to register an application, see <https://docs.microsoft.com/en-us/exchange/client-developer/exchange-web-services/how-to-authenticate-an-ews-application-by-using-oauth#register-your-application>.

- The One Identity Manager Service user account used to log into Microsoft Exchange or Exchange Online requires full access to the mailbox given in the **QER | Attestation | MailApproval | Inbox** configuration parameter.
- The **QER | Attestation | MailTemplateIds | RequestApproverByCollection** configuration parameter is not set.

- OR -

Always send notification of pending attestations is set on the attestation policy.

To set up attestation by email

1. In the Designer, set the **QER | Attestation | MailApproval | Inbox** configuration parameter and enter the mailbox to which the approval mails are to be sent.
2. Set up mailbox access.
 - If you use a Microsoft Exchange mailbox:
 - By default, One Identity Manager uses the One Identity Manager Service user account to log in to the Microsoft Exchange Server and access the mailbox.
 - OR -
 - You enter a separate user account for logging in to the Microsoft Exchange Server for mailbox access.
 - In the Designer, set the **QER | Attestation | MailApproval | Account** configuration parameter and enter the user account's name.
 - In the Designer, set the **QER | Attestation | MailApproval | Domain** configuration parameter and enter the user account's domain.
 - In the Designer, set the **QER | Attestation | MailApproval | Password** configuration parameter and enter the user account's password.
 - If you use an Exchange Online mailbox:
 - In the Designer, set the **QER | Attestation | MailApproval | AppId** configuration parameter and enter the application ID that was generated when the application was registered in the Microsoft Entra ID tenant.
 - In the Designer, set the **QER | Attestation | MailApproval | Domain** configuration parameter and enter the domain for logging into Microsoft Entra ID.
 - In the Designer, set the **QER | Attestation | MailApproval | Password** configuration parameter and enter the client secret (application password) for the application.
3. In the Designer, set the **QER | Attestation | MailTemplateIdents | ITShopApproval** configuration parameter.

The mail template used to create the attestation mail is stored with this configuration parameter. You can use the default mail template or add a custom mail template.

TIP: To use a company-specific mail template for attestation mails, change the value of the configuration parameter. To use a company-specific mail template for approval decision mails, change the value of the configuration parameter. In this case, also change the VI_MailApproval_ProcessMail script.

4. Assign the following mail templates to the approval steps.

Table 38: Mail templates for approval by mail

Property	Mail template
Mail template request	Attestation - approval required (by mail)
Mail template reminder	Attestation - remind approver (by mail)
Mail template delegation	Attestation - delegated/additional approval (by mail)
Mail template rejection	Attestation - reject approval (by mail)

5. In the Designer, configure and enable the **Processes attestation mail approvals** schedule.

Based on this schedule, One Identity Manager regularly checks the mailbox for new attestation mails. The mailbox is checked every 15 minutes. You can change how frequently it checks, by altering the interval in the schedule as required.

To clean up a mail box

- In the Designer, set the **QER | Attestation | MailApproval | DeleteMode** configuration parameter and select one of the following values.
 - **HardDelete**: The processed email is immediately deleted.
 - **MoveToDeleteItems**: The processed email is moved to the **Deleted objects** mailbox folder.
 - **SoftDelete**: The processed email is moved to the Active Directory recycling bin and can be restored if necessary.

NOTE: If you use the **MoveToDeleteItems** or **SoftDelete** cleanup method, you should empty the **Deleted objects** folder and the Active Directory recycling bin on a regular basis.

Related topics

- [Processing attestation mails](#) on page 166
- [Custom mail templates for notifications](#) on page 60
- [Requesting attestation](#) on page 154
- [Reminding attestors](#) on page 154
- [Delegating attestations](#) on page 160
- [Rejecting approvals](#) on page 160
- [Setting up multi-factor authentication for attestation](#) on page 118
- [Adaptive cards attestation](#) on page 166
- [General main data of attestation policies](#) on page 38

Processing attestation mails

The **Processes attestation mail approvals** schedule starts the `VI_Attestation_ProcessApproval_Inbox` process. This process runs the `VI_MailApproval_ProcessInBox` script, which searches the mailbox for new attestation mails and updates the attestation cases in the One Identity Manager database. The contents of the attestation mail are processed at the same time.

NOTE: The validity of the email certificate is checked with the `VID_ValidateCertificate` script. You can customize this script to suit your security requirements. Take into account that this script is also used for approval decisions for IT Shop requests by email.

If an self-signed root certification authority is used, the user account under which the One Identity Manager Service is running, must trust the root certificate.

TIP: The `VI_MailApproval_ProcessInBox` script finds the Exchange Web Service URL that uses `AutoDiscover` through the given mailbox as default. This assumes that the `AutoDiscover` service is running.

If this is not possible, enter the URL in the **QER | Attestation | MailApproval | ExchangeURI** configuration parameter.

Attestation mails are processed with the `VI_MailApproval_ProcessMail` script. The script finds the relevant approval decision, sets the **Approved** option if approval is granted, and stores the reason for the approval decision with the attestation cases. The attestor is found through the sender address. Then the attestation mail is removed from the mailbox depending on the selected cleanup method.

NOTE: If you use a custom mail template for the attestation mail, check the script and modify it as required. Take into account that this script is also used for approval decisions for IT Shop requests by email.

Adaptive cards attestation

To allow attestors who temporarily do not have access to the One Identity Manager tools to approve attestation cases, you can send adaptive cards. Adaptive cards contain all the information required for attesting the attestation case. These include:

- Current and next attestor
- Attestation history
- Link to the attestation case in the Web Portal
- Option to select a default reason or enter your own reason
- Message stating that the attested entitlement is automatically withdrawn if attestation is denied.
- Message stating whether the attestation object was already attested with the same attestation policy.

One Identity Starling Cloud Assistant uses a specified channel to post the adaptive cards to the attester, waits for a response, and send this to the One Identity Manager. Currently Slack and Microsoft Teams can be used to post adaptive cards. In Starling Cloud Assistant, channels are configured and can be allocated to each recipient separately.

Prerequisites

- The Starling Cloud Assistant service is enabled and the usable channels are configured.

For more information, see the *One Identity Starling Cloud Assistant User Guide* under <https://support.oneidentity.com/starling-cloud-assistant/hosted/technical-documents>.

Access to the following endpoints must be ensured to reach a Starling organization in the respective data center.

- United States of America:
 - <https://sts.cloud.oneidentity.com> (to receive an authentication token)
 - <https://cloud-assistant-supervisor.cloud.oneidentity.com> (to address the Starling Cloud Assistant API)
- European Union:
 - <https://sts.cloud.oneidentity.eu> (to receive an authentication token)
 - <https://cloud-assistant-supervisor.cloud.oneidentity.eu> (to address the Starling Cloud Assistant API)
- One Identity Manager is connected to One Identity Starling.

To connect One Identity Manager to One Identity Starling

1. Start the Launchpad.
2. Select **Connection to Starling Cloud** and click **Run**.
This starts the Starling Cloud configuration wizard.
3. Follow the Starling Cloud configuration wizard's instruction.

This sets the **QER | Person | Starling | ApiEndpoint** and **QER | Person | Starling | ApiKey** configuration parameters and enters the authentication credentials.

For more information about One Identity Starling, see the *One Identity Starling User Guide* under <https://support.oneidentity.com/starling-cloud-assistant/hosted/technical-documents>.

Related topics

- [Using adaptive cards for attestations](#) on page 168
- [Configuring withdrawal of entitlements](#) on page 182

Using adaptive cards for attestations

Attestators must be registered as recipients in Starling Cloud Assistant to be able to make approval decisions about attestation cases. Each recipient must be allocated to a channel that will be used to post the adaptive card. One Identity Manager provides adaptive cards for requesting attestation in German and English. These can be customized if necessary.

By default, an approval decision must be made within 1 day. If this deadline is exceeded, the Web Portal must be used to approve the attestation case. You can configure the deadline.

To use adaptive cards for attestations

1. In the Designer, set the **QER | Person | Starling | UseApprovalAnywhere** configuration parameter.
2. Ensure that a default email address is stored in One Identity Manager for each identity that will use adaptive cards. This address must correspond to the email address that the identity uses to log in to Microsoft Teams or Slack.

For detailed information about the default email address, see the *One Identity Manager Identity Management Base Module Administration Guide*.
3. Ensure that a language can be identified for each identity that will use adaptive cards. This allows attestors to obtain adaptive cards in their own language.

For more information, see the *One Identity Manager Identity Management Base Module Administration Guide*.
4. In the Designer, disable the **QER | Attestation | MailTemplateIdents | RequestApproverByCollection** configuration parameter.

- OR -

Enable the **Always send notification of pending attestations** attestation policy. This allows adaptive cards to also be sent for certain attestation policies if the scheduled request for attestation by email notification is configured.
5. On the **Mail template** tab, assign a **Mail template request** the approval steps.
6. Register all the identities, who are going to use adaptive cards for attesting, as recipients in Starling Cloud Assistant and assign them to the channel to use.
7. Install the Starling Cloud Assistant app that matches the channel.

Every registered identity must install this app.

For more information, see the *One Identity Starling Cloud Assistant User Guide* under <https://support.oneidentity.com/starling-cloud-assistant/hosted/technical-documents>.
8. (Optional) Change the timeout for adaptive cards.
 - In the Designer, set the **QER | Person | Starling | UseApprovalAnywhere | SecondsToExpire** configuration parameter and adjust the value. Enter a timeout in seconds.

9. (Optional) Provide a country-specific template for adaptive cards or make adjust the adaptive cards settings.

If a language cannot be identified or there is no suitable template for the language found, en-US is used as fallback.

Detailed information about this topic

- [Editing approval steps](#) on page 78
- [General main data of attestation policies](#) on page 38
- [Adding and deleting recipients and channels](#) on page 169
- [Creating, editing, and deleting adaptive cards for attestations](#) on page 170
- [Creating, editing, and deleting adaptive cards templates for attestations](#) on page 171
- [Deploying and evaluating adaptive cards for attestations](#) on page 173
- [Disabling adaptive cards](#) on page 174

Adding and deleting recipients and channels

Attestors can be registered in Starling Cloud Assistant as recipients through an IT Shop request and allocated to a channel. By default, the requests are approved immediately by self-service. Then the recipients are registered and the requested channel is assigned to them. Once the attestor has installed the Starling Cloud Assistant app, they can use adaptive cards to attest.

To add a recipient in Starling Cloud Assistant

- In the Web Portal, request the **New Starling Cloud Assistant recipient** product.

To allocate Microsoft Teams as a channel in Starling Cloud Assistant

1. In the Web Portal, request the **Teams channel for Starling Cloud Assistant recipient** product.
2. Install the Starling Cloud Assistant app for Microsoft Teams.

For more information, see the *One Identity Starling Cloud Assistant User Guide* under <https://support.oneidentity.com/starling-cloud-assistant/hosted/technical-documents>.

To allocate Slack as a channel in Starling Cloud Assistant

1. In the Web Portal, request the **Slack channel for Starling Cloud Assistant recipient** product.
2. Install the Starling Cloud Assistant app for Slack.

For more information, see the *One Identity Starling Cloud Assistant User Guide* under <https://support.oneidentity.com/starling-cloud-assistant/hosted/technical-documents>.

To delete a recipient in Starling Cloud Assistant

- Cancel the **New Starling Cloud Assistant recipient** product.

To remove a channel

- Cancel the respective product.

For more information about requesting and unsubscribing products, see the *One Identity Manager Web Portal User Guide*.

Related topics


- [Adaptive cards attestation](#) on page 166
- [Using adaptive cards for attestations](#) on page 168

Creating, editing, and deleting adaptive cards for attestations


One Identity Manager provides adaptive cards for requesting attestation in German and English. These can be displayed in the Manager. You can create your own templates for adaptive cards, for example to make changes to the content or to provide adaptive cards in other languages. The recipient's language preferences are taken into account when an adaptive card is generated. If a language cannot be identified or there is no suitable template for the language found, en-US is used as fallback.

To use your own adaptive cards for attestations, configure the ATT_AttestationHelper approve anywhere process accordingly.

To display an adaptive card

1. In the Manager, select the **Attestation > Basic configuration data > Adaptive cards** category.
2. Select the adaptive card in the result list.
3. Select the **Change main data** task.
4. In the **Adaptive card templates** drop-down, select a template.
This displays the adaptive card's definition in the **Template** field.
 - To display the entire JSON code, click .

To create an adaptive card.


1. In the Manager, select the **Attestation > Basic configuration data > Adaptive cards** category.
2. Click  in the result list.
3. Edit the adaptive card's main data.

4. Create a new template for adaptive cards.
5. Save the changes.
6. Create additional language-specific templates for this adaptive card as required and save the changes.

To use your customized adaptive card

1. In the Designer, edit the ATT_AttestationHelper approve anywhere process.
 - a. Select the **Send Adaptive Card to Starling Cloud Assistant** process step.
 - b. Edit the value of the **ParameterValue2** parameter and replace the name and UID with the values of your customized adaptive card.
2. Save the changes.

To delete an adaptive card.

1. In the Manager, select the **Attestation > Basic configuration data > Adaptive cards** category.
2. Select the adaptive card in the result list.
3. Click  in the result list.

This deletes the adaptive card and all the templates belonging to it.

Related topics



- [Creating, editing, and deleting adaptive cards templates for attestations](#) on page 171
- [Using adaptive cards for attestations](#) on page 168
- [Adding and deleting recipients and channels](#) on page 169
- [Deploying and evaluating adaptive cards for attestations](#) on page 173
- [Disabling adaptive cards](#) on page 174
- [General main data for adaptive cards](#) on page 173

Creating, editing, and deleting adaptive cards templates for attestations


To use your own adaptive cards or to provide adaptive cards in other languages, create your own adaptive card's templates.

To create an adaptive card template


1. In the Manager, select the **Attestation > Basic configuration data > Adaptive cards** category.
2. Select the adaptive card in the result list.

3. Edit the adaptive card's main data.
4. Next to the **Adaptive card templates** drop-down, click .
5. In the **Language** drop-down, select a language for the adaptive card.
All active languages are shown. To use another language, in the Designer, enable the corresponding countries. For more information, see the *One Identity Manager Configuration Guide*.
6. In the **Template** field, write a definition for the adaptive card.
 - To display the entire JSON code, click .You can use the Adaptive Card Designer from Microsoft or the Visual Studio Code plugin to help.
7. Save the changes.
8. In the Designer, check the ATT_CloudAssistant_ApprovalAnywhere script and modify it to suit your requirements.

To edit an adaptive card template

1. In the Manager, select the **Attestation > Basic configuration data > Adaptive cards** category.
2. In the result list, select the adaptive card whose template you want to edit.
3. Select the **Change main data** task.
4. In the **Adaptive card templates** drop-down, select a template.
5. In the **Template** field, edit the adaptive card definition.
 - To edit the entire JSON code, click .
6. Save the changes.

To delete an adaptive card template

1. In the Manager, select the **Attestation > Basic configuration data > Adaptive cards** category.
2. In the result list, select the adaptive card whose template you want to delete.
3. Edit the adaptive card's main data.
4. In the **Adaptive card templates** drop-down, select the template.
5. Click  next to the drop-down.
6. Save the changes.

Related topics

- [Creating, editing, and deleting adaptive cards for attestations](#) on page 170
- [Deploying and evaluating adaptive cards for attestations](#) on page 173
- [General main data for adaptive cards](#) on page 173

General main data for adaptive cards

Enter the following main data for an adaptive card.

Table 39: Adaptive card main data

Property	Description
Adaptive card	Name of the adaptive card.
Description	Text field for additional explanation.
Disabled	Specifies whether the adaptive card is actively used.
Adaptive card templates	Name of templates to use with this adaptive card.
Language	The template is provided in this language. The recipient's language preferences are taken into account when an adaptive card is generated and a matching template is applied. If a language cannot be identified or there is no suitable template for the language found, en-US is used as fallback.
Template	JSON template of the adaptive card that contains placeholders for Adaptive Cards Templating.

Related topics

- [Creating, editing, and deleting adaptive cards for attestations](#) on page 170
- [Creating, editing, and deleting adaptive cards templates for attestations](#) on page 171
- [Disabling adaptive cards](#) on page 174

Deploying and evaluating adaptive cards for attestations

If an attestor is found in an approval step and this approval step has a mail template allocated to it, the `ATT_AttestationHelper approve anywhere` process is run. The process is generated if the following conditions are fulfilled:

- The attestor is registered as the recipient in Starling Cloud Assistant.
- A default email address is stored for the attestor.
- The **QER | Person | Starling | UseApprovalAnywhere** configuration parameter is set.

- An expiry date is entered in the **QER | Person | Starling | UseApprovalAnywhere | SecondsToExpire** configuration parameter.
- The **QER | Attestation | MailTemplateIdents | RequestApproverByCollection** configuration parameter is not set.

- OR -

Always send notification of pending attestations is set on the attestation policy.

The process calls the ATT_CloudAssistant_CreateMessage_AttestationHelper script passing to it the name and UID of the adaptive card to send. The script creates the adaptive card from the JSON template for adaptive cards and the data in the attestation case and then sends it to the attester. The QER_CloudAssistant_CheckMessage_AttestationHelper script checks if the attester has sent a response, evaluates the response and updates the attestation case according to the approval decision.

NOTE: If you want to use your own adaptive cards template, check the ATT_CloudAssistant_CreateMessage_AttestationHelper, ATT_CloudAssistant_CreateData_AttestationHelper, and ATT_CloudAssistant_CheckMessage_AttestationHelper scripts and adjust them if necessary to reflect content changes in the template. For more information about overriding scripts, see the *One Identity Manager Configuration Guide*.

Related topics

- [Creating, editing, and deleting adaptive cards templates for attestations](#) on page 171
- [Creating, editing, and deleting adaptive cards for attestations](#) on page 170
- [Using adaptive cards for attestations](#) on page 168
- [General main data of attestation policies](#) on page 38

Disabling adaptive cards

Adaptive cards that are not used can be disabled.

To disable an adaptive card

1. In the Manager, select the **Attestation > Basic configuration data > Adaptive cards** category.
2. Select the adaptive card in the result list.
3. Select the **Change main data** task.
4. Set **Disabled**.
5. Save the changes.

Related topics

- [Using adaptive cards for attestations](#) on page 168
- [Creating, editing, and deleting adaptive cards for attestations](#) on page 170

Approving attestation cases in the Manager

In the Manager, the **Attestation cases** report is available for attestors. Attestors can use this report to make approval decisions about attestation cases.

To approve an attestation case in the Manager

1. In the Manager, select the **Identities > Identities** category.
2. Select the identity in the result list.
3. Select the **Attestation cases** report.
4. Select the **Pending attestation cases** tab.
5. If a report has been defined for the attestation case, you can view it using the button in the **View report** column.
6. Select the attestation case and enable the **Approve** or the **Deny** option in the list.
7. Enter the **Reason for decision** or select a **Standard reason**.
8. Click **Carry out approval**.

Related topics

- [Displaying attestation cases of an attestor](#) on page 175

Displaying attestation cases of an attestor

An **Attestation cases** report is available for attestors. The report shows all the attestor's pending and closed attestation cases. Attestors can use this report to make approval decisions in the Manager about attestation cases.

To display the Attestation cases report for an identity

1. In the Manager, select the **Identities > Identities** category.
2. Select the identity in the result list.

3. Select the **Attestation cases** report.
4. If a report with details about an attestation object has been defined for the attestation case, you can view it using the button in the **View report** column.

Related topics

- [Approving attestation cases in the Manager](#) on page 175

Displaying information about attestation objects

The data about an attestation object of an attestation case is provided as a report or as a snapshot.

To display the report for an attestation case

1. In the Manager, select the category
 - **Attestation > Attestation runs > Attestation policies > <attestation policy> > Attestation runs > <year> > <month> > <day>** - OR -
 - **Attestation > Attestation run > Policy collections > <policy collection> > Attestation runs > <year> > <month> > <day>**.
2. Select the **Pending attestations** or the **Completed attestations** filter.
3. Select an attestation case from the result list.
4. Select the **Show report** task.

This displays the report defined by the attestation procedure report in an external PDF reader.

NOTE: The report will be generated in the language given in the attestation guideline if there are translations available for it in the database. Otherwise, the default language is used, which is stored as a fallback variant in the database information.

To display a snapshot of an attestation case

1. In the Manager, select the category
 - **Attestation > Attestation runs > Attestation policies > <attestation policy> > Attestation runs > <year> > <month> > <day>** - OR -
 - **Attestation > Attestation run > Policy collections > <policy collection> > Attestation runs > <year> > <month> > <day>**.
2. Select the **Pending attestations** or the **Closed attestations** filter.
3. Select an attestation case from the result list.
4. Select the **Show object data** task.

This displays all the attestation procedure properties that are defined for the snapshot.

Related topics

- [Defining snapshot content](#) on page 20
- [Defining reports for attestation](#) on page 20
- [General main data of attestation policies](#) on page 38

Assigning extended properties to attestation cases

Extended properties are meta objects, such as operating codes, cost codes, or cost accounting areas that cannot be mapped directly in One Identity Manager.


For more information about using extended properties, see the *One Identity Manager Compliance Rules Administration Guide*.

To specify extended properties for an attestation case

1. In the Manager, select the category
 - **Attestation > Attestation runs > Attestation policies > <attestation policy> > Attestation runs > <year> > <month> > <day>** - OR -
 - **Attestation > Attestation run > Policy collections > <policy collection> > Attestation runs > <year> > <month> > <day>**.
2. Select the **Pending attestations** or the **Closed attestations** filter.
3. Select an attestation case from the result list.
4. Select **Assign extended properties**.
5. In the **Add assignments** pane, assign extended properties.

TIP: In the **Remove assignments** pane, you can remove assigned extended properties.

To remove an assignment

- Select the extended property and double-click .
6. Save the changes.

Related topics

- [Attestation case overview](#) on page 147

Displaying incomplete attestation runs

The Manager displays attestation runs where not all attestation cases have been generated yet. For example, this might happen if there is a large number of attestation objects or if the process that generates the attestation cases, is not processed.

To display an incomplete attestation run

1. In the Manager, select the category
 - **Attestation > Incomplete attestation runs > Attestation policies > <attestation policy>**. - OR -
 - **Attestation > Incomplete attestation runs > Policy collections > <policy collection>**.
2. Select the attestation run in the result list.
3. Select the **Attestation run overview** task.

This gives you an overview of attestation cases that already exist and are either pending attestation (pending attestation cases) or already closed (denied and approved attestation cases).

If incomplete attestation runs are shown, check in the Job Queue Info program whether the process that processes the `CompleteCasesUnderConstruction` customizer method is still running. Check and correct any errors. If the errors cannot be corrected, you can cancel the incomplete attestation runs.

Related topics

- [Canceling incomplete attestation runs](#) on page 178
- [Displaying canceled attestation runs](#) on page 179

Canceling incomplete attestation runs

If errors that occur when attestation cases are being generated for an attestation run, cannot be corrected the incomplete attestation run can be canceled. After that, attestation can be restarted with the affected attestation policy.

As long as an incomplete attestation run still exists for an attestation policy, attestation cannot be restarted. If attestation needs to be started although a incomplete attestation run still exists, the attestation run must be canceled.

To cancel an incomplete attestation run

1. In the Manager, select the category
 - **Attestation > Incomplete attestation runs > Attestation policies > <attestation policy>**. - OR -
 - **Attestation > Incomplete attestation runs > Policy collections > <policy collection>**.
2. Select the attestation run in the result list.
3. Select the **Change main data** task.
4. Select the **Cancel attestation run** task.
5. Confirm the security prompt with **Yes**.

There are no new attestation cases generated. All pending attestation cases are canceled and the attestation run is labeled as canceled.

Related topics

- [Displaying incomplete attestation runs](#) on page 178
- [Displaying canceled attestation runs](#) on page 179

Displaying canceled attestation runs

All the attestation runs that are canceled manually are displayed in the Manager.

To display a canceled attestation run

1. In the Manager, select the category
 - **Attestation > Canceled attestation runs > Attestation policies > <attestation policy>** - OR -
 - **Attestation > Canceled attestation runs > Policy collections > <policy collection>**.

2. Select the attestation run in the result list.

3. Select the **Attestation run overview** task.

This shows you an overview of the denied and approved attestation cases in this attestation run.

Related topics

- [Canceling incomplete attestation runs](#) on page 178
- [Displaying incomplete attestation runs](#) on page 178

Reports about attestations

One Identity Manager makes various reports available containing information about the selected base object and its relations to other One Identity Manager database objects. You can use attestations to generate the following reports.

Table 40: Reports about attestations

Report	Published for	Description
Overview attestation run results	Attestation policy	This report shows the results of an attestation run for the selected attestation policy.
Overview attestation run results including attestation history	Attestation policy	This report shows the results of an attestation run for the selected attestation policy including the attestation history.
Detailed status of an attestation run	Attestation policy	This report shows the detailed status of an attestation run including the estimated completion date.
Detailed status of an attestation run including approval history	Attestation policy	This report shows the detailed status of an attestation run including the estimated completion date and attestation history.
Overview attestation run results	Policy collection	This report shows the results of an attestation run for the attestation policies from the selected policy collection.

Default attestations

One Identity Manager provides various default attestation procedures for different data situations and default attestation procedures.

Data situations for default attestations:

- System entitlements owned by an identity
- System entitlements assigned to system entitlements
- System entitlements assigned to hierarchical roles
- System roles assigned to an identity
- Company resources assigned to system roles
- System roles assigned to hierarchical roles
- Business and application role memberships
- New One Identity Manager user's main data
- Existing One Identity Manager user's main data
- Attestation of access to OneLogin applications.
- Attestation of unused access to OneLogin applications.

The attestation policies required for attesting identity main data are also supplied by default. You can also use the default supplied attestation policies without modifying them. The prerequisites and the attestation sequence for identity main data are described in [User attestation and recertification](#) on page 190.

Default attestation policies and default attestation procedures are provided for recertification of unused entitlements under Behavior Driven Governance. For more information on how to use these, see the *One Identity Manager Administration Guide for Behavior Driven Governance*.

You can set up attestation policies easily in the Web Portal using default attestation procedures for other data situations. You can also use the default attestation policies supplied without customizing them. Furthermore, you can configure how to deal with denied attestations that are based on these default attestation procedures. For more information, see [Configuring withdrawal of entitlements](#) on page 182.

A default policy collection and a default sample are provided to attest a selection of identities along with all their entitlements and memberships. The policy collection combines

all default attestation policies required for this purpose. For more information, see [Configuring sample attestation of identities and their entitlements](#) on page 189.

Configuring withdrawal of entitlements

If your specific data situation allows, denied entitlements can be withdrawn by One Identity Manager following attestation.

To withdraw denied entitlements automatically

1. In the Designer, set the **QER | Attestation | AutoRemovalScope** configuration parameter and the configuration subparameters.
2. If the entitlements were obtained through IT Shop, specify whether these requests should be unsubscribed or canceled. To do this, set the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter and select a value.
 - **Abort**: Requests are canceled. In this case, they do not go through a cancellation workflow. The requested entitlements are withdrawn without additional checks.
 - **Unsubscribe**: Requests are unsubscribed. They go through the cancellation workflow defined in the approval policies. Withdrawal of the entitlement can thus be subjected to an additional check.

If the cancellation is denied, the entitlement is not withdrawn even though the attestation has been denied.

If the configuration parameter is not set, the requests are canceled.

IMPORTANT: If role memberships or system roles are withdrawn from an identity, the identity loses the denied entitlement. They also lose all other company resources inherited through this role. These could be other system entitlements or account definitions. This might cause valid system entitlements to be withdrawn or user accounts to be deleted from the identity!

Check whether your data situation allows automatic withdrawal of entitlements before you enable configuration parameters under **QER | Attestation | AutoRemovalScope**.

Automatic removal of entitlements is triggered by an additional approval step with the EX approval procedure in the default approval workflows.

Attestation sequence with subsequence withdrawal of denied entitlements:

1. Attestation is carried out using a default attestation procedure.
2. The attestor denies attestation. The approval step is not granted approval and approval is passed on the next approval level with the EX approval procedure.
3. The approval step triggers the AUTOREMOVE event. This runs the VI_Attestation_AttestationCase_AutoRemoveMembership process.

4. The process runs the `VI_AttestationCase_RemoveMembership` script. This removes the affected entitlement depending on which configuration parameters are set.
5. The script sets the approval step status to **Denied**. This means the entire attestation case is finally denied.
6. Tasks to recalculate inheritance are entered in the DBQueue.

Detailed information about this topic

- [Attesting system entitlements](#) on page 183
- [System role attestation](#) on page 185
- [Application role attestation](#) on page 188
- [Business role attestation](#) on page 188

Attesting system entitlements

Installed modules: Target System Base Module

If you attest memberships in system entitlements, you can use the **QER | Attestation | AutoRemovalScope | GroupMembership** configuration parameter to configure automatic removal of system entitlements. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the system entitlement.

- **QER | Attestation | AutoRemovalScope | GroupMembership | RemoveDirect**

Direct membership of the user account in the system entitlement, is removed.

- **QER | Attestation | AutoRemovalScope | GroupMembership | RemovePrimaryRole**

If membership in the system entitlement was inherited through a primary role, the role is withdrawn from the identity.

This removes all indirect assignments obtained by the identity through this role.

- **QER | Attestation | AutoRemovalScope | GroupMembership | RemoveRequestedRole**

If membership of the system entitlement was inherited through a requested role, the role request is canceled or unsubscribed.

This removes all indirect assignments obtained by the identity through this role.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | GroupMembership | RemoveDelegatedRole**

If membership in the system entitlement was inherited through a delegated role, delegation of this role is canceled or unsubscribed.

This removes all indirect assignments obtained by the identity through this role.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | GroupMembership | RemoveRequested**

If membership of the system entitlement was requested through the IT Shop, the request is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | GroupMembership | RemoveSystemRole**

System roles incorporating the system entitlements are withdrawn from the identity.

This removes all indirect assignments obtained by the identity through this system role.

This configuration parameter is only available if the System Roles Module is installed.

- **QER | Attestation | AutoRemovalScope | GroupMembership | RemoveDirectRole**

If membership in the system entitlement was inherited through a secondary role (organization or business role), the identity's membership is removed from this role.

This removes all indirect assignments obtained by the identity through this role.

- **QER | Attestation | AutoRemovalScope | GroupMembership | RemoveDynamicRole**

If membership in the system entitlement was inherited through a dynamic role, the identity is excluded from the dynamic role.

This removes all indirect assignments obtained by the identity through this role.

If you attest assignments to system entitlements, you can use the **QER | Attestation | AutoRemovalScope | UNSGroupInUNSGroup** configuration parameter to configure automatic removal of system entitlements.

- **QER | Attestation | AutoRemovalScope | UNSGroupInUNSGroup | RemoveDirect**

Assignment of the system entitlement to a system entitlement is removed.

If you attest system entitlement assignments to hierarchical roles, you can use the following configuration parameters to configure automatic removal of system entitlements.

If the assignment of the system entitlement to a hierarchical role is removed after attestation is denied, the system entitlement is removed from all identities that inherit assignments from this role.

- **QER | Attestation | AutoRemovalScope | DepartmentHasUNSGroup | RemoveDirect**
The assignment of the system entitlement to a department is removed.
- **QER | Attestation | AutoRemovalScope | ProfitCenterHasUNSGroup | RemoveDirect**
The assignment of the system entitlement to a cost center is removed.
- **QER | Attestation | AutoRemovalScope | LocalityHasUNSGroup | RemoveDirect**
The assignment of the system entitlement to a location is removed.
- **QER | Attestation | AutoRemovalScope | OrgHasUNSGroup | RemoveDirect**
The assignment of a system entitlement to a business role is removed.

Related topics

- [Configuring withdrawal of entitlements](#) on page 182

System role attestation

Installed modules: System Roles Module

If you attest memberships in system roles, you can use the **QER | Attestation | AutoRemovalScope | ESetAssignment** configuration parameter to configure the automatic removal of system roles. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the system role.

If membership of the system role is removed after an attestation has been denied, all indirect assignments that the identity obtained via this system role are removed.

- **QER | Attestation | AutoRemovalScope | ESetAssignment | RemoveDirect**
Direct membership in the system role is removed.
- **QER | Attestation | AutoRemovalScope | ESetAssignment | RemovePrimaryRole**
If the system role was inherited through a primary role, the role is withdrawn.
This removes all indirect assignments obtained by the identity through this role.
- **QER | Attestation | AutoRemovalScope | ESetAssignment | RemoveRequestedRole**
If the system role was inherited through a requested role, the role request is canceled or unsubscribed.
This removes all indirect assignments obtained by the identity through this role.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | ESetAssignment | RemoveDelegatedRole**

If the system role was inherited through a delegated role, the delegation of this role is canceled or unsubscribed.

This removes all indirect assignments obtained by the identity through this role.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | ESetAssignment | RemoveRequested**

If the system role was requested through the IT Shop, the request is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | ESetAssignment | RemoveDirectRole**

If the system role was inherited through a secondary role (organization or business role), the identity's membership is removed from this role.

This removes all indirect assignments obtained by the identity through this role.

- **QER | Attestation | AutoRemovalScope | ESetAssignment | RemoveDynamicRole**

If the system role was inherited through a dynamic role, the identity is excluded from the dynamic role.

This removes all indirect assignments obtained by the identity through this role.

If you attest assignments to system roles, you can use the **QER | Attestation | AutoRemovalScope | ESetHasEntitlement** configuration parameter to configure automatic removal of assignments.

- **QER | Attestation | AutoRemovalScope | ESetHasEntitlement | RemoveDirect**

The directly assignment of the company resource to a system role is removed.

- **QER | Attestation | AutoRemovalScope | ESetHasEntitlement | RemoveRequested**

If the assignment of the company resource to a system role was requested through the IT Shop, the request is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

If you attest system role assignments to hierarchical roles, you can use the following configuration parameters to configure automatic removal of system roles.

If the assignment of the system role to a hierarchical role is removed after attestation is denied, the system role is removed from all identities that inherit assignments from this

role. This removes all indirect assignments obtained by the identities through this system role.

- **QER | Attestation | AutoRemovalScope | DepartmentHasESet | RemoveDirect**

Direct system roles assignments to departments are removed.

- **QER | Attestation | AutoRemovalScope | DepartmentHasESet | RemoveRequested**

If the system role assignment to a department was requested via the IT Shop, the request is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | ProfitCenterHasESet | RemoveDirect**

Direct system roles assignments to cost centers are removed.

- **QER | Attestation | AutoRemovalScope | ProfitCenterHasESet | RemoveRequested**

If the system role assignment to a cost center was requested via the IT Shop, the request is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | LocalityHasESet | RemoveDirect**

Direct system roles assignments to locations are removed.

- **QER | Attestation | AutoRemovalScope | LocalityHasESet | RemoveRequested**

If the system role assignment to a location was requested via the IT Shop, the request is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | OrgHasESet | RemoveDirect**

Direct system roles assignments to business roles are removed.

- **QER | Attestation | AutoRemovalScope | OrgHasESet | RemoveRequested**

If the system role assignment to a business role was requested via the IT Shop, the request is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

Related topics

- [Configuring withdrawal of entitlements](#) on page 182

Application role attestation

If you attest memberships in application roles, you can use the **QER | Attestation | AutoRemovalScope | AERoleMembership** configuration parameter to configure automatic removal of application roles. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the application role.

If membership of the application role is removed after an attestation has been denied, all indirect assignments that the identity obtained via this application role are removed.

- **QER | Attestation | AutoRemovalScope | AERoleMembership | RemoveDirectRole**

The identity's secondary membership is removed from the application role.

Membership in dynamic roles is not removed in this process.

- **QER | Attestation | AutoRemovalScope | AERoleMembership | RemoveRequestedRole**

If the identity requested the application role through the IT Shop, the request is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | AERoleMembership | RemoveDelegatedRole**

If the application role was delegated to the identity, delegation is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | AERoleMembership | RemoveDynamicRole**

The identity is excluded from the application role's dynamic role.

This does not remove memberships in the application role that were created in another way.

Related topics

- [Configuring withdrawal of entitlements](#) on page 182

Business role attestation

Installed modules: Business Roles Module

If you attest memberships in business roles, you can use the **QER | Attestation | AutoRemovalScope | RoleMembership** configuration parameter to configure automatic removal of business roles. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the business role.

If membership of the business role is removed after an attestation is denied, all indirect assignments that the identity obtained via this business role are removed.

- **QER | Attestation | AutoRemovalScope | RoleMembership | RemoveDirectRole**

The identity's secondary membership in the business role is removed.

Membership in dynamic roles is not removed by this.

- **QER | Attestation | AutoRemovalScope | RoleMembership | RemoveRequestedRole**

If the identity requested the business role through the IT Shop, the request is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | RoleMembership | RemoveDelegatedRole**

If the business role was delegated to the identity, delegation is canceled or unsubscribed.

Set the desired behavior in the **QER | Attestation | AutoRemovalScope | PWOMethodName** configuration parameter.

- **QER | Attestation | AutoRemovalScope | RoleMembership | RemoveDynamicRole**

The identity is excluded from the business role's dynamic role.

This does not remove memberships in the business role that were created in another way.

Related topics

- [Configuring withdrawal of entitlements](#) on page 182

Configuring sample attestation of identities and their entitlements

The **Identity attestation** default policy collection combines all default attestation policies to attest identities along with all their entitlements and memberships. The policy collection is assigned to a default sample that you use to specify which identities to attest.

To set up comprehensive attestation of selected identities

1. Manually assign the identities to be attested to the **Individual selection of identities** sample.
2. Create a schedule and assign it to the **Identity attestation** policy collection. By doing this, you replace the schedule assigned by default.
 - Enable the schedule.

Related topics

- [General main data of policy collections](#) on page 57
- [Attestation schedules](#) on page 24
- [Managing sampling data](#) on page 52

User attestation and recertification

Use the One Identity Manager attestation functionality to regularly check and authorize identities' main data and target system entitlements and assignments. In addition, One Identity Manager provides default procedures for managers to quickly attest and certify the main data of newly added One Identity Manager users in the One Identity Manager database. This functionality can be used, for example, if external identities, such as contract workers, are provided with temporary access to One Identity Manager. The sequence is different for internal and external identities.

Regular recertification can be run through scheduled tasks.

In the context of an attestation, a manager can check and update the main data of the user to be certified, if necessary. Use the Web Portal for attestation.

Detailed information about this topic

- [Configuring user attestation and recertification](#) on page 192
- [Attesting new users](#) on page 193
- [Recertifying existing users](#) on page 201

Related topics

- [Certifying new roles and organizations](#) on page 204

One Identity Manager users for attesting and recertifying users

The following users are used for attesting and recertifying identities.

Table 41: Users

Users	Tasks
Identity administrators	<p>Identity administrators must be assigned to the Identity Management Identities Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Can edit any identity's main data • Assign managers to identities. • Can assign company resources to identities. • Check and authorize identity main data. • Create and edit risk index functions. • Edit password policies of identities' passwords. • Delete identity's security keys (WebAuthn) • Can see everyone's requests, attestations, and delegations and edit delegations in the Web Portal.
Manager	<ul style="list-style-type: none"> • Check identity main data of the internal user to be certified. • Update identity main data as required. • Assign another manager if required. • Attests the main data.
Attestors for external users	<p>Attestors for external users must be assigned to the Identity & Access Governance Attestation Attestors for external users application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Attests new, external identities.
Administrators for attestation cases	<p>Administrators must be assigned to the Identity & Access Governance Attestation Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Modify the attestation policies if necessary. • Create more schedules if required.
Web Portal users	<ul style="list-style-type: none"> • Log on to the Web Portal and enter their main data,
Self-registered identities	<p>External identities, who have registered themselves in the Web Portal, are assigned to the Base roles Self-registered identities application role through a dynamic role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Specify their password and password questions for logging in to One Identity Manager tools.

Configuring user attestation and recertification

To use the attestation and recertification function for new internal users

1. In the Designer, set the **QER | Attestation | UserApproval** configuration parameter.
2. Assign at least one identity to the **Identity Management | Identities | Administrators** application role.

All identities with this application role can assign a manager to the identity being attested during the attestation run.

To use the attestation and recertification function for new external users

1. In the Designer, set the following configuration parameters:
 - **QER | Attestation | ApproveNewExternalUsers**: Select the value **1**.
 - **QER | WebPortal | PasswordResetURL**: Specify the API Server's web address that deploys the Password Reset Portal. This web address is used for navigation.
 - **QER | Attestation | MailTemplateIdents | NewExternalUserVerification**: Mail template sending verification links.
 - **QER | Attestation | NewExternalUserTimeoutInHours**: For new external users, specify the duration of the verification link in hours.

The default is 4 hours. If logging in to the Password Reset Portal fails because the timeout has expired, the user can ask for a new verification link to be sent. To change the duration of the verification link, change the value in the configuration parameter.
 - **QER | Attestation | NewExternalUserFinalTimeoutInHours**: Specify the duration in hours, within which self-registration must be successfully completed.

If the user does not complete registration with 24 hours, the attestation case quits. To register anyway, the user must log in again to the Web Portal from the beginning. To change the checkout duration of registration, change the value of the configuration parameter.
2. Assign at least one identity to the **Identity & Access Governance | Attestation | Attestor for external users** application role.

Detailed information about this topic

- [Self-registration of new users in the Web Portal](#) on page 193
- [Adding new identities using a manager or administrator for identities](#) on page 195
- [Importing new identity main data](#) on page 198

- [The recertification sequence](#) on page 202
- [Link for verifying new external users](#) on page 162

Attesting new users

Attestation of new users is divided into three use cases by One Identity Manager:

1. Registration of new external users logging in to the Web Portal.
2. Adding new identities in the Manager or using a manager in the Web Portal.
3. Adding new identities by importing identity main data.

The result of attestation is the same in all three cases.

- Certified, activated identities who can access all entitlements assigned to them in One Identity Manager and the connected target systems.

Company resources are inherited. Account definitions are assigned to internal identities.

- OR -

- Denied and permanently deactivated identities.

Disable identities cannot log in to One Identity Manager tools. Company resources are not inherited. Account definitions are not automatically assigned. User accounts associated with the identity are also locked or deleted. You can customize the behavior to meet your requirements.

Self-registration of new users in the Web Portal

Users who are not yet registered have the option to register themselves to use the Web Portal. These users can log in to the Web Portal once a manager has attested the user's main data and the set the user's password. This adds an external identity to the One Identity Manager database.

Attestation sequence:

1. The user logs in to the Web Portal for the first time and enters the required properties.

A new identity is added to the One Identity Manager database with properties:

Table 42: Properties of a newly added identity

Property	Value
Certification status	New
External	Set
Contact email address	Email address to send the verification link to.
Permanently deactivated	Set
No inheritance	Set

2. Attestation is started automatically.

Attestation policy used: **New user certification**

NOTE: The attestation only starts automatically if the **QER | Attestation | UserApproval** configuration parameter is set. Otherwise the new user remains permanently deactivated until a manager changes the identity main data manually.

3. Attestors are found.

Effective approval policy: **Certification of users**

4. If the **QER | Attestation | ApproveNewExternalUsers** configuration parameter is set and the value is **1**, attestation of members of the **Identity & Access Governance | Attestation | Attestors for external users** is submitted.
 - a. If an attestor for external users denies the attestation, the attestation case is closed. The identity's properties are updated in the database.

Table 43: Properties of an external identity with denied attestation

Property	Value	Explanation
Certification status	Denied	
External	Set	
Permanently deactivated	Set	The user cannot log in to the Web Portal.
No inheritance	Set	Company resources are not inherited.

- b. If an attestor for external users approves attestation, an email with a verification link is sent to the new user.

NOTE: If the **QER | Attestation | ApproveNewExternalUsers** configuration parameter is not set or the value is **0**, an email with a verification link is sent immediately to the new user.

5. Once the user has followed the link and a password and a password question have been set, the attestation case is approved. The identity's properties are updated in the database.

Table 44: Properties of an external identity with approved attestation

Property	Value	Explanation
Certification status	Certified	
External	Set	
Permanently deactivated	Not set	The user can log in to the Web Portal.
No inheritance	Not set	Company resources are inherited.

The default is 4 hours. If logging in to the Password Reset Portal fails because the timeout has expired, the user can ask for a new verification link to be sent.

If the user does not complete registration with 24 hours, the attestation case quits. To register anyway, the user must log in again to the Web Portal from the beginning.

Related topics

- [Configuring user attestation and recertification](#) on page 192

Adding new identities using a manager or administrator for identities

You can also attest new users if new identities are added in the Manager or if a manager in the Web Portal adds a new identities. Specify the required behavior with the configuration parameter **QER | Attestation | UserApproval | InitialApprovalState**. This configuration parameter has the default value **0**. This gives each new identity the certification status **Certified**. Automatic attestation is not carried out.

To automatically attest new users

- In the Designer, enable the **QER | Attestation | UserApproval | InitialApprovalState** configuration parameter and set the value to **1**.

All identities added to the database from this point on are given the certification status **New**. This means automatic attestation of these identities is carried out.

The sequence is different for internal and external identities.

Attestation sequence:

1. Enter the new user's main data and assign a manager to them.

For more information about adding identities, see the *One Identity Manager Identity Management Base Module Administration Guide* and the *One Identity Manager Web Portal User Guide*.

The certification status corresponds to the value of the **QER | Attestation | UserApproval | InitialApprovalState** configuration parameter. If the configuration parameter has the value **1**, certification status is set to **New**.

The identity is activated by default. They can therefore log in to One Identity Manager immediately. To ensure that the identity cannot log in to One Identity Manager until their main data has been attested, deactivate the identity.

- To do this, run the **Deactivate identity permanently** task.
2. Once the identity's main data has been saved, attestation starts.
Attestation policy used: **New user certification**
 3. Attestors are found.
Effective approval policy: **Certification of users**
 4. If the **External** option is set for the identity:
Attestation takes place as described in the [Self-registration of new users in the Web Portal](#) section, steps 4 to 5.
 5. If the **External** option is set for the identity:
 - a. One Identity Manager checks whether you have assigned a manager to the identity.
 - If you have assigned a manager to the identity, the case is immediately passed on to them for approval.
 - If you have not assigned a manager to the identity, the case is assigned to the identity administrators for approval.
 - b. An identity administrator checks your main data and also assigns a manager to you.
 - An identity administrator assigns a manager and approves attestation. The attestation case is assigned to the manager for approval.
 - If the identity administrator does not assign a manager and approves attestation, the attestation case is closed. The identity's properties are updated in the database.

Table 45: Properties of an identity with approved attestation

Property	Value	Explanation
Certification status	Certified	
External	Not set	
Disabled permanently	Not set	
No inheritance	Not set	Company resources are inherited.

- If the identity administrator denies attestation, the attestation case is closed. The identity properties are updated in the database.

Table 46: Properties of an identity with rejected attestation

Property	Value	Explanation
Ceritfication status	Rejected	
External	Not set	
Permanently disabled	Set	
No inheritance	Set	Company resources are not inherited. User accounts are not created automatically.

- c. The manager can deny attestation approval if they are not the manager in charge of the user.
- The manager can assign another identity as manager. The attestation case is immediately assigned to this manager.
 - If the manager does not know who your manager is, approval is returned to the identity administrators. These can
 - Assign another manager
 - Not assign another manager and grant attestation approval
 - Deny attestation approval
- d. If the manager approves attestation, the attestation case is closed. The identity properties are updated in the database.

Table 47: Properties of an identity with approved attestation

Property	Value	Explanation
Certification status	Certified	
External	Not set	
Disabled permanently	Not set	
No inheritance	Not set	Company resources are inherited.

NOTE: Only identity administrators can ultimately deny attestation approval. If a manager denies attestation, the case is returned to the identity administrators for approval in any case.

Related topics

- [Configuring user attestation and recertification](#) on page 192

Importing new identity main data

You can request attestation of new identities if the main data is imported from other systems into the One Identity Manager database. To ensure that new identities are automatically attested, you must set the identity's certification status to **New** (`Person.ApprovalState = '1'`). There are two possible ways to do this:

1. The **QER | Attestation | UserApproval | InitialApprovalState** configuration parameter is evaluated for certification status. If the configuration parameter has the value **1**, certification status is set to **New**.

Prerequisite: The import does not alter the `Person.ApprovalState` property.

NOTE: The **QER | Attestation | UserApproval | InitialApprovalState** configuration parameter has the value **0** by default. This gives each new identity the certification status **Certified**. Automatic attestation is not carried out.

If you want to attest new identities immediately, change the value of the configuration parameter to **1**.

2. The import sets the `Person.ApprovalState` property explicitly.
 - The import sets `ApprovalState='1'` (**New**).
The identity is automatically sent to the manager for attestation.
 - The import sets `ApprovalState='0'` (**Certified**).
Imported identity main data has already been authorized. It should not be attested again.
 - The import sets `ApprovalState='3'` (**Denied**).
The identity is deactivated permanently and is not attested.

Attestation of new users is triggered when:

- The **QER | Attestation | UserApproval** configuration parameter is set
- New identity main data was imported into the One Identity Manager database
- The certification status for new identities is set to **New**
- No **Import data source** is stored with the identity.

If the **External** option is not set for an identity, attestation takes place as described in the [Adding new identities using a manager or administrator for identities](#) section, step 5.

If the **External** option is set for the identity, attestation takes place as described in the [Self-registration of new users in the Web Portal](#) section, steps 4 to 5.

The **New user certification** attestation policy is run.

Related topics

- [Configuring user attestation and recertification](#) on page 192

Scheduled attestation

Users are also attested when the certification status for an identity is set to **New** at a later date (manually or through import). The **Daily** schedule is assigned to the **New user certification** attestation policy for this purpose. Attestation of new users is started when the time set in the schedule is reached. This process determines all identities with the certification status **New** and for whom no attestation cases are pending.

You can assign a custom schedule to the attestation policy if required.

Detailed information about this topic

- [Attestation schedules](#) on page 24

Limiting attestation objects for certification

IMPORTANT: In order to customize the default **New user certification** attestation policy, you must make changes to One Identity Manager objects. Always use a custom copy of the respective object to make changes.

It may be necessary to limit attestation of new users to a certain group of identities, for example, if only identities in a specific departments should be attested. To do this, you can extend the condition attached to the attestation policy. Create a custom attestation policy for this.

The following objects must be changed so that attestation of new users can be carried out with this attestation policy. Always create a copy of the respective object to do this.

- **New user certification** attestation policy
- VI_Attestation_Person_new_AttestationCase_for_Certification process
- VI_Attestation_AttestationCase_Person_Approval_Granted process
- VI_Attestation_AttestationCase_Person_Approval_Dismissed process

IMPORTANT: In order for attestation to run correctly in the Web Portal, the default **Certification of users** attestation procedure and the default **Certification of users** approval policy must be assigned to the attestation policy.

The default attestation procedure, the default approval policy, and the default **Certification of users** approval workflow must not be changed.

To customize default attestation of new users

1. Copy the **Certification of users** attestation policy and customize it.

Table 48: Attestation policy properties

Property	Value
Attestation procedure	Certification of users.
Approval policies	Certification of users.
Editing conditions	Copy the default condition without modification so that the correct attestation object is selected. To limit the number of attestation objects, you can add additional partial conditions to the database query.

2. In the Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Certification process of the Person base object and customize the copy.

Table 49: Process properties with changes

Process step	Parameter	Change
Create attestation instance	WhereClause	Replace the UID of the New user certification attestation policy with the UID of the new attestation policy.

3. In the Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Granted process of the AttestationCase base object and customize the copy.

Table 50: Process properties with changes

Process property	Change
Pre-script for generating condition	Replace the UID of the New user certification attestation policy with the UID of the new attestation policy.

4. In the Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Dismissed process of the AttestationCase base object and customize the copy.

Table 51: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the New user certification attestation policy with the UID of the new attestation policy.
Generating condition	

For more information about editing processes, see the *One Identity Manager Configuration Guide*.

Detailed information about this topic

- [General main data of attestation policies](#) on page 38
- [Copy attestation policies](#) on page 48

Recertifying existing users

IMPORTANT: Access to connected target systems may possibly be denied to One Identity Manager users as a result of recertification. You can configure this behavior to meet your company's requirements. Read the following section thoroughly before you use the recertification function.

One Identity Manager provides an attestation policy for performing cyclical attestation of existing users allowing companies to regularly test and authorize identity main data stored in the One Identity Manager database. Cyclical attestation is triggered through a scheduled task. This resets the certification status for all identities stored in the database. One Identity Manager uses the same procedure for this as for attesting new users. The case is referred to as recertification.

Result of recertification

- Certified, activated identities who can access all entitlements assigned to them in One Identity Manager and the connected target systems.

Company resources are inherited. Account definitions are assigned to internal identities.

- OR -

- Denied and permanently deactivated identities.

Disable identities cannot log in to One Identity Manager tools. Company resources are not inherited. Account definitions are not automatically assigned. User accounts associated with the identity are also locked or deleted. You can customize the behavior to meet your requirements.

Preparing for recertification

To set up regular user attestation

1. In the Designer, set the required configuration parameters.
2. Create a schedule and assign it to the **User recertification** attestation policy. By doing this, you replace the schedule assigned by default.
 - Enable the schedule.

Detailed information about this topic

- [Configuring user attestation and recertification](#) on page 192

Related topics

- [General main data of attestation policies](#) on page 38
- [Attestation schedules](#) on page 24

The recertification sequence

One Identity Manager uses the same method for recertification as for certification of new users. User recertification is triggered when all the following are true:

- The **QER | Attestation | UserApproval** configuration parameter is set.
- No **Import data source** is stored with the identity or the **Import data source** is not **E-Business Suite**.
- The processing time in the schedule stored for the **User recertification** attestation policy has been reached.

Internal identities are attested by their manager. If an identity is not assigned a manager, the identity administrator assigns an initial manager for them. Only identity administrators can ultimately deny recertification. If a manager denies recertification, the case is returned to the identity administrators for approval in any case.

External identities are attested by members of the **Identity & Access Governance | Attestation | Attestors for external users** application role.

If the **External** option is not set for an identity, attestation takes place as described in the [Adding new identities using a manager or administrator for identities](#) section, step 5.

If the **External** option is set for the identity, attestation takes place as described in the [Self-registration of new users in the Web Portal](#) section, steps 4 to 5.

The attestors are determined using the **Certification of users** approval policy.

Limiting attestation objects for recertification

IMPORTANT: In order to customize the **User recertification** default attestation policy, you must make changes to One Identity Manager objects. Always use a custom copy of the relevant object to make these changes.

All identities saved in the database are recertified using the **User recertification** attestation policy supplied in One Identity Manager. It may be necessary to limit recertification of new users to a certain group of identities, for example, if only identities in a specific departments should be attested. To do this, you can extend the condition attached to the attestation policy. Create a custom attestation policy for this.

The following objects must be changed so that recertification of users can be carried out with this attestation policy. Always create a copy of the respective object to do this.

- **User recertification** attestation policy
- VI_Attestation_AttestationCase_Person_Approval_Granted process
- VI_Attestation_AttestationCase_Person_Approval_Dismissed process

IMPORTANT: In order for recertification to run correctly in the Web Portal, the default **Certification of users** attestation procedure and the default **Certification of users** approval policy must be assigned to the attestation policy.

The default attestation procedure, the default approval policy, and the default **Certification of users** approval workflow must not be changed.

To customize default recertification of users

1. Copy the **User recertification** attestation policy and customize it.

Table 52: Attestation policy properties

Property	Value
Attestation procedure	Certification of users.
Approval policies	Certification of users.
Editing conditions	Copy the default condition without modification so that the correct attestation object is selected. To limit the number of attestation objects, you can add additional partial conditions to the database query.

2. In the Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Granted process of the AttestationCase base object and customize the copy.

Table 53: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the User recertification attestation policy with the UID of the new attestation policy.
Generating condition	

3. In the Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Dismissed process of the AttestationCase base object and customize the copy.

Table 54: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the User recertification attestation policy with the UID of the new attestation policy.
Generating condition	

For more information about editing processes, see the *One Identity Manager Configuration Guide*.

Detailed information about this topic

- [General main data of attestation policies](#) on page 38
- [Copy attestation policies](#) on page 48

Certifying new roles and organizations

NOTE: This functionality is only available if the Target System Base Module is installed.

One Identity Manager provides default procedures for managers to quickly attest and certify the main data of newly added application roles, business roles, and organizations in the One Identity Manager database. Attestation is performed only for roles and organizations with the **New** certification status. If the attestation is approved, the certificate status of the attested role or organization is set to **Certified** and otherwise, to **Denied**.

Attestation is performed when a new role or organization is created in the Manager or the Web Portal or imported into the One Identity Manager database. No **Import data source** can be stored for the role or organization.

NOTE: Following attestation, the certification status is changed. If attestation was granted approval, it disables the **Identities do not inherit** option.

If attestation was denied approval, only the certification status changes. Other behavioral changes, for example in the inheritance calculation, are not associated with this and can be implemented on a custom basis.

Detailed information about this topic

- [One Identity Manager users for certifying roles and organizations](#) on page 205
- [Configuring certification of new departments](#) on page 207
- [Configuring certification of new locations](#) on page 208
- [Configuring certification of new cost centers](#) on page 207
- [Configuring certification of new business roles](#) on page 209
- [Configuring certification of new application roles](#) on page 210

Related topics

- [User attestation and recertification](#) on page 190

One Identity Manager users for certifying roles and organizations

The following users are involved in the certification of roles and organizations.

Table 55: Users

Users	Tasks
Administrators for organizations	Administrators must be assigned to the Identity Management Organizations Administrators application role. Users with this application role: <ul style="list-style-type: none">• Set up and edit departments, cost centers, and locations.• Assign company resources to departments, cost centers, and locations.• Attest the main data of departments, cost centers, and locations.• Administrate application roles for role approvers, role approvers (IT), and attestors.• Set up other application roles as required.
Business roles	Administrators must be assigned to the Identity Management

Users	Tasks
administrators	<p>Business roles Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Create and edit business roles. • Assign company resources to business roles. • Attest business roles' main data. • Administrate application roles for role approvers, role approvers (IT), and attestors. • Set up other application roles as required.
Administrators for basic functionality	<p>Administrators must be assigned to the Base roles Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Administer application roles for administrators. • Assign identities to administrator application roles. • Add other identities to the Base roles Administrators application role and edit conflicting application roles. • See the main data for the other application roles. • Attest application roles' main data. • Can use Password Reset Portal to set passwords for selected system users.
Manager	<ul style="list-style-type: none"> • Check the main data of the roles and organizations to be certified. • Assign another manager if required. • Attests the main data.
Administrators for attestation cases	<p>Administrators must be assigned to the Identity & Access Governance Attestation Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Modify the attestation policies if necessary. • Create more schedules if required.

Detailed information about this topic

- [Certifying new roles and organizations](#) on page 204

Configuring certification of new departments

Attestation and certification of departments with the **New** certification status can start when the following requirements are met.

To certify new departments

1. In the Designer, set the **QER | Attestation | DepartmentApproval** and **QER | Attestation | DepartmentApproval | InitialApprovalState** configuration parameters.
2. The value of the **InitialApprovalState** configuration parameter to **1**.
All departments added to the database from this point on are given the certification status **New**.
3. In the Manager, edit the main data of the **New departments certification** attestation policy.
 - **Calculation schedule**: Schedule for starting attestation.
 - **Disabled**: Disabled.
4. In the Manager, assign at least one identity to the **Identity Management | Organizations | Administrators** application role.
5. Save the changes.

Attestation of imported departments is triggered when:

- Initial certification status was set to **New** by the **InitialApprovalState** configuration parameter.
- OR -
The import sets `Department.ApprovalState='1'`
- There is no **Import data source** stored with the department (`ProfitCenter.ImportSource=''`)

The **Identities do not inherit** option (`Department.IsNoInheritToPerson`) is disabled by the `VI_Attestation_AttestationCase_Department_Approval_Granted` process.

Related topics

- [Certifying new roles and organizations](#) on page 204

Configuring certification of new cost centers

Attestation and certification of cost centers with the **New** certification status can start when the following requirements are met.

To certify new cost centers

1. In the Designer, set the **QER | Attestation | ProfitCenterApproval** and **QER | Attestation | ProfitCenterApproval | InitialApprovalState** configuration parameters.
2. The value of the **InitialApprovalState** configuration parameter to **1**.
All cost centers added to the database from this point on are given the certification status **New**.
3. In the Manager, edit the main data of the **New cost centers certification** attestation policy.
 - **Calculation schedule**: Schedule for starting attestation.
 - **Disabled**: Disabled.
4. In the Manager, assign at least one identity to the **Identity Management | Organizations | Administrators** application role.
5. Save the changes.

Attestation of imported cost centers is triggered when:

- Initial certification status was set to **New** by the **InitialApprovalState** configuration parameter.
- OR -
The import sets `ProfitCenter.ApprovalState='1'`
- There is no **Import data source** stored with the cost center (`ProfitCenter.ImportSource=''`)

The **Identities do not inherit** option (`ProfitCenter.IsNoInheriteToPerson`) is disabled by the `VI_Attestation_AttestationCase_ProfitCenter_Approval_Granted` process.

Related topics

- [Certifying new roles and organizations](#) on page 204

Configuring certification of new locations

Attestation and certification of locations with the **New** certification status can start when the following requirements are met.

To certify a new location

1. In the Designer, set the **QER | Attestation | LocalityApproval** and **QER | Attestation | LocalityApproval | InitialApprovalState** configuration parameters.
2. The value of the **InitialApprovalState** configuration parameter to **1**.

All locations added to the database from this point on are given the certification status **New**.

3. In the Manager, edit the main data of the **New location certification** attestation policy.
 - **Calculation schedule**: Schedule for starting attestation.
 - **Disabled**: Disabled.
4. In the Manager, assign at least one identity to the **Identity Management | Organizations | Administrators** application role.
5. Save the changes.

Attestation of imported locations is triggered when:

- Initial certification status was set to **New** by the **InitialApprovalState** configuration parameter.
 - OR -
 - The import sets `Locality.ApprovalState='1'`
- There is no **Import data source** stored with the location (`Locality.ImportSource=''`)

The **Identities do not inherit** option (`Locality.IsNoInheritToPerson`) is disabled by the `VI_Attestation_AttestationCase_Locality_Approval_Granted` process.

Related topics

- [Certifying new roles and organizations](#) on page 204

Configuring certification of new business roles

Attestation and certification of business roles with the **New** certification status can start when the following requirements are met.

To certify new business roles

1. In the Designer, set the **QER | Attestation | OrgApproval** and **QER | Attestation | OrgApproval | InitialApprovalState** configuration parameters.
2. The value of the **InitialApprovalState** configuration parameter to **1**.

All business roles added to the database from this point on are given the certification status **New**.
3. In the Manager, edit the main data of the **New business roles certification** attestation policy.

- **Calculation schedule:** Schedule for starting attestation.
 - **Disabled:** Disabled.
4. In the Manager, assign at least one identity to the **Identity Management | Business roles | Administrators** application role.
 5. Save the changes.

Attestation and certification is started automatically for business role that were added with the Analyzer tool.

The **Identities do not inherit** option (Org.IsNoInheriteToPerson) is disabled by the VI_Attestation_AttestationCase_Org_Approval_Granted process.

Related topics

- [Certifying new roles and organizations](#) on page 204

Configuring certification of new application roles

Attestation and certification starts for application roles with **New** certification status if the following requirements are met.

To certify new application roles

1. In the Designer, set the **QER | Attestation | AERoleApproval** and **QER | Attestation | AERoleApproval | InitialApprovalState** configuration parameters.
2. The value of the **InitialApprovalState** configuration parameter to **1**.
All application roles added to the database from this point on are given the certification status **New**.
3. In the Manager, edit the main data of the **New application roles certification** attestation policy.
 - **Calculation schedule:** Schedule for starting attestation.
 - **Disabled:** Disabled.
4. In the Manager, assign at least one identity to the **Base roles | Administrators** application role.
5. Save the changes.

Related topics

- [Certifying new roles and organizations](#) on page 204

Mitigating controls for attestation policies

Violation of regulatory requirements can harbor different risks for companies. To evaluate these risks, you can apply risk indexes to attestation policies. These risk indexes provide information about the risk involved for the company if this particular policy is violated. Once the risks have been identified and evaluated, mitigating controls can be implemented.

Mitigating controls are independent on One Identity Manager's functionality. They are not monitored through One Identity Manager.

Mitigating controls describe controls that are implemented if an attestation rule was violated. The attestation can be approved after the next attestation run, once controls have been applied.

To edit mitigating controls

- In the Designer, set the **QER | CalculateRiskIndex** configuration parameter and compile the database.

If you disable the configuration parameter at a later date, model components and scripts that are no longer required, are disabled. SQL procedures and triggers are still carried out. For more information about the behavior of preprocessor relevant configuration parameters and conditional compiling, see the *One Identity Manager Configuration Guide*.

For more information about risk assessment, see the *One Identity Manager Risk Assessment Administration Guide*.

General main data of mitigating controls

To create or edit mitigating controls

1. In the Manager, select the **Risk index functions > Mitigating controls** category.
2. Select a mitigating control in the result list and run the **Change main data** task.

- OR -

Click  in the result list.

3. Edit the mitigating control main data.
4. Save the changes.

Enter the following main data of mitigating controls.

Table 56: General main data of a mitigating control

Property	Description
Measure	Unique identifier for the mitigating control.
Significance reduction	When the mitigating control is implemented, this value is used to reduce the risk of denied attestation cases. Enter a number between 0 and 1 .
Description	Detailed description of the mitigating control.
Functional area	Functional area in which the mitigating control may be applied.
Department	Department in which the mitigating control may be applied.

Additional tasks for mitigating controls

After you have entered the main data, you can run the following tasks.

Mitigating controls overview

You can display the most important information about a mitigating control on the overview form.

To obtain an overview of a mitigating control

1. In the Manager, select the **Risk index functions > Mitigating controls** category.
2. Select the mitigating control in the result list.
3. Select the **Mitigating control overview** task.

Assigning attestation policies

Use this task to specify for which attestation policies the mitigating control is valid.


To assign attestation policies to mitigating controls

1. In the Manager, select the **Risk index functions > Mitigating controls** category.
2. Select the mitigating control in the result list.
3. Select the **Assign attestation policies** task.

Assign the attestation policies in **Add assignments**.

TIP: In **Remove assignments**, you can remove the assignment of attestation policies.

To remove an assignment

- Select the approval policy and double-click .
4. Save the changes.

Calculating mitigating controls for attestation policies

The reduction in significance of a mitigating control supplies the value by which the risk index of an attestation policy is reduced when the control is implemented. One Identity Manager calculates a reduced risk index based on the risk index and the significance reduction. One Identity Manager supplies default functions for calculating reduced risk indexes. These functions cannot be edited with One Identity Manager tools.

The reduced risk index is calculated from the company policy and the significance reduced sum of all assigned mitigating controls.

$\text{Risk index (reduced)} = \text{Risk index} - \text{sum significance reductions}$

If the significance reduction sum is greater than the risk index, the reduced risk index is set to 0.

Setting up attestation in a separate database

Scheduled attestations are often processes that generate a high load. It is possible to outsource such processes to a separate database and thus relieve the central database. To synchronize both databases, set up system synchronization using the One Identity Manager connector. You can optimize use of One Identity Manager functionality by synchronizing with a central database, containing all the data, on a regular basis.

All data required for attestation are transferred from the central database to a work database. The attestation is set up and carried out in the work database. The results of the attestation are transferred to the central database. Subsequent processes, such as the withdrawing entitlements after attestation is denied or risk index calculations, are carried out in the central database.

Detailed information about this topic

- [Requirements for the central database](#) on page 214
- [Setting up work databases](#) on page 215
- [Setting up synchronization between central and work databases](#) on page 217
- [Setting up and running attestations in the work database](#) on page 218

Requirements for the central database

The prerequisites and guidance for connecting a One Identity Manager database apply, as described in the *One Identity Manager User Guide for the One Identity Manager Connector*.

Prerequisites

- The central database has at least version 8.2.
- The System Synchronization Service Module (ISM) is installed in the central database.
 - Disable the **ISM | PrimaryDB | AppServer** configuration parameter. The central database connection parameters are configured in the work database.
- Even if the work and central database have the same product version, it is recommended you connect the central database through an application server and enable the required plugins. This is the only way to use the function that automatically revokes entitlements if attestation is denied.

The Attestation Module can be present in the central database, but it does not have to be. Regardless of this, attestation configuration, such as attestation policies or approval workflows, and the attestation cases themselves, are not synchronized with the central database. Only the attestations results are transferred to enable the evaluation and further processing of the results in the central database.

Related topics

- [Setting up attestation in a separate database](#) on page 214
- [Setting up work databases](#) on page 215
- [Setting up synchronization between central and work databases](#) on page 217
- [Setting up and running attestations in the work database](#) on page 218

Setting up work databases

Ensure that the minimum system requirements for installing the work database are met. For more information, see the *One Identity Manager Installation Guide*.

To set up the work database

1. Install a work database with at least version 8.2.
 - Install the same modules as in the central database, including the System Synchronization Service Module.
 - In addition, install the Attestation Module (ATT).
2. Set up a Job server to handle SQL processes for the work database.
3. To be able to use the Web Portal for attestations
 - a. Install an application server
 - b. Install an API Server.

For more information, see the *One Identity Manager Installation Guide*.

4. In the work database, set the following configuration parameters and specify the credentials to connect to the central database's application server.

Use the same settings that are used when setting up synchronization between the central and working databases.

- **ISM | PrimaryDB | AppServer | AuthenticationString:**

Authentication data for establishing a connection using the REST API of the central database's application server.

Syntax: Module=<authentication module>;<property1>=<value1>;<property2>=<value2>,...

All authentication modules provided by the application server being addressed are allowed. For more information about authentication modules, see the *One Identity Manager Authorization and Authentication Guide*.

Recommended values are:

- Module=DialogUser;User=<user name>;Password=<password>
- Module=DialogUserAccountBased
- Module=Token

For authentication using an OAuth 2.0 access token, additionally specify ClientId, ClientSecret, and TokenEndpoint in the **ConnectionString** configuration parameter. For more information about OAuth 2.0/OpenID Connect authentication, see the *One Identity Manager Authorization and Authentication Guide*.

- **ISM | PrimaryDB | AppServer | ConnectionString:**

Connection parameters for establishing a connection using the REST API of the central database's application server.

Syntax: Url=<application server URL>

If **Module=Token** is set in the AuthenticationString configuration parameter, the following parameter are required in addition:

- ClientId: Client ID for authentication at the token endpoint.
- ClientSecret: Secret value for authentication at the token endpoint.
- TokenEndpoint: URL of the token endpoint.

Syntax: url=<application server URL>[;ClientId=<client ID>;ClientSecret=<secret>;TokenEndpoint=<token endpoint>]

Related topics

- [Setting up attestation in a separate database](#) on page 214
- [Requirements for the central database](#) on page 214
- [Setting up synchronization between central and work databases](#) on page 217
- [Setting up and running attestations in the work database](#) on page 218
- [Configuration parameters for attestation](#) on page 220

Setting up synchronization between central and work databases

Synchronization between the work and central databases is handled by the One Identity Manager connector. You can set up synchronization through individual configuration, configuring it completely manually. To ensure that all data required for attestation are transferred to the work database and the attestation results are returned, set up the system synchronization. The One Identity Manager supports you with the scripts provided.

System synchronization allows you to map selected application data from the central database to the work database. The synchronization configuration is generated completely automatically based on selected criteria. The synchronization project is set up on the work database.

To set up the system synchronization, proceed as described in the *One Identity Manager User Guide for the One Identity Manager Connector*.

To set up the system synchronization

1. Provide One Identity Manager users with the necessary permissions to set up synchronization.
2. Install and configure a synchronization server and declare the server as a Job server in One Identity Manager.
3. Determine which application data to attest.
 - a. In Designer, mark the tables and columns required for this purpose. You can use the scripts provided for this purpose.

NOTE: The scripts select all tables and columns that contain application data to attest. If only a limited section of this application data requires attesting, you can also mark the required tables and columns manually.
 - b. Check the automatically selected tables and columns. You can modify this selection to suit your requirements.
4. Generate a synchronization project with the Synchronization Editor.

When selecting the database system, use the same settings that are specified in the configuration parameters under **ISM | PrimaryDB | AppServer**.
5. Start the initial synchronization.

To automatically mark the tables and columns

Run the following scripts on the given database using a suitable program for SQL queries. The scripts are located on the installation media in the ATT\dvd\AddOn\SDK\SystemSyncPreConfig directory.

1. On the work database, run the AttestationInAnotherOneIMDB_Part1_GeneralConfig.sql script.

The script makes some general settings.

2. On the central database, run the `AttestationInAnotherOneIMDB_Part1_GeneralConfig.sql` script.
3. On the work database, run the `AttestationInAnotherOneIMDB_Part2_TableConfig.sql` script.

The script selects all the necessary tables and sets the values required in the table properties.

4. On the work database, run the `AttestationInAnotherOneIMDB_Part3_ColumnConfig.sql` script.

The script selects all required columns and sets the mapping direction.

5. Check the selected tables and columns as well as the set properties and adjust if necessary.

NOTE:

- If you change the tables or columns to be synchronized after the synchronization project has been generated, the synchronization project will be updated automatically.
- Only the connection credentials for the connected systems may be changed manually in a generated synchronization project.

Related topics

- [Setting up attestation in a separate database](#) on page 214
- [Requirements for the central database](#) on page 214
- [Setting up work databases](#) on page 215
- [Setting up and running attestations in the work database](#) on page 218

Setting up and running attestations in the work database

After you have initially loaded all the data into the work database, set up the attestation and then start it. For more information, see [Attestation and recertification](#) on page 10.

The status of completed attestation cases is stored in the attestation overview (`ISMObjectAttLast` table) and immediately provisioned to the central database. This is where subsequent processes are carried out, such as the withdrawal of entitlements after attestation is denied or risk index calculations.

NOTE: When attestations are carried out in a work database, the risk indexes of the attested objects in the central database are calculated based on the attestation overview (`ISMObjectAttLast` table). Separate calculation functions are provided for this purpose.

For more information about calculating risk indexes, see the *One Identity Manager Risk Assessment Administration Guide*.

Related topics

- [Setting up attestation in a separate database](#) on page 214
- [Requirements for the central database](#) on page 214
- [Setting up work databases](#) on page 215
- [Setting up synchronization between central and work databases](#) on page 217

Configuration parameters for attestation

The following configuration parameters are additionally available in One Identity Manager after the module has been installed. Some general configuration parameters are relevant for attestation. The following table contains a summary of all applicable configuration parameters for attestation.

Table 57: Overview of configuration parameters

Configuration parameter	Description
QER Attestation	Preprocessor relevant configuration parameter for controlling the model parts for attestation. Changes to the parameter require recompiling the database. If the parameter is enabled you can use the attestation function. If you disable the configuration parameter at a later date, model components and scripts that are no longer required, are disabled. SQL procedures and triggers are still carried out. For more information about the behavior of preprocessor relevant configuration parameters and conditional compiling, see the <i>One Identity Manager Configuration Guide</i> .
QER Attestation AERoleApproval	Application role certification is defined under this configuration parameter.
QER Attestation AERoleApproval InitialApprovalState	Certification status for new application roles. If an application role is added with the status 1 (NEW) , it triggers attestation of the data by their manager.
QER Attestation AllowAllReportTypes	This configuration parameter specifies whether all report formats are permitted for attestation policies. By default, only PDF is allowed because it is the only audit secure format.
QER Attestation	This configuration parameter specifies whether new

Configuration parameter	Description
ApproveNewExternalUsers	external users must be attested before they are enabled.
QER Attestation AutoCloseInactivePerson	If this configuration parameter is set, pending attestation cases for an identity are closed, when this identity is permanently deactivated.
QER Attestation AutoRemovalScope	General configuration parameter for defining automatic withdrawal of memberships/assignments if attestation approval is not granted.
QER Attestation AutoRemovalScope AERoleMembership	Determines default behavior for automatic removal of application role memberships if attestation approval is not granted.
QER Attestation AutoRemovalScope AERoleMembership RemoveDelegatedRole	If this configuration parameter is set, it ends the application role delegation if attestation approval is not granted.
QER Attestation AutoRemovalScope AERoleMembership RemoveDirectRole	If this configuration parameter is set, the identity's membership of the application role is removed if attestation approval is not granted. This removes all indirect assignments obtained by the identity through this application role!
QER Attestation AutoRemovalScope AERoleMembership RemoveRequestedRole	If this configuration parameter is set, requests for membership in the application role are either unsubscribed or canceled, depending on the setting of the QER Attestation AutoRemovalScope PWOMethodName configuration parameter, if attestation is denied. This removes all indirect assignments obtained by the identity through this application role!
QER Attestation AutoRemovalScope AERoleMembership RemoveDynamicRole	If this configuration parameter is set, the identity is excluded from the application role's dynamic role if attestation approval is not granted. This removes all indirect assignments obtained by the identity through this application role!
QER Attestation AutoRemovalScope DepartmentHasESet	Determines default behavior for automatic removal of system role assignments to departments if attestation approval has been denied.
QER Attestation AutoRemovalScope DepartmentHasESet	If this configuration parameter is set, system role to department assignments are removed if attestation approval is not granted.

Configuration parameter	Description
RemoveDirect	
QER Attestation AutoRemovalScope DepartmentHasESet RemoveRequested	If this configuration parameter is set, system role assignment requests to business roles are unsubscribed or canceled when attestation approval is denied. Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter.
QER Attestation AutoRemovalScope DepartmentHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to departments if attestation approval has been denied.
QER Attestation AutoRemovalScope DepartmentHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to department assignments are removed if attestation approval is not granted.
QER Attestation AutoRemovalScope ESetAssignment	Determines default behavior for automatic removal of system role memberships if attestation approval is not granted.
QER Attestation AutoRemovalScope ESetAssignment RemoveDelegatedRole	If this configuration parameter is set, it ends the role delegation through which the identity obtained the system role if attestation approval is not granted. This removes all indirect assignments obtained by the identity through this role!
QER Attestation AutoRemovalScope ESetAssignment RemoveDirect	If this configuration parameter is set, the direct user account membership in the system role will be removed if attestation approval is not granted. This removes all indirect assignments obtained by the identity through the system role.
QER Attestation AutoRemovalScope ESetAssignment RemoveDirectRole	If this configuration parameter is set, the secondary membership of the identity in the role (organization or business role) through which the identity obtained the system role is removed if attestation approval is not granted. This removes all indirect assignments obtained by the identity through this role!
QER Attestation AutoRemovalScope ESetAssignment RemoveDynamicRole	If this configuration parameter is set, the identity is excluded from the dynamic role through which the identity obtained the system role if attestation approval is not granted.

Configuration parameter	Description
	This removes all indirect assignments obtained by the identity through this role!
QER Attestation AutoRemovalScope ESetAssignment RemovePrimaryRole	<p>If this configuration parameter is set, the primary role assignment through which the identity obtained the system role is removed from the identity if attestation approval is not granted.</p> <p>This removes all indirect assignments obtained by the identity through this role!</p>
QER Attestation AutoRemovalScope ESetAssignment RemoveRequested	<p>If this configuration parameter is set, the requested system role is canceled if attestation approval is denied.</p> <p>If this configuration parameter is set, the system role request is unsubscribed or canceled if attestation approval is not granted. Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter.</p> <p>This removes all indirect assignments obtained by the identity through the system role.</p>
QER Attestation AutoRemovalScope ESetAssignment RemoveRequestedRole	<p>If this configuration parameter is set, requests for the role, through which the identity obtains the system role, are either unsubscribed or canceled if attestation is denied. Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter.</p> <p>This removes all indirect assignments obtained by the identity through this role!</p>
QER Attestation AutoRemovalScope ESetHasEntitlement	Determines default behavior for automatic removal of system role assignments after attestation approval has been denied.
QER Attestation AutoRemovalScope ESetHasEntitlement RemoveDirect	If this configuration parameter is set, company resource assignments to system roles are removed if attestation approval is denied.
QER Attestation AutoRemovalScope ESetHasEntitlement RemoveRequested	If this configuration parameter is set, assignment requests of company resources to system roles are unsubscribed or canceled if attestation approval is denied. Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter.

Configuration parameter	Description
QER Attestation AutoRemovalScope GroupMembership	Determines default behavior for automatic removal of united namespace system entitlements if attestation approval is not granted.
QER Attestation AutoRemovalScope GroupMembership RemoveDelegatedRole	If this configuration parameter is set, it ends the role delegation through which the identity obtained the system entitlement if attestation approval is not granted. This removes all indirect assignments obtained by the identity through this role!
QER Attestation AutoRemovalScope GroupMembership RemoveDirect	If this configuration parameter is set, the direct user account membership in the system entitlement will be removed if attestation approval is not granted.
QER Attestation AutoRemovalScope GroupMembership RemoveDirectRole	If this configuration parameter is set, secondary membership of the identity in the role (organization or business role) through which the identity obtained the system entitlement is removed if attestation approval is not granted. This removes all indirect assignments obtained by the identity through this role!
QER Attestation AutoRemovalScope GroupMembership RemoveDynamicRole	If this configuration parameter is set, the identity is excluded from the dynamic role through which the identity obtained the system entitlement if attestation approval is not granted. This removes all indirect assignments obtained by the identity through this role!
QER Attestation AutoRemovalScope GroupMembership RemovePrimaryRole	If this configuration parameter is set, the primary role assignment through which the identity obtained the system entitlement is removed from the identity if attestation approval is not granted. This removes all indirect assignments obtained by the identity through this role!
QER Attestation AutoRemovalScope GroupMembership RemoveRequested	If this configuration parameter is set, requests for system entitlements are unsubscribed or canceled if attestation is denied. Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter.
QER Attestation AutoRemovalScope GroupMembership	If this configuration parameter is set, requests for the role through which the identity obtained the system entitlement are either unsubscribed or

Configuration parameter	Description
RemoveRequestedRole	<p>canceled depending on the setting of the QER Attestation AutoRemovalScope PWOMethodName configuration parameter, if attestation is denied.</p> <p>This removes all indirect assignments obtained by the identity through this role!</p>
QER Attestation AutoRemovalScope GroupMembership RemoveSystemRole	<p>If this configuration parameter is set, the system role assignment through which the identity obtained the system entitlement is removed from the identity if attestation approval is not granted.</p> <p>This removes all indirect assignments obtained by the identity through this system role.</p> <p>NOTE: This configuration parameter is only available if the System Roles Module is installed.</p>
QER Attestation AutoRemovalScope LocalityHasESet	Determines default behavior for automatic removal of system role assignments to locations if attestation approval has been denied.
QER Attestation AutoRemovalScope LocalityHasESet RemoveDirect	If this configuration parameter is set, system role to location assignments are removed if attestation approval is not granted.
QER Attestation AutoRemovalScope LocalityHasESet RemoveRequested	If this configuration parameter is set, assignment requests of system roles to locations are unsubscribed if attestation approval is denied. Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter.
QER Attestation AutoRemovalScope LocalityHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to locations if attestation approval has been denied.
QER Attestation AutoRemovalScope LocalityHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to location assignments are removed if attestation approval is not granted.
QER Attestation AutoRemovalScope OrgHasESet	Determines default behavior for automatic removal of system role assignments to business roles if attestation approval has been denied.
QER Attestation AutoRemovalScope OrgHasESet RemoveDirect	If this configuration parameter is set, system role to business role assignments are removed if attestation approval is not granted.

Configuration parameter	Description
QER Attestation AutoRemovalScope OrgHasESet RemoveRequested	If this configuration parameter is set, assignment requests of system roles to cost centers are unsubscribed if attestation approval is denied. Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter.
QER Attestation AutoRemovalScope OrgHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to business roles if attestation approval has been denied.
QER Attestation AutoRemovalScope OrgHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to business role assignments are removed if attestation approval is not granted.
QER Attestation AutoRemovalScope ProfitCenterHasESet	Determines default behavior for automatic removal of system role assignments to system roles if attestation approval has been denied.
QER Attestation AutoRemovalScope ProfitCenterHasESet RemoveDirect	If this configuration parameter is set, system role to cost center assignments are removed if attestation approval is not granted.
QER Attestation AutoRemovalScope ProfitCenterHasESet RemoveRequested	If this configuration parameter is set, assignment requests of system roles to departments are unsubscribed if attestation approval is denied. Set the desired behavior in the QER Attestation AutoRemovalScope PWOMethodName configuration parameter.
QER Attestation AutoRemovalScope ProfitCenterHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to system roles if attestation approval has been denied.
QER Attestation AutoRemovalScope ProfitCenterHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to cost center assignments are removed if attestation approval is not granted.
QER Attestation AutoRemovalScope PWOMethodName	Method to be run on requests if the requested assignment is to be deleted if attestation approval is not granted. The requests can be unsubscribed (Unsubscribe) or canceled (Abort). If the configuration parameter is not set, the requests are canceled by default.
QER Attestation AutoRemovalScope	Determines default behavior for automatic removal of business role memberships if attestation

Configuration parameter	Description
RoleMembership	approval is not granted.
QER Attestation AutoRemovalScope RoleMembership RemoveDelegatedRole	<p>If this configuration parameter is set, it ends the business role delegation if attestation approval is not granted.</p> <p>This removes all indirect assignments the identity obtained through this business role.</p>
QER Attestation AutoRemovalScope RoleMembership RemoveDirectRole	<p>If this configuration parameter is set, the identity secondary membership in the business role will be removed if attestation approval is not granted.</p> <p>This removes all indirect assignments the identity obtained through this business role.</p>
QER Attestation AutoRemovalScope RoleMembership RemoveDynamicRole	<p>If this configuration parameter is set, the identity is excluded from the business role's dynamic role if attestation approval is not granted.</p> <p>This removes all indirect assignments the identity obtained through this business role.</p>
QER Attestation AutoRemovalScope RoleMembership RemoveRequestedRole	<p>If this configuration parameter is set, requests for membership in the business role are either unsubscribed or canceled, depending on the setting of the QER Attestation AutoRemovalScope PWOMethodName configuration parameter, if attestation is denied.</p> <p>This removes all indirect assignments the identity obtained through this business role.</p>
QER Attestation AutoRemovalScope UNSGroupInUNSGroup	Specifies the default behavior for removing assignments from system entitlements to system entitlement is attestation approval is not granted.
QER Attestation AutoRemovalScope UNSGroupInUNSGroup RemoveDirect	If this configuration parameter is set, the system entitlement assignment to a system entitlement is removed if attestation approval is not granted.
QER Attestation DefaultSenderAddress	<p>Sender's default email address for sending automatically generated notifications about attestation cases. Replace the default address with a valid email address.</p> <p>Syntax:</p> <p>sender@company.com</p> <p>Example:</p>

Configuration parameter	Description
	<p>noreply@company.com</p> <p>You can enter the sender's display name in addition to the email address. In this case, ensure that the email address is enclosed in chevrons (<>).</p> <p>Example:</p> <p>One Identity <noreply@company.com></p>
QER Attestation DepartmentApproval	Department certification is defined under this configuration parameter.
QER Attestation DepartmentApproval InitialApprovalState	Certification status for new departments. If a department is added with the status 1 (NEW) , it triggers attestation of the data by their manager.
QER Attestation LocalityApproval	Location certification is defined under this configuration parameter.
QER Attestation LocalityApproval InitialApprovalState	Certification status for new locations. If a location is added with the status 1 (NEW) , it triggers attestation of the data by their manager.
QER Attestation MailApproval Account	Name of the user account for authenticating the mailbox used for approval by mail.
QER Attestation MailApproval AppID	Exchange Online application ID for authentication with OAuth 2.0. If the value is not set, the Basic or the NTLM authentication method is used.
QER Attestation MailApproval DeleteMode	Specifies the way emails are deleted from the inbox.
QER Attestation MailApproval Domain	Domain of the user account for authenticating the mailbox used for approval by mail.
QER Attestation MailApproval ExchangeURI	URL of the Microsoft Exchange web service for accessing the mailbox. If this is not given, AutoDiscover mode is used to detect the URL.
QER Attestation MailApproval Inbox	Microsoft Exchange mailbox to which approvals by mail are sent.
QER Attestation MailApproval Password	Password of the user account for authenticating the mailbox used for approval by mail.
QER Attestation MailTemplateIds AnswerToApprover	This mail template is used to send a notification with an answer to a question from an approver.
QER Attestation MailTemplateIds	Mail template used for attestation by mail.

Configuration parameter	Description
AttestationApproval	
QER Attestation MailTemplateIdents InformAddingPerson	This mail template is used to notify approvers that an approval decision has been made for the step they added.
QER Attestation MailTemplateIdents InformDelegatingPerson	This mail template is used to notify approvers that an approval decision has been made for the step they delegated.
QER Attestation MailTemplateIdents NewExternalUserVerification	Mail template for sending a message with a verification link to a new external user.
QER Attestation MailTemplateIdents QueryFromApprover	This mail template is used to send a notification with a question from an approver to an identity.
QER Attestation MailTemplateIdents RequestApproverByCollection	This mail template is used for generating an email when there are pending attestation for an approver. If this configuration parameter is not set, a Mail template request or Mail template reminder can be entered for single approval steps. This template is then sent for each individual attestation case. If this configuration parameter is set, single mails are not sent.
QER Attestation NewExternalUserFinalTimeoutInHours	Number of hours given for new external users to register (default: 24 hrs).
QER Attestation NewExternalUserTimeoutInHours	Number of hours that the passcode and verification link for new external users are valid (default: 4 hrs).
QER Attestation OnWorkflowAssign	This configuration parameter specifies how pending attestation cases are handled when a new approval workflow is assigned to the approval policy.
QER Attestation OnWorkflowUpdate	This configuration parameter specifies how pending attestations are handled when the approval workflow is changed.
QER Attestation OrgApproval	Business role certification is defined under this configuration parameter.
QER Attestation OrgApproval InitialApprovalState	Certification status for new business roles. If a business role is added with the status 1 (NEW) , it triggers attestation of the data by their manager.
QER Attestation	This configuration parameter allows automatic

Configuration parameter	Description
PeerGroupAnalysis	approval of attestation cases by peer group analysis.
QER Attestation PeerGroupAnalysis ApprovalThreshold	This configuration parameter defines a threshold for peer group analysis between 0 and 1. The default value is 0.9.
QER Attestation PeerGroupAnalysis CheckCrossfunctionalAssignment	This configuration parameter specifies whether functional areas should be taken into account in peer group analysis. If the parameter is set, the attestation case is only approved if the identity linked to the attestation case and the attestation object belong to the same functional area.
QER Attestation PeerGroupAnalysis IncludeManager	This configuration parameter specifies whether identities can be added to the peer group who have the same manager as the identity linked to the attestation case.
QER Attestation PeerGroupAnalysis IncludePrimaryDepartment	This configuration parameter specifies whether identities can be added to the peer group who are primary members of the primary department of the identity linked to the attestation object.
QER Attestation PeerGroupAnalysis IncludeSecondaryDepartment	This configuration parameter specifies whether identities can be added to the peer group who are secondary members of the secondary department of the identity linked to the attestation object.
QER Attestation PersonToAttestNoDecide	This configuration parameter specifies whether identities to be attested are allowed to approve this attestation case. If the parameter is set, an attestation case cannot be approved by identities, which are contained in the attestation object (<code>AttestationCase.ObjectKeyBase</code>) or in the objects identifiers 1-3 (<code>AttestationCase.UID_ObjectKey1</code> , <code>ObjectKey2</code> or <code>ObjectKey3</code>). If the parameter is not set, these identities are allowed to make approval decisions for this attestation case.
QER Attestation PrepareAttestationTimeout	Number in hours given to generate new attestation cases (default: 48). If exceeded, the process is canceled.
QER Attestation ProfitCenterApproval	Cost center certification is defined under this configuration parameter.
QER Attestation ProfitCenterApproval	Certification status for new cost centers. If a cost center is added with the status 1 (NEW) , it triggers

Configuration parameter	Description
InitialApprovalState	attestation of the data by their manager.
QER Attestation Recommendation	Threshold values for approval recommendations are defined under this configuration parameter.
QER Attestation Recommendation ApprovalRateThreshold	This configuration parameter specifies the threshold for the approval rate. The approval rate determines the proportion of approvals for this attestation object in previous attestation runs that were decided with the same approval procedure. The lower the threshold, the more likely granting approval will be recommended.
QER Attestation Recommendation PeerGroupThreshold	This configuration parameter specifies the threshold for the peer group factor. The peer group factor determines the proportion of identities in the peer group that already own the system entitlement or membership to be attested. The lower the threshold, the more likely granting approval will be recommended.
QER Attestation Recommendation RiskIndexThreshold	This configuration parameter specifies the threshold for the risk index of the attestation object. The higher the threshold, the more likely granting approval will be recommended.
QER Attestation Recommendation UnusedDaysThreshold	The configuration parameter specifies the number of days after which a user account or system entitlement is considered to be unused. If a user account or a system entitlement is not used for a longer period of time, the recommendation is to deny attestation.
QER Attestation ReuseDecision	The configuration parameter specifies whether approval granted by an attester is passed on to all approval steps the attester can approve within an approval process. If the parameter is set, the current step is approved if an approval step is reached in the approval process for which an identity with approval authorization has already granted approval. If the parameter is not set, the attester must separately approve each step for which they have approval authorization.
QER Attestation ReducedApproverCalculation	This configuration parameter specifies, which approval steps are recalculated if modifications require attestors to be redetermined.
QER Attestation UserApproval	Supports attestation procedures for regularly

Configuration parameter	Description
	checking and confirming One Identity Manager users through their Manager.
QER Attestation UserApproval InitialApprovalState	Certification status for new identities. If an identity is added with the certification status 1 = new, data attestation by the identity's manager is started.
QER Attestation UseWorkingHoursDefinition	Specifies whether working days should be taken into account when calculating the due date of attestation cases according to the definition in the QBM WorkingHours configuration parameter.
QER CalculateRiskIndex	<p>Preprocessor relevant configuration parameter controlling system components for calculating the risk index. Changes to the parameter require recompiling the database.</p> <p>If the parameter is enabled, values for the risk index can be entered and calculated.</p> <p>If you disable the configuration parameter at a later date, model components and scripts that are no longer required, are disabled. SQL procedures and triggers are still carried out. For more information about the behavior of preprocessor relevant configuration parameters and conditional compiling, see the <i>One Identity Manager Configuration Guide</i>.</p>
QER Person Starling	<p>Specifies whether connecting to the One Identity Starling cloud platform is supported.</p> <p>Initiate your subscription within your One Identity on-prem product and join your on-prem solutions to our One Identity Starling cloud platform. Giving your organization immediate access to a number of cloud-delivered microservices, which expand the capabilities of your One Identity on-prem solutions. We will continuously make available new products and features to One Identity Starling. For a free trial of our One Identity Starling offerings and to get the latest product feature updates, visit cloud.oneidentity.com.</p>
QER Person Starling ApiEndpoint	Token endpoint for logging in to One Identity Starling The value is determined by the Starling configuration wizard.
QER Person Starling ApiKey	Authentication credentials for logging in to One Identity Starling The value is determined by the Starling configuration wizard.

Configuration parameter	Description
QER Person Starling UseApprovalAnywhere	This configuration parameter defines whether requests and attestation cases can be approved by adaptive cards.
QER Person Starling UseApprovalAnywhere SecondsToExpire	This configuration parameter specifies the time in seconds by which the adaptive card must be answered.
QER WebPortal BaseURL	API Server URL. This address is used in mail templates to add hyperlinks to the Web Portal.
QER WebPortal PasswordResetURL	URL of the API Server that deploys the Password Reset Portal. This web address is used for navigation.
Common MailNotification DefaultCulture	Default language used to send email notifications if a language cannot be determined for a recipient.
Common MailNotification Signature	Data for the signature in email automatically generated from mail templates.
Common MailNotification Signature Caption	Signature under the salutation.
Common MailNotification Signature Company	Company name.
Common MailNotification Signature Link	Link to the company's website.
Common MailNotification Signature LinkDisplay	Display text for the link to the company's website.
Common MailNotification SMTPAccount	User account name for authentication on an SMTP server.
Common MailNotification SMTPDomain	User account domain for authentication on the SMTP server.
Common MailNotification SMTPPassword	User account password for authentication on the SMTP server.
Common MailNotification SMTPPort	Port of the SMTP service on the SMTP server. Default: 25
Common MailNotification SMTPRelay	SMTP server for sending email notifications. If a server is not given, localhost is used.
Common MailNotification SMTPUseDefaultCredentials	Specifies which credentials are used for authentication on the SMTP server. If this parameter is set, the

Configuration parameter	Description
	<p>One Identity Manager Service login credentials are used for authentication on the SMTP server.</p> <p>If the configuration parameter is not set, the login data defined in the Common MailNotification SMTPDomain and Common MailNotification SMTPAccount or Common MailNotification SMTPPassword configuration parameters is used. (Default)</p>
Common ProcessState PropertyLog	<p>When this configuration parameter is set, changes to individual values are logged and shown in the process view. Changes to the parameter require recompiling the database.</p> <p>If you disable the configuration parameter at a later date, model components and scripts that are no longer required, are disabled. SQL procedures and triggers are still carried out. For more information about the behavior of preprocessor relevant configuration parameters and conditional compiling, see the <i>One Identity Manager Configuration Guide</i>.</p>
QBM WorkingHours IgnoreHoliday	<p>The configuration parameter specifies whether holidays are taken into account when calculating working hours. If the configuration parameter is set, holidays are not taken into account.</p>
QBM WorkingHours IgnoreWeekend	<p>The configuration parameter specifies whether weekends are included in the calculation of working hours. If the configuration parameter is set, holidays are not taken into account.</p>
ISM	<p>General configuration parameter for the system synchronization service module.</p>
ISM PrimaryDB	<p>Information about the central database located within the corporate infrastructure.</p>
ISM PrimaryDB AppServer	<p>Connection parameter for the central database's application server.</p>
ISM PrimaryDB AppServer AuthenticationString	<p>Authentication data for establishing a connection using the REST API of the central database's application server.</p> <p>Syntax: Module=<authentication module>;<property1>=<value1>;<property2>=<value2>,...</p> <p>All authentication modules provided by the</p>

Configuration parameter	Description
ISM PrimaryDB AppServer ConnectionString	<p>application server being addressed are allowed. For more information about authentication modules, see the <i>One Identity Manager Authorization and Authentication Guide</i>.</p> <p>Connection parameters for establishing a connection using the REST API of the central database's application server.</p> <p>Syntax: url=<application server URL> [;ClientId=<client ID>;ClientSecret=<secret>;TokenEndpoint=<token endpoint>]</p>

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales and other inquiries, such as licensing, support, and renewals, visit <https://www.oneidentity.com/company/contact-us.aspx>.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product

A

- adaptive card 166, 168
 - apply 170
 - attestation template 171
 - attestors 169
 - channel 169
 - create 170, 173
 - deactivate 173-174
 - delete 170
 - edit 170
 - evaluate 173
 - language 173
 - process ATT_AttestationHelper
 - approve anywhere 170
 - script 173
 - template 170, 173
- application role
 - attestation 204
 - attestation policy owner 32
 - chief approval team 32, 116
- approval 83
- approval by mail 163
- approval level 77
 - connect 83
- approval policies 38, 69
 - copy 72
 - default 71
 - user certification 193, 195
 - verify 71
- approval procedure 86
 - Active Directory group product owner and additional owner 99, 101
 - add 109
 - additional owner of the Active Directory group 103
 - application entitlement approver 104
 - application owner 104
 - approvals made externally 107
 - approver for attestation policy 105
 - attestation base object 114
 - attestation policy owner 105
 - attestor assigned service item 92
 - attestor of the attested company policy 88
 - attestor of the attested compliance rule 88
 - attestor of the attested role 88
 - attestor of the attested system entitlement or system role 92
 - attestor of the primary business role of the attested identity 91
 - attestor of the primary cost center of the attested identity 91
 - attestor of the primary department of the attested identity 90
 - attestor of the primary location of the attested identity 90
 - attestor of the role of the attested role assignment 88
 - business role manager of the identity to attest 95
 - calculated approval 106
 - challenge the approval decision 98
 - condition 111
 - copy 115

- cost center manager of identity to attest 95
- custom 109
- delete 116
- department manager for system entitlement attestation 94
- department manager of identity to attest 94
- department manager of linked identity 94
- escalation 137
- identity itself 98
- identity manager for system entitlement attestation 94
- identity of the user account to attest 99
- location manager of identity to attest 95
- manager of linked identity 94
- manager of the identity for all attestations 97
- manager of the identity to attest 93
- manager of the system role to attest 95
- members of a certain role 97
- overview form 115
- owner of a privileged object 103
- owner of service principals 104
- permitted for tables 114
- product owners 101
- proposed manager 93
- proposed owner 102
- query 111
- role manager for membership attestation 96
- role manager for role and role assignment attestation 96
- specific role Manager 97
- target system manager of the system entitlement to attest 99
- waiting for further approval 108
- approval process 69
 - publish 122
 - verify 122
- approval rate
 - attestation 130
- approval reason 34
- approval recommendation for attestors 129
 - configure 133
 - criteria 130
- approval step 77-78
 - edit 78
- approval workflow 72, 147
 - change 149
 - copy 83
 - default 85
 - delete 84
 - edit 76
 - overview form 84
 - user certification 193, 195
- approver
 - notification 160
 - select 86
- assignment rate
 - attestation 130
- attestation 10
 - application role 204
 - approval process test criteria 123
 - approval recommendation 129
 - approve automatically 120
 - business role 204
 - by peer group 126, 128
 - challenge 124

- cost center 204
- deactivate 68
- department 204
- identity 190
 - policy collection 59
- identity sample 189
- in separate database 214, 218
 - prepare 215
 - prerequisites 214
 - script 217
 - select tables and columns 217
 - synchronization set up 217
- in the Manager 175
- location 204
- new application role 210
- new business role 209
- new cost center 207
- new department 207
- new identity 193
- new location 208
- new user 193
 - approver 193, 195
 - customize 199
 - imported identity main data 198
 - prepare 195
 - prepare import 198
 - sequence 193, 195
 - start schedule 199
- object with policy violation 68
- organizations 204
- phase 121
- remove application role
 - automatically 188
- remove business role
 - automatically 188
- remove entitlement
 - automatically 125, 182
- remove system entitlement automatically 183
- remove system role
 - automatically 185
- sample 50
- sample for identities 55
- sample for system entitlements 54
- show object properties 176
- staging phase 122
- start 47, 145
 - for selected objects 145
- suspend 68
- user 190
- user certification
 - attestation policy 43
 - attestation procedure 22
 - with recommendation 129
- attestation by Starling Cloud Assistant 166, 168
- attestation case 145
 - additional attestors 136
 - approval sequence 147
 - approve 175
 - approve automatically 140
 - assign extended properties 177
 - attestation history 148
 - close attestations 145
 - closed 151
 - create 47, 145
 - delegate approval 136
 - delete 38, 57, 151
 - escalate 137
 - notification 153
 - overview form 147

- pending attestation 145
- processing time 147
- query 135
- quit 141
- record 151
- reject approval 136
- reroute approval 136
- show report 175-176
- show snapshot 176
- timeout 137, 140-141
- attestation object 38, 47-48
 - also attestor 119
 - show properties 176
- attestation policy
 - assign approver 44
 - assign compliance framework 45
 - assign mitigating control 46
 - assign policy collection 58
 - calculation schedule
 - assign 38
 - copy 48
 - create 37
 - create in Web Portal 181
 - deactivate 38, 49
 - default 43, 181
 - delete 49
 - edit 37
 - mitigating control 45
 - new user certification 193, 195, 198
 - customize 199
 - obsolete attestation cases 151
 - overview form 44
 - owner 38
 - processing time 38
 - report 38
 - risk index 38, 43
 - sample 38, 53
 - show condition 48
 - terms of use 36
- attestation policy owner 32
- attestation procedure
 - assign approval policy 23
 - default 22, 181
 - group 13
 - overview form 22
 - set up 15
 - snapshot 20
- attestation run 145
 - cancel incomplete 178
 - empty 38
 - no attestation case 38
 - show canceled 179
 - show incomplete 178
- attestation type 15
 - assign attestation procedure 15
 - default 14
 - overview form 14
- attestors 147
 - adaptive card 166, 168-169
 - approval acceptance 120
 - approval by email 163
 - approve own attestation case 119
 - attestation case 175
 - channel 169
 - notification 154, 156, 160-161
 - recalculate 116
 - restrict 119
 - select 86

B

- base object 15
 - mail template 61
- basic data 13
- Behavior Driven Governance 68
- business role
 - attestation 204

C

- calculation schedule 24
 - assign attestation policy 28
 - assign policy collection 28
 - default schedule 27
 - default schedule attestation check 24
 - new user certification 199
 - overview form 29
 - recertification 202
 - start immediately 30
- central database 214
 - application server set up 214
- certification
 - see attestation 190, 204
- certification status
 - application role 210
 - business role 209
 - cost center 207
 - department 207
 - identity 193
 - location 208
- chief approval team 32, 116
- compliance framework 30
 - assign attestation policy 31
 - manager 30

- overview form 31
- cost center
 - attestation 204
- cross-functional assignment
 - attestation 130
- cross-functional membership
 - attestation 130
- cross-functional product 126

D

- default attestation policy 181
- default attestation procedure 181
- default mail template 162
- default policy collection 59
- delegation
 - approval notification 158
- deny 83
- department
 - attestation 204

E

- email notification
 - set up 153
- escalation 83
 - notification 160
- extended property
 - attestation case 177

F

- fallback approver 139

I

identity

- attestation 190
- certification status 193
 - initial 195, 198
- certified 193, 201
- no inheritance 193, 201
- not set 193, 201
- set 193, 201

install Web Portal 215

L

location

- attestation 204

login

- verification link 162

M

mail template

- base object 61, 63
- hyperlink 64

mitigating control 211

- assign attestation policy 46, 212
- create 46
- log 211
- overview form 212
- significance reduction 211

Multi-factor authentication 118

N

notification

- additional attestors 161

- approval 157
- attestors 156
- default mail template 162
- deny 157
- deny approval 160
- escalation 160
- external user 162
- mail template 60, 153
- on delegation 158
- query 161
- quit 159
- recipient 153
- refuse approval 160
- reject approval 160
- reminder 154, 156
- request 154, 160
- sender 153
- verification link 162

O

organizations

- attest 204

P

peer group analysis

- for attestation 126
- for configuring attestation 128

peer group factor

- attestation 130

policy collection 55

- assign attestation policy 58
- calculation schedule 57
- change 56
- create 56

- deactivate 57-58
- default 59
- delete 59
- owner 57
- sample 57
- policy violation
 - attest 68
 - recertification 68
- product
 - cross-functional 126

R

- reason 34
- recertification 10, 190
 - attestation policy
 - customize 203
 - calculation schedule 202
 - customize 203
 - identity 201
 - object with policy violation 68
 - prepare 202
 - sequence 202
 - user 201
- report 15
 - create 20
 - default 20
- reroute 83
- risk assessment
 - attestation policy 43
- risk factor
 - attestation 130
- risk index
 - calculate 213
 - reduced
 - calculate 213

S

- sample
 - assign attestation policy 38, 53
 - assign element 52
 - assign policy collection 57
 - attestation 50
 - automatic 52
 - create 50
 - delete 50
 - edit 50
 - manual 51-52
 - overview form 54
 - table 51
- sample item 51-52
- sampling data 51
 - delete 51-52, 54
 - display 52
 - generate 52
- scheduled 145
- significance reduction 211
- snapshot
 - attestation 20
 - object reference 20
- standard reason 34
 - usage type 35
- Starling Cloud Assistant
 - attestors 169
 - channel 169
- system synchronization 217

T

- terms of use 36
 - overview form 37

PDF file 36
timeout 83

U

user certification
 approval policies 71
 approval workflow 85
 calculation schedule 27

W

work database 215
Workflow Editor
 open 72