



One Identity Authentication Services
4.1.3

Installation Guide

Copyright 2017 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC .

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity make no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity do not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.

Attn: LEGAL Dept

4 Polaris Way

Aliso Viejo, CA 92656

Refer to our Web site (<http://www.OneIdentity.com>) for regional and international office information.




Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal. All other trademarks are the property of their respective owners.

Legend

-  **WARNING:** A WARNING icon indicates a potential for property damage, personal injury, or death.
-  **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.
-  **IMPORTANT, NOTE, TIP, MOBILE, or VIDEO:** An information icon indicates supporting information.

Authentication Services Installation Guide

Updated - September 2017

Version - 4.1.3

Contents

Privileged Access Suite for Unix	7
About this guide	8
Introducing One Identity Authentication Services	10
Licensing Authentication Services	10
System requirements	10
Windows management tools requirements	11
Authentication Services Windows components	12
Windows permissions	12
Unix agent requirements	13
Authentication Services Unix components	14
Authentication Services permissions matrix	15
Authentication Services encryption types	19
Management Console for Unix requirements	20
Network requirements	22
Installing and configuring Authentication Services	23
Install the management console	23
Installing and configuring the management console	24
Install Authentication Services Windows components	25
Installing Authentication Services Windows components	25
Customize installation options	25
Installation using msixexec.exe	26
Configure Active Directory for Authentication Services	29
Configuring Active Directory for Authentication Services	29
About Active Directory configuration	31
Join the host to AD without the Authentication Services application configuration	32
Version 3 compatibility mode	33
Configure Unix agent components	34
Setup Management Console for Unix	35
Configure the console for Active Directory logon	35
Setup console access by role	36
Identify Console	36

Set Supervisor Password dialog	37
Summary dialog	37
Management Console for Unix log on page	37
Prepare Unix hosts	38
Add hosts to the management console	39
Profile hosts	40
Install software on hosts	44
Check readiness	46
Join hosts to Active Directory	46
Check QAS agent status	47
Installing and joining from the Unix command line	51
The Authentication Services pre-installation diagnostic tool	51
Running preflight	53
The Authentication Services install script	53
Installing the Authentication Services agent	54
Installation script options	54
Licensing Authentication Services	56
Verifying Authentication Services license information	57
Installing licenses from the command line	57
Creating the application configuration from the Unix command line	58
Changing the schema configuration mode	58
Joining the domain	59
Joining the domain using VASTOOL	59
Joining the domain using VASJOIN script	60
Dynamic DNS update tool	61
Getting started with Authentication Services	63
Getting acquainted with the Control Center	63
Management console	64
Group Policy	65
Filter options	65
Edit GPO	65
Settings report	65
Show Files	66
Launch GPMC	66

Tools	66
Preferences	67
Licensing	67
Global Unix Options	68
Logging options	69
Custom Unix attributes	70
Learning the basics	73
Add a local group	73
Add local user account	74
Add an Active Directory group account	74
Add an Active Directory user account	75
Change the default Unix attributes	75
Active Directory account administration	76
Enable local user for AD authentication	76
Test the mapped user login	77
Unix-enable an Active Directory group	78
Unix-enable an Active Directory user	78
Test the Active Directory user login	79
Run reports	79
Reports	81
Use Authentication Services PowerShell	92
Unix-enable a user and user group	92
PowerShell cmdlets	94
Change Auditor for Authentication Services	96
Install Change Auditor for Authentication Services	97
One Identity Defender	97
Install Defender	97
Troubleshooting	99
Getting help from technical support	99
Disaster recovery	100
Long startup delays on Windows	100
Pointer Record updates are rejected	100
Resolving DNS problems	101
Resolving preflight failures	101
System optimization	105

Time synchronization problems	105
Unable to install or upgrade	106
Unable to join the domain	106
Unable to log in	107
vasypd has unsatisfied dependencies	107
Enterprise package deployment	109
Install the Authentication Services agent package	109
Authentication Services agent upgrade commands	111
Restarting Authentication Services services	114
Uninstall the Authentication Services agent packages	115
Solaris 10 zones/containers support	116
Authentication Services and Solaris 10 Zones installation guidelines	116
About us	118
Contacting us	118
Technical support resources	118
Index	119

Privileged Access Suite for Unix

Unix Security Simplified

Privileged Access Suite for Unix solves the inherent security and administration issues of Unix-based systems (including Linux and Mac OS X) while making satisfying compliance requirements a breeze. It unifies and consolidates identities, assigns individual accountability and enables centralized reporting for user and administrator access to Unix. The Privileged Access Suite for Unix is a one-stop shop for Unix security that combines an Active Directory bridge and root delegation solutions under a unified console that grants organizations centralized visibility and streamlined administration of identities and access rights across their entire Unix environment.

Active Directory Bridge

Achieve unified access control, authentication, authorization and identity administration for Unix, Linux, and Mac OS X systems by extending them into Active Directory (AD) and taking advantage of AD's inherent benefits. Patented technology allows non-Windows resources to become part of the AD trusted realm, and extends AD's security, compliance and Kerberos-based authentication capabilities to Unix, Linux, and Mac OS X. (See www.oneidentity.com/products/authentication-services/ for more information about the Active Directory Bridge product.)

Root Delegation

The Privileged Access Suite for Unix offers two different approaches to delegating the Unix root account. The suite either *enhances* or *replaces* sudo, depending on your needs.

- By choosing to enhance sudo, you will keep everything you know and love about sudo while enhancing it with features like a central sudo policy server, centralized keystroke logs, a sudo event log, and compliance reports for who can do what with Sudo.

(See www.oneidentity.com/products/privilege-manager-for-sudo/ for more information about enhancing sudo.)

- By choosing to replace sudo, you will still be able to delegate the Unix root privilege based on centralized policy reporting on access rights, but with a more granular permission and the ability to log keystrokes on all activities from the time a user logs

in, not just the commands that are prefixed with "sudo". In addition, this option implements several additional security features like restricted shells, remote host command execution, and hardened binaries that remove the ability to escape out of commands and gain undetected elevated access.

(See www.oneidentity.com/products/privilege-manager-for-unix/ for more information about replacing sudo.)

Privileged Access Suite for Unix

Privileged Access Suite for Unix offers two editions - *Standard* edition and *Advanced* edition. Both editions include: **Management Console for Unix**, a common management console that provides a consolidated view and centralized point of management for local Unix users and groups; and, **Authentication Services**, patented technology that enables organizations to extend the security and compliance of Active Directory to Unix, Linux, and Mac OS X platforms and enterprise applications. In addition

- The *Standard* edition licenses you for Privilege Manager for Sudo.
- The *Advanced* edition licenses you for Privilege Manager for Unix.

One Identity recommends that you follow these steps:

1. Install Authentication Services on one machine, so you can set up your Active Directory Forest.
2. Install Management Console for Unix, so you can perform all the other installation steps from the management console.
3. Add and profile host(s) using the management console.
4. Configure the console to use Active Directory.
5. Deploy client software to remote hosts.

Depending on which Privileged Access Suite for Unix edition you have purchased, deploy either:

- **Privilege Manager for Unix** software (that is, Privilege Manager Agent packages)
- OR-
- **Privilege Manager for Sudo** software (that is, Sudo Plugin packages)

About this guide

The *Authentication Services Installation Guide* is intended for Windows, Unix*, Linux and Macintosh system administrators, network administrators, consultants, analysts, and any other IT professionals who will be installing and configuring Authentication Services for the first time. This guide walks you through the process of installing, upgrading, and uninstalling the Authentication Services agent.

NOTE: The term "Unix" is used informally throughout the Authentication Services documentation to denote any operating system that closely resembles the trademarked system, UNIX.

Introducing One Identity Authentication Services

One Identity Authentication Services is patented technology that enables organizations to extend the security and compliance of Active Directory to Unix, Linux, and Mac OS X platforms and enterprise applications. It addresses the compliance need for cross-platform access control, the operational need for centralized authentication and single sign-on, and enables the unification of identities and directories for simplified identity and access management.

Licensing Authentication Services

Authentication Services must be licensed in order for Active Directory users to authenticate on Unix and Mac OS X hosts.

- NOTE:** While you can install and configure Authentication Services on Windows and use the included management tools to Unix-enable users and groups in Active Directory without installing a license, you must have the Authentication Services license installed for full functionality.

Contact your account representative for a license.

System requirements

Prior to installing Authentication Services, ensure your system meets the minimum hardware and software requirements for your platform. Authentication Services consists of Windows management tools and Unix client agent components.

Windows management tools requirements

The following are the minimum requirements for installing Authentication Services in your Windows environment:

Table 1: Authentication Services Windows requirements

System Requirements:

Supported Windows Platforms	<p>You can install Authentication Services on 32-bit or 64-bit editions of the following configurations:</p> <ul style="list-style-type: none">• Windows XP SP2 (or later)• Windows Vista• Windows 7• Windows 8• Windows Server 2003 SP1 (or later)• Windows Server 2008• Windows Server 2008 R2• Windows Server 2012 <p>NOTE: Due to tightened security, when running Authentication Services Control Center on Windows 2008 R2 (or higher) operating system, functioning as a domain controller, the process must be elevated or you must add authenticated users to the Distributed COM Users group on the computer. As a best practice, One Identity does not recommend that you install or run the Authentication Services Windows components on Active Directory domain controllers. The recommended configuration is to install the Authentication Services Windows components on an administrative workstation.</p>
Prerequisite Windows Software	<p>You can download all of the following prerequisite software free from the Microsoft website:</p> <ul style="list-style-type: none">• Windows Installer 3.1 (http://support.microsoft.com/kb/893803)• Microsoft .NET Framework 3.5 SP1 or higher• Windows PowerShell 1.0 or higher (http://support.microsoft.com/kb/968929) <p>If any of the prerequisites are missing, the Authentication Services installer suspends the installation process to allow you to download the required component; it then continues the install.</p>

Authentication Services Windows components

Authentication Services includes the following Windows components:

Table 2: Windows components

Windows Component	Description
Authentication Services Control Center	A single console for access to all of the tools and configuration settings for Authentication Services.
Active Directory Users and Computers MMC Snapin Extensions	Unix management extensions for Active Directory users and groups.
Group Policy Management Editor MMC Snapin Extensions	Group Policy extensions for management of Unix, Linux and Mac OS X.
RFC2307 NIS Map Editor MMC Snapin	Provides the ability to manage NIS data in Active Directory.
NIS Map Import Wizard	Imports NIS data into Active Directory.
Unix Account Import Wizard	Imports Unix identity data into Active Directory.
Authentication Services Power-Shell cmdlets	Provides the ability to script Unix management tasks.
Documentation	Full product documentation and online help.

Windows permissions

To install Authentication Services on Windows, you must have:

- Local administrator rights
- Rights to create and delete all child objects in the container where you will install the configuration settings (first-time only)

Authenticated Users must have rights to read *cn*, *displayName*, *description*, and *whenCreated* attributes for container objects in the application configuration location. To change Active Directory configuration settings, Administrators must have rights to Create Child Object (container) and Write Attribute for *cn*, *displayName*, *description*, *showInAdvancedViewOnly* in the application configuration location.

Table 3: Required Windows permissions

Rights Required	For User	Object Class	Attributes
Create	Authentication Services	Container	

Rights Required	For User	Object Class	Attributes
Child Object	Administrators Only		
Delete Child Object	Authentication Services Administrators Only	Container	
Delete Child Object	Authentication Services Administrators Only	Container	
Write Attribute	Authentication Services Administrators Only	Container	cn, displayName, description, showInAdvancedViewOnly
Read Attribute	Authenticated Users	Container	cn, displayName, description, whenCreated

Unix agent requirements

NOTE: To install Authentication Services on Unix, Linux, or Mac OS X, you must have root access rights.

Click www.oneidentity.com/products/authentication-services/ to view a list of supported Unix and Linux platforms for Authentication Services 4.1.

With Authentication Services 4.1, Linux platforms require glibc 2.4 or greater.

For maximum security and performance, before you begin the installation, make sure that you have the latest patches for your operating system version.

Table 4: Patch level requirements

Platform	Patch Level
Solaris 8 SPARC	108993-55 or greater
Solaris 8 X86	108994-01 or greater
Solaris 9 SPARC	112874-37 or greater 112960-14 or greater 113319-22 or greater
Solaris 9 X86	114432-37 or greater
Solaris 10 SPARC	127127-11 or greater
Solaris 10 x86	127128-11 or greater

Platform	Patch Level
AIX 5.3	OS level 5300-05 or greater
AIX 6.1	OS level 5300-05 or greater
AIX 7.1	OS level 5300-05 or greater
HPUX 11.11	GOLDQPK11i - GOLDBASE11i GOLDAPPS11i quality packs BUNDLE11i - Patch bundle linker tools cumulative patch (PHSS_30970 or greater)
HPUX 11.23	MAINTPACK E0306 or greater

NOTE: One Identity recommends that you run the Preflight utility to check for supported operating system and correct operating system patches.
(For more information, see [Running preflight on page 53.](#))

Authentication Services Unix components

Authentication Services includes the following Unix components:

Table 5: Authentication Services Unix components

Unix Component	Description
vasd	The Authentication Services agent background process that manages the persistent cache of Active Directory information used by the other Authentication Services components. vasd is installed as a system service. You can start and stop vasd using the standard service start/stop mechanism for your platform. vasd is installed by the vasclnt package.
vastool	The Authentication Services command line administration utility that allows you to join a Unix host to an Active Directory Domain; access and modify information about users, groups and computers in Active Directory; and configure the Authentication Services components. vastool is installed at /opt/quest/bin/vastool. vastool is installed by the vasclnt package.
vgptool	A command line utility that allows you to manage the application of Group Policy settings to Authentication Services clients. vgptool is installed at /opt/quest/bin/vgptool. vgptool is installed by the vasgp package.
oat (Ownership Alignment Tool)	A command line utility that allows you to modify file ownership on local Unix hosts to match user accounts in Active Directory. oat is installed at /opt/quest/libexec/oat/oat. oat is installed by the vasclnt package.

Unix Component	Description
LDAP proxy	A background process that secures the authentication channel for applications using LDAP bind to authenticate users without introducing the overhead of configuring secure LDAP (LDAPS). The LDAP proxy is installed by the vasproxy package.
NIS proxy	A background process that acts as a NIS server which can provide backwards compatibility with existing NIS infrastructure. The NIS proxy is installed by the vasyp package.
SDK package	The vasdev package, the Authentication Services programming API.

Authentication Services permissions matrix

The following table details the permissions required for full Authentication Services functionality.

Table 6: Authentication Services: Required permissions

Function	Active Directory Permissions	Local Client Permissions
Authentication Services Application Configuration: creation	Location in Active Directory with Create Container Object rights	NA
Authentication Services Application Configuration: changes <ul style="list-style-type: none"> • Unix Global Settings • Licensing • Custom Unix Attributes 	Update permission to the containers created above (no particular permissions if you are the one who created it)	NA
Schema optimization	Schema Administrator rights	NA
Display Specifier Registration	Enterprise Administrator rights	NA
Editing Users	Administrator rights	NA

Function	Active Directory Permissions	Local Client Permissions
Create any group policy objects	Group Policy Creator Owners rights	NA
RFC 2307 NIS Import Map Wizard	Location in Active Directory with Create Container Object rights (you create containers for each NIS map)	NA
Unix Account Import Wizard	Administrator rights (you are creating new accounts)	NA
Logging Options	Write permissions to the file system folder where you want to create the logs	NA
vasd daemon	The client computer object is expected to have read access to user and group attributes, which is the default. In order for Authentication Services to update the host object operating system attributes automatically, set the following rights for "SELF" on the client computer object: Write Operating System , Write operatingSystemHotfix , and Write operatingSystemServicePack .	vasd must run as root
QAS/VAS PAM module	NA (updated by means of vasd)	Any local user
QAS/VAS NSS module vastool nss	NA (updated by means of vasd)	Any local user
vastool command-line tool	Depends on which vastool command is run	Any local user for most commands
vastool join vastool unjoin	computer creation or deletion permissions in the desired container	root
vastool configure vastool unconfigure	NA	root
vastool search vastool attrs	read permission for the desired objects (regular Active Directory user)	Any local user
vastool setattrs	write permissions for the desired object	Any local user

Function	Active Directory Permissions	Local Client Permissions
vastool cache	NA	Run as root if you want all tables including authcache
vastool create	permissions to create new users, groups, and computers as specified	Any local user; root needed to create a new local computer
vastool delete	permissions to delete existing users, groups, or computers as specified; permissions to remove the keytab entry for the host object created (root or write permissions in the directory and the file)	Any local user
vastool flush	The client computer object is expected to have read access to user and group attributes, which should be the default	root
vastool group add vastool group del	permission to modify group membership	Any local user
vastool group hasmember	read permission for the desired objects (regular Active Directory user)	Any local user
vastool info { site domain domain -n forest-root forest-root -dn server acl }	NA	Any local user
vastool info { id domains domains -dn adsecurity toconf }	read permission for the desired objects (regular Active Directory user)	Any local user
vastool isvas vastool inspect vastool license	NA	Any local user

Function	Active Directory Permissions	Local Client Permissions
vastool kinit vastool klist vastool kdestroy	local client needs permissions to modify the keytab specified, default is the computer object which is root.	Any local user
vastool ktutil	NA	root if you are using the default host.keytab file
vastool list (with -l option)	read permission for the desired objects (regular Active Directory user)	Any local user
vastool load	permissions to create users and groups in the desired container	Any local user
vastool merge vastool unmerge	NA	root
vastool passwd	Regular Active Directory user	Any local user
vastool passwd <AD user>	Active Directory user with password reset permission	Any local user
vastool schema list vastool schema detect	Regular Active Directory user	Any local user
vastool schema cache	Regular Active Directory user	root (to modify the local cache file)
vastool service list	Regular Active Directory user	Any local user
vastool service { create delete }	Active Directory user with permission to create/delete service principals in desired container	NA
vastool smartcard	NA	root
vastool status	NA	root
vastool timesync	NA	root, if you

Function	Active Directory Permissions	Local Client Permissions
		only query the time from AD, you can run as any local user
vastool user { enable disable }	modify permissions on the AD Object	Any local user
vastool user { checkaccess checkconflict }	NA	Any local user
vastool user checklogin	Access to Active Directory users password	Any local user

Authentication Services encryption types

The following table details the encryption types used in Authentication Services.

Table 7: Authentication Services: Encryption types

Encryption Types	Specification	Active Directory Version	Authentication Services Version
KERB_ENCTYPE_DES_CBC_CRC			
CRC32	RFC 3961	All	All
KERB_ENCTYPE_DES_CBC_MD5			
RSA-MD5	RFC 3961	All	All
KERB_ENCTYPE_RC4_HMAC_MD5			
RC4-HMAC-MD5	RFC 4757	All	All
KERB_ENCTYPE_AES128_CTS_HMAC_SHA1_96			
HMAC-SHA1-96-AES128	RFC 3961	Windows Server 2008 +	3.3.2+
KERB_ENCTYPE_AES256_CTS_HMAC_SHA1_96			
HMAC-SHA1-96-AES256	RFC 3961	Windows Server 2008 +	3.3.2+

Management Console for Unix requirements

One Identity recommends that you install One Identity Management Console for Unix, a separate One Identity product which provides a management console that is a powerful and easy-to-use tool that dramatically simplifies deployment of Authentication Services agents to your clients. The management console streamlines the overall management of your Unix, Linux, and Mac OS X hosts by enabling centralized management of local Unix users and groups and providing granular reports on key data and attributes.

Prior to installing Management Console for Unix, ensure your system meets the minimum hardware and software requirements for your platform.

Table 8: Management Console for Unix: Hardware and software requirements

Component	Requirements
Supported Windows Platforms	<p>Can be installed on 32-bit or 64-bit editions of the following configurations:</p> <ul style="list-style-type: none">• Windows XP SP2 (or later)• Windows Vista• Windows 7• Windows 8• Windows Server 2003 SP1 (or later)• Windows Server 2008• Windows Server 2008 R2• Windows Server 2012 <p>i NOTE: When running Management Console for Unix on Windows Server 2008 R2, functioning as a domain controller, the process must be elevated. As a best practice, One Identity does not recommend that you install or run the Windows components on Active Directory domain controllers. The recommended configuration is to install them on an administrative workstation.</p> <p>i NOTE: The performance of some Active Directory searches may be better on:</p> <ul style="list-style-type: none">• 64bit: Windows Server 2003 64-bit and above• 32bit: Windows Server 2003 SP1 + hotfix* or Windows 2003 SP2 (and above) <p>(*Click Microsoft Support to read a Microsoft article entitled, "A hotfix is available that improves the performance of programs that query Active Directory for group memberships in Windows Server 2003".</p>

Component Requirements

	<p>To apply this hotfix, you must have Windows Server 2003 Service Pack 1 (SP1) installed. Note: The x64-based versions of Windows Server 2003 already include the fixes and features that are included in Windows Server 2003 SP1. If the computer is running an x64-based version of Windows Server 2003, you do not have to install SP1.</p>
Server Requirements	<p>You can install Management Console for Unix on any platform that has 32-bit Sun JRE (Java Runtime Environment) 1.6.</p> <p>i NOTE: Management Console for Unix is not supported on AIX.</p>
Managed Host Requirements	<p>Click here to view a list of supported Unix, Linux, and Mac OS X platforms that the server can manage; that is, hosts you can add and profile from the management console.</p> <p>i NOTE: To use Authentication Services with the management console on a Solaris 10 Sparc, you must have Authentication Services 4.0.3.152 or greater.</p> <p>i NOTE: To enable the Management Console for Unix server to interact with the host, you must install both an SSH server (that is, sshd) and an SSH client on each managed host. Both OpenSSH 2.5 (and higher) and Tectia SSH 5.0 (and higher) are supported.</p>
Default memory requirement:	<p>1024 MB</p> <p>i NOTE: See <i>Tune JVM Memory</i> in online help for information about changing the default memory allocation setting in the configuration file.</p>
Supported Web Browsers	<p>The management console officially supports the following web browsers:</p> <ul style="list-style-type: none">• Microsoft Internet Explorer 7, 8, 9, and 10• Mozilla Firefox 3 and greater• Apple Safari 4 (Mac OS X only; Windows not supported) <p>i NOTE: To use specific features such as the SSH to Host feature or the Policy Editors, you must install the Sun JRE (Java Runtime Environment) 1.6 browser plugin.</p> <p>i NOTE: One Identity recommends that you do not open two sessions of the management console in the same browser.</p> <p>i NOTE: One Identity recommends that set your screen resolution to a minimum of 1024 x 768 for the best results.</p>

Network requirements

Authentication Services must be able to communicate with Active Directory including domain controllers, global catalogs and DNS servers using Kerberos, LDAP and DNS protocols. The following table summarizes the network ports that must be open and their function.

Table 9: Network ports

Port	Function
389	Used for LDAP searches against Active Directory Domain Controllers. TCP is normally used, but UDP is used when detecting the Active Directory site membership.
3268	Used for LDAP searches against Active Directory Global Catalogs. TCP is always used when searching against the Global Catalog.
88	Used for Kerberos authentication and Kerberos service ticket requests against Active Directory Domain Controllers. TCP is used by default.
464	Used for changing and setting passwords against Active Directory using the Kerberos change password protocol. Authentication Services always uses TCP for password operations.
53	Used for DNS. Since Authentication Services uses DNS to locate domain controllers, DNS servers used by the Unix hosts must serve Active Directory DNS SRV records. Both UDP and TCP are used.
123	UDP only. Used for time-synchronization with Active Directory.
445	CIFS port used to enable the client to retrieve configured group policy.

NOTE: Authentication Services, by default, operates as a client, initiating connections. It does not require any firewall exceptions for incoming traffic.

Installing and configuring Authentication Services

To extend the authentication, authorization, and administration infrastructure of Active Directory to the rest of your enterprise, allowing Unix, Linux, and Mac OS X systems to act as full citizens within Active Directory, you must install and configure Authentication Services.

This section explains the steps you must take in detail:

1. Install Management Console for Unix.
2. Install Authentication Services Windows components.
3. Configure Active Directory for Authentication Services (one time, only).
4. Configure Unix Agent Components
 - a. Configure the management console for Active Directory.
 - b. Prepare the Unix hosts for Active Directory user access:
 - Add and profile a host.
 - Check the host for readiness to join Active Directory.
 - Install Authentication Services agent software packages on the host to allow Active Directory user access.
 - **NOTE:** For users to authenticate on Unix, Linux, and Mac OS X hosts with Active Directory credentials, your Unix hosts must have the Authentication Services agent installed.
 - Join the host to Active Directory.

Install the management console

In preparing for your Authentication Services installation, One Identity recommends that you install Management Console for Unix. This provides a management console that is a powerful and easy-to-use tool that dramatically simplifies deployment, enables management of local Unix users and groups, provides granular reports on key data and

attributes, and streamlines the overall management of your Unix, Linux, and Mac OS X hosts.

You can install the management console on Windows, Unix, or Mac OS X computers. Each hosting platform prompts for similar information.

The following install files are located on the Authentication Services distribution media under `mcu | server`:

- `ManagementConsoleForUnix_unix_2_n.n.sh` - for Unix
- `ManagementConsoleForUnix_windows_2_n.n.exe` - for Windows
- `ManagementConsoleForUnix_macos_2_n.n.dmg` - for Mac OS X

where "n.n" indicates the product version number.

The *Management Console for Unix Administrator's Guide* contains detailed instructions for installing the management console on all of these platforms. Use the following procedure to install the console on a supported Windows platform from the Authentication Services 4.1 distribution media.

Of course, you can install Authentication Services without using Management Console for Unix. If you wish to do that, skip these instructions and go to: [Installing and joining from the Unix command line on page 51](#).

Installing and configuring the management console

The easiest way to install and configure Authentication Services Unix agent components is by means of Management Console for Unix.

- NOTE:** The procedures in this topic assume you do not have Management Console for Unix already installed.

To install the management console on a supported Windows platform

1. Mount the Authentication Services 4.1 distribution media.

Autorun starts automatically.

- NOTE:** To start the Autorun installation wizard, you can also navigate to the root of the distribution media and double-click **autorun** Application file.

2. From the Authentication Services Autorun *Home* page, click the **Setup** tab.
3. From the Setup tab, click **Management Console for Unix**.

The install wizard guides you through the rest of the setup dialogs:

- Management Console for Unix License Agreement
- Configure TCP/IP Port
- Completing the Management Console for Unix installation

4. On the Complete dialog, clear the **Launch the Management Console** option and click **Finish** to exit the install wizard and return to the Authentication Services Autorun Setup tab.

Once you have installed Management Console for Unix, you are ready to install or upgrade the Authentication Services Windows components.

Install Authentication Services Windows components

One Identity recommends that you install the Windows components and configure Active Directory before you install the Unix components.

Installing Authentication Services Windows components

Install Authentication Services on each Windows Workstation you plan to use to administer Unix data in Active Directory.

To install the Authentication Services Windows components

1. From the Autorun Setup tab, click **Authentication Services** to launch the setup wizard.
2. At the Software License Agreement dialog, accept the terms of the End User License Agreement and click **Install**.

The Authentication Services Setup wizard installs all Authentication Services components by default.

To only install specific components, click the **Customize installation options** link. (For more information, see [Customize installation options on page 25.](#))

3. Once the installation completes successfully, click **Finish** or **Launch Control Center**.

Customize installation options

To install specific Authentication Services Windows components

1. From the Software License Agreement dialog, click the **Customize installation options** link.

2. On the Installation Options dialog, select the components and options you want to install and click **OK**.

Available components:

- Core Components (required)
- ADUC Extensions
- Group Policy Extensions
- Documentation
- Authentication Services Control Center

Available options:

- Install Start Menu Shortcuts
- Install Desktop Shortcuts

NOTE: You must install the Core Components.

3. To add other Authentication Services components later or modify the current installation of Authentication Services, run the setup wizard again.

From the root of the distribution media, double-click the autorun application.

Installation using `msiexec.exe`

You can install specific Authentication Services components from the Windows command line using `Msiexec.exe`, the Microsoft Windows Installer program, which processes product installation files in the `.MSI` format. You can either double-click the individual Authentication Services component `.msi` files or you can run `msiexec.exe` to install, modify, and perform other operations from the Windows command line.

The individual Authentication Services component `.msi` files, located on the distribution media in the `windows` folder, are:

- `aducX64.msi` - Installs the Active Directory Users and Computers Unix extensions for user and group management on a Windows 64-bit platforms
- `aducX86.mis` - Installs the Active Directory Users and Computers Unix extensions for user and group management on a Windows 32-bit platforms
- `cc.msi` - Installs the Control Center extension
- `corX64.msi` - Installs the core packages on a Windows 64-bit platform.
- `coreX86.msi` - Installs the core packages on a Windows 32-bit platform.
- `doc.msi` - Installs the User Documentation
- `GpSettingsX86` - Installs the Authentication Services Group Policy settings reporting library used by third parties such as Change Auditor and Group Policy Manager to report on Group Policy settings.
- `gpX64.msi` - Installs the Group Policy extension on a Windows 64-bit platforms
- `gpX86.msi` - Installs the Group Policy extension on a Windows 32-bit platforms

You can use the following properties on the command line when installing the individual Authentication Services components:

Table 10: MSI properties

MSI Property	Description
INSTALLFOLDER	Specifies the directory where you want to install the package. (Core X86 only.) Default: %PROGRAMFILES(X86)%\Quest Software\Authentication Services
INSTALLDESKTOPSHORTCUTS	Specifies whether or not to install desktop shortcuts. Default: 0 (Do not install desktop shortcuts)
INSTALLSTARTMENUSHORTCUTS	Specifies whether or not to install <i>Start</i> menu shortcuts. Default: 0 (Do not install <i>Start</i> menu shortcuts)
ARPSYSTEMCOMPONENT	Specifies whether or not to add an entry in the <i>Uninstall or change a program</i> interface (Add/Remove Programs) for each individual component (ADUC, Group Policy, Control Center and Docs). Default: 0 (Add entry in Add/Remove Programs.)
NOCHANGEPSPOLICY	Specifies whether or not to allow PowerShell execution policy modifications. (Core X86 only.) Default: 0 (Allow PowerShell policy modifications)

The following procedures show examples of using the MSI Properties from the Windows command line.

To install Authentication Services Windows components using Msiexec.exe

1. To install the Control Center, enter the following:

```
msiexec /i cc.msi
```

NOTE: Run `msiexec -help` to see the full command syntax.

2. To specify the install directory path for the core packages, enter:

```
msiexec INSTALLFOLDER=%SystemDrive%\<Directory> /i coreX86.msi
```

NOTE: By default, the installation directory is:

- On Windows 64-bit platforms:
%SystemDrive%\Program Files\Quest Software\Authentication Services
- On Windows 32-bit platforms:
%SystemDrive%\Program Files (x86)\Quest Software\Authentication Services

3. To install the Control Center and create a Desktop icon for it, enter:

```
msiexec INSTALLDESKTOPSHORTCUTS=1 /i cc.msi
```

4. To install the Control Center and create a *Start* menu shortcut for it, enter:

```
msiexec INSTALLSTARTMENUSHORTCUTS=1 /i cc.msi
```

5. To install the ADUC extensions and add a separate entry in the *Uninstall or change a program* interface for it, enter:

```
msiexec ARPSYSTEMCOMPONENT=0 /i aducX64.msi
```

NOTE: Setting ARPSYSTEMCOMPONENT to 1 prevents the application from displaying in the *Uninstall or change a program* interface (Add/Remove Programs).

6. You can apply several MSI properties simultaneously, as in the following example:

```
Msiexec.exe INSTALLFOLDER=C:\foo INSTALLDESKTOPSHORTCUTS=1  
INSTALLSTARTMENUSHORTCUTS=0 ARPSYSTEMCOMPONENT=1 NOCHANGEPSPOLICY=1 /i  
corex86.msi
```

If you run this command line, the Core X86 package will be installed into C:\foo, icons will be added to the Desktop, but no *Start* menu shortcut will be added. Furthermore, this package will not be listed in the *Uninstall or change a program* interface (Add/Remove Programs) and the PowerShell Execution Policy will not be updated.

To uninstall Authentication Services components from the Windows command line

1. To uninstall the Control Center, enter the following:

```
msiexec /uninstall cc.msi
```

NOTES:

You can specify either `/uninstall` or `/x`.

If you manually install MSI files, take care to uninstall them in the reverse order that they are installed. For example if you install CoreX86 and AducExtensionsx86 remove them in this order: AducExtensionsx86, then Corex86.

Configure Active Directory for Authentication Services

To utilize full Active Directory functionality, when you install Authentication Services in your environment, One Identity recommends that you prepare Active Directory to store the configuration settings that it uses. Authentication Services adds the Unix properties of Active Directory users and groups to Active Directory and allows you to map a Unix user to an Active Directory user. This is a one-time process that creates the Authentication Services application configuration in your forest.

- ① **NOTE:** To use the Authentication Services Active Directory Configuration Wizard, you must have rights to create and delete all child objects in the Active Directory container.

If you do not configure Active Directory for Authentication Services, you can run your Authentication Services client agent in "Version 3 Compatibility Mode" which allows you to join a host to an Active Directory domain.

(For more information, see [Version 3 compatibility mode on page 33.](#))

When running Authentication Services client agent in "Version 3 Compatibility Mode", you have the option in One Identity Management Console for Unix to set the schema configuration to use Windows 2003 R2. (See *Configure Windows 2003 R2 Schema* in the management console online Help for details.) The Windows 2003 R2 schema option extends the schema to support the direct look up of Unix identities in Active Directory domain servers.

You can also create the Authentication Services application configuration from the Unix command line, if you prefer. [For more information, see Creating the application configuration from the Unix command line on page 58.](#)

Configuring Active Directory for Authentication Services

The first time you install Authentication Services in your environment, One Identity recommends that you perform this one-time Active Directory configuration step to utilize full Authentication Services 4.1 functionality.

- ① **NOTE:** If you do not configure Active Directory for Authentication Services, you can run your Authentication Services client agent in "Version 3 Compatibility Mode" which allows you to join a host to an Active Directory domain.
(For more information, see [Version 3 compatibility mode on page 33.](#))

To configure Active Directory for Authentication Services

1. At the Authentication Services Active Directory Configuration Wizard Welcome dialog, click **Next**.
2. At the Connect to Active Directory dialog:
 - a. Provide Active Directory login credentials for the wizard to use for this task:
 - Select **Use my current AD logon credentials** if you are a user with permission to create a container in Active Directory.
 - Select **Use different AD logon credentials** to specify the Active Directory credentials of another user, enter the User name and Password.

NOTE: The wizard does not save these credentials; it only uses them for this setup task.
 - b. Indicate how you want to connect to Active Directory:

Select whether to connect to an Active Directory Domain Controller or One Identity Active Roles Server.

NOTE: If you have not installed the One Identity Active Roles Server MMC Console on your computer, the **ActiveRoles Server** option is not available.
 - c. Optionally enter the Domain or domain controller and click **Next**.
3. At the License Authentication Services dialog, browse to select your license file and click **Next**.

Refer to [Licensing Authentication Services on page 10](#) for more information about licensing requirements.

NOTE: You can add additional licenses later from the Authentication Services Control Center Preferences Licensing dialog.
4. At the Configure Settings in Active Directory dialog, accept the default location in which to store the configuration or browse to select the Active Directory location where you want to create the container and click **Setup**.

NOTE: You must have rights to create and delete all child objects in the selected location. For more information on the structure and rights required see [Windows permissions on page 12](#).
5. Once you have configured Active Directory for Authentication Services, click **Close**.

The Control Center opens. You are now ready to configure your Unix Agent Components.

(Proceed to [Configure Unix agent components on page 34](#))

About Active Directory configuration

The first time you install or upgrade the Authentication Services 4.1 Windows components in your environment, One Identity recommends that you configure Active Directory for Authentication Services to utilize full functionality. This is a one-time Active Directory configuration step that creates the application configuration in your forest. Authentication Services uses the information found in the application configuration to maintain consistency across the enterprise. Without the application configuration, store UNIX attributes in the RFC2307 standard attributes to achieve the most functionality.

- NOTE:** If you do not configure Active Directory for Authentication Services, you can run your client agent in "Version 3 Compatibility Mode" which allows you to join a host to an Active Directory domain.

(For more information, see [Version 3 compatibility mode on page 33.](#))

The Authentication Services application configuration stores the following information in Active Directory:

- Application Licenses
- Settings controlling default values and behavior for Unix-enabled users and groups
- Schema configuration

The Unix agents use the Active Directory configuration to validate license information and determine schema mappings. Windows management tools read this information to determine the schema mappings and the default values it uses when Unix-enabling new users and groups.

The Authentication Services application configuration information is stored inside a container object with the specific naming of: `cn={786E0064-A470-46B9-83FB-C7539C9FA27C}`. The default location for this container is `cn=Program Data,cn=Quest Software,cn=Authentication Services,dc=<your domain>`. This location is configurable.

There can only be one Active Directory configuration per forest. If Authentication Services finds multiple configurations, it uses the one created first as determined by reading the `whenCreated` attribute. The only time this would be a problem is if different groups are using different schema mappings for Unix attributes in Active Directory. In that case, standardize on one schema and use local override files to resolve conflicts. You can use the `Set-QasUnixUser` and `Set-QasUnixGroup` PowerShell commands to migrate Unix attributes from one schema configuration to another. Refer to the PowerShell help for more information.

The first time you run the Control Center, the Authentication Services Active Directory Configuration Wizard walks you through the setup.

- NOTE:** You can also create the Authentication Services application configuration from the Unix command line, if you prefer.

For more information, see [Creating the application configuration from the Unix command line on page 58.](#)

You can modify the settings using the Authentication Services Control Center **Preferences**. To change Active Directory configuration settings, you must have rights to

Create Child Object (container) and Write Attribute for *cn*, *displayName*, *description*, *showInAdvancedViewOnly* for the Active Directory configuration root container and all child objects.

In order for Unix clients to read the configuration, authenticated users must have rights to read *cn*, *displayName*, *description*, and *whenCreated* attributes for container objects in the application configuration. For most Active Directory configurations, this does not require any change.

This table summarizes the required rights.

Table 11: Authentication Services: Required rights

Rights Required	For User	Object Class	Attributes
Create Child Object	Authentication Services Administrators Only	Container	<i>cn</i> , <i>displayName</i> , <i>description</i> , <i>showInAdvancedViewOnly</i>
Write Attribute	Authentication Services Administrators Only	Container	
Read Attribute	Authenticated Users	Container	<i>cn</i> , <i>displayName</i> , <i>description</i> , <i>whenCreated</i>

At any time you can completely remove the Authentication Services application configuration using the `Remove-QasConfiguration` cmdlet. However, without the application configuration Authentication Services Active Directory-based management tools do not function.

Join the host to AD without the Authentication Services application configuration

You can install the Authentication Services Agent on a Unix system and join it to Active Directory without installing Authentication Services on Windows and setting up the Authentication Services Application Configuration.

The Authentication Services 4.x client-side agent required detection of a directory-based Application Configuration data object within the Active Directory forest in order to join the host computer to the Active Directory Domain. Authentication Services 4.0.2 removed this requirement for environments where directory-based User and/or Group identity information is not needed on the host Unix computer. These environments include full Mapped-User environments, GSS-API based authentication-only environments, or configurations where the Authentication Services agent will auto-generate posix attributes for Active Directory Users and Groups objects.

Version 3 compatibility mode

When upgrading to or installing Authentication Services 4.1, you can choose not to configure Active Directory for Authentication Services and run your Authentication Services client agent in "Version 3 Compatibility Mode". While this prevents you from running the Control Center and accessing its many features and tools, you can join a host to an Active Directory domain when operating in "Version 3 Compatibility Mode".

- 1 | **NOTE:** When you run the `join` command without first creating a One Identity Application Configuration, Authentication Services displays a warning.

Without the Authentication Services application configuration the following information is stored locally:

- Application Licenses
- Settings controlling default values and behavior for Unix-enabled users and groups
- Schema configuration

Default User Login Name Changes

In VAS 3.5.x, the default user login name was the User Principal Name; Authentication Services 4.1 uses the `sAMAccountName` as the default user login name. After upgrading to 4.1, if you want to continue to login with the User Principal Name, then you must ensure that the `username-attr-name` in the `vas.conf` file is set to the User Principal Name before you begin the client agent upgrade.

- 1 | **NOTE:** This is not necessary if the value of the User Principal Name prefix and the `sAMAccountName` are the same across your enterprise, which is the Active Directory default.

There are two ways to change the `username-attr-name` in the `vas.conf` file:

1. Manually configure each client agent to use the User Principal Name.

To manually configure each client agent to use the User Principal Name

- a. Before you upgrade each client agent, open the `/etc/opt/quest/vas/vas.conf` file and find the `username-attr-name` attribute in the `[vasd]` section.
- b. If there is no value set for this attribute, then set it to:

```
username-attr-name = userPrincipalName
```

- 1 | **NOTE:** If the attribute is already explicitly set to another value (such as: `username-attr-name = uid`), do not change it.

Alternatively, you can run the following command on each client to change the setting in `vas.conf`:

```
vastool configure vas vasd username-attr-name userprincipalname
```

2. Use Group Policy to automatically configure all the clients in your environment.

To automatically configure all the clients in your environment

- a. Open the Group Policy Management Editor and navigate to **Computer Configuration | Policies | Unix Settings | Quest Authentication Services | Client Configuration**.

NOTE: Your version of Group Policy Management Editor may not have the *Policies* directory layer.

- b. Double click **Authentication Services Configuration** to open the *Properties*.
- c. Enter **username-attr-name** in the **vas.conf Settings** box and click **Search**.
- d. Enter **userPrincipalName** and click **OK**.

Best Practice

Because *Version 3 Compatibility Mode* does not allow you run the Control Center and access its many features and tools, One Identity recommends that you create the application configuration so you can utilize full Authentication Services 4.1 functionality.

There are two ways to create the application configuration:

1. When you start the Control Center from a Windows workstation, the Set up Authentication Services Active Directory Configuration Wizard starts automatically to lead you through the process of configuring Active Directory for Authentication Services.
2. Alternatively, you can run `vastool configure ad` from the Unix command line to create the One Identity Application Configuration in Active Directory.

Configure Unix agent components

The Control Center gives you access to the tools you need to perform Unix identity management tasks.

NOTE: If the Control Center is not currently open, you can either double-click the desktop icon or access it by means of the **Start** menu.

Follow the steps outlined on the Control Center *Home* page to get your Unix agents ready.

NOTE: Of course, you can install Authentication Services without using Management Console for Unix. If you wish to do that, skip these instructions and go to: [Installing and joining from the Unix command line on page 51](#).

To start the mangement console

1. From the Control Center, click the **Management Console** link in the left-navigation pane.

Setup Management Console for Unix

The first time you launch the management console, the Setup Management Console for Unix wizard leads you through some post-installation configuration steps. Choose one of these options:

- **Skip the Active Directory configuration, I'll do that later from the console**

This option allows you to use the core features of the console and limits access to the console to the default **supervisor** account only.

- **Walk me through the configuration steps for using AD user accounts for logon to the console**

When you configure the console for Active Directory, you unlock additional Active Directory features.

- ① **NOTE:** To use the management console with Authentication Services, or to use roles to allow access to the console using Active Directory, you must configure the console for Active Directory log on.

Choose an option and click **Next**.

- ① **NOTE:** If you choose the **Skip** option, the Identify Console dialog displays. ([For more information, see Identify Console on page 36.](#))

If you choose the **Walk me through** option, it allows you to configure the console for Active Directory log on. (See *Configure the Console for Active Directory* on the management console online Help for details.)

- ① **NOTE:** If you can not configure the console for Active Directory during your initial installation of Management Console for Unix, choose the **Skip** option. After the installation, log into the console as **supervisor** and configure the console for Active Directory from System Settings. (See *Active Directory Configuration* in the management console online Help for more information.)

Configure the console for Active Directory logon

The Setup Management Console for Unix wizard opens the Configure Console for Active Directory Logon dialog when you choose the **Walk me through the configuration steps for using AD user accounts for logon to the console** option.

To configure the management console for Active Directory logon

1. On the Configure console for Active Directory Logon dialog, enter a valid Active Directory domain in the forest, in the form **example.com**.
2. Enter the credentials for an Active Directory account that has log-on rights.

Enter a sAMAccountName, which uses the default domain or a User Principal Name, as in **username@domain**. The wizard uses these credentials to configure the management console for use with Active Directory.

NOTE: This is a read-only operation; no changes are made to Active Directory.

3. Click **Connect to Active Directory**.
4. When you see the message that indicates the console connected to Active Directory successfully, click **Next**.

The Set up console access by role dialog opens.

Setup console access by role

After you Configure Console for Active Directory Logon, the setup wizard displays the Set up console access by role dialog.

To add Active Directory users or groups to the console access list

1. On the Set up console access by role dialog, click **Add** to specify the Active Directory users and groups that you want to have access to the features available in Management Console for Unix.
2. On the Select Users and Groups dialog, use the search controls to find and select Active Directory user(s) or group(s). Select one or more objects from the list and click **OK**.

The management console adds the selected object(s) to the list on the Set up console access by role dialog.

By default the management console assigns users to *All Roles*, which gives those accounts permissions to access and perform all tasks within the console. (See *Console Roles and Permissions System Settings* in the management console online Help for details.)

3. Click in the **Roles** cell to activate a drop-down menu from which you can choose a role for the user account.

NOTE: During the initial set up, you can only assign one role per user. Add additional roles to a user in System Settings. (See *Add (or Remove) Role Members* in the management console online Help for details.)

4. Click **Next** to save your selections.

The Identify Console dialog opens.

Identify Console

The setup wizard displays the Identify Console dialog during the post-installation configuration steps. The Control Center uses this information to identify this management

console. Hosts configured for automatic profiling or automatic QAS agent status also use this information to contact the management console server.

To identify the management console

1. On the Identify Console dialog, modify the information about this management console, if necessary, and click **Next** to open the Set supervisor password dialog.

NOTE: You can modify these settings from **Settings | System settings | General | Console Information**. (See *Console Information Settings* in the console's online Help for details.)

Set Supervisor Password dialog

The **supervisor** account is the default account for accessing all features of the management console. The **supervisor** is a member of all roles and no permissions can be removed from **supervisor**. However, the **supervisor** does not have Active Directory credentials and therefore is blocked from performing Active Directory tasks.

To set the supervisor password

1. On the Set supervisor password dialog, enter a password for the **supervisor** account and click **Next**.

The Summary dialog displays.

2. To log on using the console supervisor account, use "**supervisor**" as the user name.

NOTE: The **supervisor** is the only account that has rights to change the **supervisor** account password in System Settings. (See *Reset the Supervisor Password* in the management console online Help for details.)

Summary dialog

To complete the Management Console for Unix Setup wizard

1. On the Summary dialog, click **Finish**.

The Management Console for Unix log in screen opens.

Management Console for Unix log on page

Whenever you launch the management console, you must enter an authorized account to proceed. The Management Console for Unix features that are available depend on the account with which you log in.

To use the core version to manage local Unix users and groups and to access the management console system settings, you must use the **supervisor** account (that is, you

must log on with the **supervisor** user name). However, to use the Active Directory features of Management Console for Unix, you must log on with an Active Directory account that has been granted access to the management console. That is, defined during the post-installation configuration. (See *Setup Console Access by Role* in online Help for details.) To add additional accounts to this access list, see *Add (or Remove) Role Members* in online Help for details.

To log on to the management console

1. Enter the user name and password and click **Sign In**.

Enter:

- the **supervisor** account name
- a sAMAccountName, which uses the default domain
- a User Principal Name in the form, username@domain

The management console opens and displays the user name you specified in the upper right-hand corner of the screen.

2. To log on using a different account, click the authenticated user's login name and click **Sign Out**. Then sign back on using a different account.

The Log-on page redisplay, allowing you to enter a different account.

Prepare Unix hosts

The management console provides a central management and reporting console for local Unix users and groups.

Using Management Console for Unix with Authentication Services not only allows you to centrally manage your hosts, but it allows you to do these additional features for managing Unix systems with Active Directory:

- Ability to remotely install Authentication Services agents, join systems to Active Directory, and implement AD-based authentication for Unix, Linux, and Mac OS X systems.
- Ability to manage access control on a single host system or across multiple hosts.
- Ability to create reports about Unix-enabled users and groups in Active Directory.
- Ability to create access control reports that show which user is permitted to log into which Unix host.

Whether you have the core version or are using the management console with Authentication Services, once you have successfully installed Management Console for Unix, you must first add your hosts to the console, and then profile them to gather system information. Once a host is added and profiled you can then manage users and groups on the hosts and run reports.

Add hosts to the management console

In order to manage a Unix host from the management console, you must first add the host. Go to the *Hosts* tab of the management console to either manually enter hosts or import them from a file.

To add hosts to the management console

1. Click the **Add Hosts** tool bar button to display the Add Hosts dialog.
2. To manually add one or more hosts, enter the FQDN, IP address, or short name of a host you want to add to the management console and either click the **Add** button or press **Enter**.

Once added, the **Host** column displays the value you enter. The management console uses that value to connect to the host. You can rename the host if it has not been profiled using the **Rename Host** command on the **Host** panel of the tool bar. After a host is profiled the only way to change what is displayed in the **Host** column is to remove the host from the console and re-add it. For example, if you add a host by its IP address, the IP address displays in the **Host** column (as well as in the **IP Address** column); to change what is displayed in the **Host** column, you must use the **Remove from console** tool bar button to remove the host from the console; then use the **Add Hosts** button to re-add the client by its host name. If you had profiled the host before removing it, you will have to re-profile it after re-adding it.

3. To add hosts from a `known_hosts` file, click the **Import** button.
 - a. On the Import hosts from file dialog, browse to select a `.txt` file containing a list of hosts to import.

Once imported, the host addresses display in the Add Host dialog list.

- NOTE:** The valid format for an import file is:
- `.txt` file - contains the IP address or DNS name, one per line
 - `known_hosts` file - contains address algorithm hostKey (separated by a space), one entry per line

(See *Known_hosts File Format* in the online help for more information about the supported `known_hosts` file format.)

4. Once you have a list of one or more hosts to add, if you do not wish to profile the host(s) at this time, clear the **Profile hosts after adding** option.

- NOTE:** If you add more hosts to the list than selected in the **Rows to show** drop-down menu in the View panel of the tool bar, this option is disabled.

5. If you do not clear the **Profile hosts after adding** option on the Add Hosts dialog, when you click **OK**, the Profile Host dialog prompts you to enter the user credentials to access the host(s). (Refer to [Profile hosts on page 40](#) which walks you through the host profile steps.)
6. If you clear the **Profile hosts after adding** option on the Add Hosts dialog, when you click **OK**, the Add Hosts dialog closes and control returns to the management console.

The management console lists hosts that were successfully added on the All Hosts view by the FQDN, IP address, or short name of the hosts you entered on the Add Hosts dialog.

Profile hosts

Profiling imports information about the host, including local users and groups, into the management console. It is a read-only operation and no changes are made to the host during the profiling operation. Profiling does not require elevated privileges.

To profile hosts

1. Select one or more hosts on the All Hosts view and click **Profile** from the Prepare panel of the tool bar, or open the **Profile** menu and choose **Profile**.
2. In the Profile Host dialog, enter user credentials to access the host(s).
If you selected multiple hosts, you are asked if you want to use the same credentials for all the hosts (default) or enter different credentials for each host.
3. If you selected multiple hosts and the **Use the same credentials for all selected hosts** option, enter the following information:
 - a. Enter the user name and password to log onto the selected host(s).
 - b. Optionally enter the SSH port to use. It uses port 22 by default.
 - c. To save the credentials entered for the host, select the **Save my credentials on the server** option.

Once saved, the management console uses these credentials to access the host during this and subsequent sessions.

NOTE: If you do not save a password to the server, the user name and password fields will be blank the first time the management console needs credentials to complete a task on the host during a log on session. Once entered, the management console caches the user name and password and reuses these credentials during the current session, and pre-populates the user name and password fields in subsequent tasks during the current log on session.

If you choose to save a host's credentials to the server, the management console encrypts the credentials and saves them in the Java keystore. Saved user names and passwords persist across log on sessions, and when needed, the management console pre-populates the user name and password fields each subsequent time it needs them to perform a task. (For more information, see *Caching Unix Host Credentials* in the online Help.)

4. If you selected multiple hosts and the **Enter different credentials for each selected host** option, a grid displays allowing you to enter different credentials and specify different settings for each host.
 - a. To enter different credentials, place your cursor in the **Username** and **Password** columns to the right of the **Host** column and enter the credentials

- to use.
- b. To change the SSH port for a host, place your cursor in the **SSH Port** column and enter the new SSH port number.
 - c. To save the credentials entered for a host, select the check box in the **Save** column.
5. If you want the management console to prompt you to review and accept new SSH keys for the selected hosts (that do not have previously cached SSH keys), clear the **Automatically accept SSH keys** option before you click **OK**.

NOTE: When profiling one or more hosts, you must accept at least one key before continuing. The management console only profiles hosts with accepted keys.

By default the **Automatically accept SSH keys** option is checked. This enables the management console to automatically accept SSH key for all selected hosts that do not have a previously cached key. When it accepts the key, the console adds it to the accepted-keys cache on the Management Console for Unix server. If you clear the **Automatically accept SSH keys** option, when the management console encounters a modified key, it opens the Validate Host SSH Keys dialog, allowing you to manually accept keys that are encountered. Once you have manually verified the fingerprint, the console adds the SSH host key(s) to the accepted-keys cache.

NOTE: Once you profile a host, all future tasks that involve an SSH connection will verify the SSH host key against the accepted-keys cache. When profiling, if the console encounters a modified key, the profile task prompts you to accept new/changed key(s). When performing any other SSH action, other than profile, if the console encounters a different SSH key, the task will fail. To update the accepted-keys cache for the host, you can either profile/reprofile the host, accept the new key, and try the task again. Or, you can import a new SSH host key from the host's properties or from the All Hosts view. (See *Import SSH Host Key* or *Managing SSH Host Keys* in the online help for more information.)

A progress bar displays in the Task Progress pane. The final status of the task displays, including any failures or advisories encountered.

Profile automatically


To keep the Management Console for Unix database up to date with accurate information about users, groups, and One Identity products, you can configure the management console to profile hosts automatically.

BEST PRACTICE: Configure newly added hosts for auto-profiling before you perform any other actions so that the management console dynamically updates user and group information. (See *UID or GID Conflicts* in online Help.)

Configuring a host for auto-profiling sets up a cron job on the client that runs every five minutes. If it detects changes on the host, it triggers a profile operation.

The cron job detects changes to the following:

- local users, groups, or shells
- installed Authentication Services or Privilege Manager software
- Authentication Services access control lists
- Authentication Services mapped user information
- Privilege Manager configuration
- Authentication Services configuration
- Privilege Manager licenses

The cron job also sends a heartbeat every day. This updates the **Last profiled** date displayed on the host properties. If the **Last profiled** date is more than 24 hours old, the host icon changes to  to indicate no heartbeat.

To configure automatic profiling

1. Select one or more hosts on the *All Hosts* view, open the **Profile** menu from the Prepare panel of the tool bar, and choose **Profile Automatically**.

NOTE: The **Profile Automatically** option is only available for multiple hosts if all hosts are in the same 'Auto-profile' state; that is, they all have 'Auto-profile' turned on, or they all have 'Auto-profile' turned off.

2. In the Profile Automatically dialog, select the **Profile the host automatically** option.
3. Choose the user account you want to use for profiling, either:

- **Create a user service account on the host**

When you choose to create the user service account on the host, if it does not already exist, the management console, does the following:

- a. Creates "questusr", the user service account, and a corresponding "questgrp" group on the host that the management console uses for automatic profiling.
- b. Adds *questusr* as an implicit member of *questgrp*.

-OR-

- **Use an existing user account (user must exist on all selected hosts)**

(Click **Select** to browse for a user.)

4. Click **OK** on the Profile Automatically dialog.

Whether you choose to create the user service account or use an existing user account, the management console,

- Adds the user account (the "questusr" or your existing user account) to the cron.allow file, if necessary. For example, the console takes no action if the cron.allow file does not already exist, but there is a cron.deny file:

cron.allow	cron.deny	Console's action	Resultant User Access
NO	NO	Creates cron.allow and adds root and <i>questusr</i> to it	Both root and <i>questusr</i> have access.
NO	YES	No action	All users have access except those in cron.deny; <i>questusr</i> has access unless explicitly denied.
YES	NO	Adds <i>questusr</i> to cron.allow	Users in cron.allow have access.
YES	YES	Adds <i>questusr</i> to cron.allow	Users in cron.allow have access unless in cron.deny.

- Adds the auto-profile SSH key to *questusr*'s `authorized_keys`, `/var/opt/quest/home/questusr/.ssh/authorized_keys`.
- Verifies the service account user can login to the host.

1 | **NOTE:** If you receive an error message saying you could not log in with the user service account, please refer to *Service Account Login Fails* in online Help to troubleshooting this issue.

The *questusr* account is a non-privileged account that does not require root-level permissions. This account is used by the console to gather information about existing user and groups in a read-only fashion, however, the mangement console does not use *questusr* account to make changes to any configuration files.

If *questusr* is inadvertently deleted from the console, the console turns 'Auto-profiling' off.

To recreate the "questusr" account

- Re-profile the host.
 - Reconfigure the host for automatic profiling.
5. On the Log on to Host dialog, enter the user credentials to access the selected host(s) and click **OK**.

1 | **NOTE:** This task requires elevated credentials.

If you select multiple hosts, you are asked if you want to use the same credentials for all the hosts (default) or enter different credentials for each host.

- If you selected multiple hosts and the **Use the same credentials for all selected hosts** option, enter your credentials to log on to access the selected host(s) and click **OK**.

- b. If you selected multiple hosts and the **Enter different credentials for each selected host** option, it displays a grid which allows you to enter different credentials for each host listed. Place your cursor in a cell in the grid to activate it and enter the data.

To disable automatic profiling

1. Select one or more hosts on the All Hosts view and choose **Profile Automatically**.
2. Clear the **Profile the host automatically** option and click **OK**.
3. On the Log on to Host dialog, enter the user credentials to access the selected host(s) and click **OK**.

When you disable auto-profiling for a host, the management console,

1. leaves the "questusr" and the corresponding "questgrp" accounts on the host, if they were previously created.
2. leaves *questusr* as an implicit member of *questgrp*, if it exists.
3. removes the user account (the "questusr" or your existing user account) from the `cron.allow` file.
4. removes the auto-profile SSH key from that user's `authorized_keys` file.

Install software on hosts

Once you have successfully added and profiled one or more hosts, and checked them for AD Readiness, you can remotely deploy software products to them from the management console.

To install Authentication Services software on hosts

1. Select one or more profiled hosts on the All Hosts view and click the **Install Software** tool bar button.

NOTE: The **Install Software** tool bar menu is enabled when you select hosts that are profiled.

The tool bar button will not be active if

- You have not selected any hosts.
- You have selected multiple hosts with different states (added, profiled, or joined).

2. On the Install Software dialog, select the Authentication Services software products you want to install and click **OK**.
 - **Authentication Services Agent (Required)** - Select to allow Active Directory users access to selected host. Authentication Services provides centralized user and authentication management. It uses Kerberos and LDAP to provide secure data transport and an authentication framework that works with Microsoft Active Directory. Components include: `vasd`, `nss_vas`, `pam_vas`, and

vastool.

- **Authentication Services for Group Policy (Required)** - Select to install the Group Policy component which provides Active Directory Group Policy support for Unix, Linux, and Mac OS X platforms.
- **Authentication Services for NIS** - Select to install the NIS Proxy component which provides the NIS compatibility features for Authentication Services. `vasyp` is a NIS daemon that acts as a `ypserv` replacement on each host.
- **Authentication Services for LDAP** - Select to install the LDAP Proxy component which provides a way for applications that use LDAP bind to authenticate users to Active Directory without using secure LDAP (LDAPS). Instead of sending LDAP traffic directly to Active Directory domain controllers, you can configure applications to send plain text LDAP traffic to `vasldapd` by means of the loopback interface. `vasldapd` proxies these requests to Active Directory using Kerberos as the security mechanism.
- **Dynamic DNS Updater** - Select to install the Dynamic DNS Updater component which provides a way to dynamically update host records in DNS and can be triggered by DHCP updates.
- **Defender PAM Module** - Select to install the Defender authentication components for PAM based Unix/Linux systems. Includes PAM module, documentation and utilities to appropriately configure the PAM subsystem for Active Directory/Defender OTP authentication.

NOTE: You must install the Authentication Services Agent and the Group Policy packages.

NOTE: If you do not see all of these software packages, verify the path to the software packages is correctly set in System Settings. (Refer to *Set the Authentication Services Client Software Location on the Server* in the management console online help for details.)

3. On the Log on to Host dialog, enter the user credentials to access the selected host(s) and click **OK**.

NOTE: This task requires elevated credentials.

If you selected multiple hosts, it asks whether you want to use the same credentials for all the hosts (default) or enter different credentials for each host.

- a. If you selected multiple hosts and the **Use the same credentials for all selected hosts** option, enter your credentials to log on to access the selected host(s) and click **OK**.
- b. If you selected multiple hosts and the Enter different credentials for each selected host option, it displays a grid which allows you to enter different credentials for each host listed. Place your cursor in a cell in the grid to activate it and enter the data.

Check readiness

Once you install the software on your remote hosts, the management console allows you to perform a series of tests to verify that a host meets the minimum requirements to join an Active Directory domain. Running the readiness checks does NOT require elevated privileges.

- i** **NOTE:** This task is only available when you are logged on as **supervisor** or an Active Directory account in the Manage Hosts role. (See *Roles and Permissions System Settings* in the management console online Help for more information.)

To check host(s) for Active Directory Readiness

1. Select one or more hosts on the All Hosts view of the Hosts tab, open the **Check** menu from the Prepare panel of the tool bar, and choose **Check for AD Readiness**.
2. In the Check AD Readiness view, enter the Active Directory domain to use for the readiness check.
3. Enter Active Directory user credentials, and click **OK**.
4. On the Log on to Host dialog, enter the user credentials to access the selected host(s) and click **OK**.

If you selected multiple hosts, it asks whether you want to use the same credentials for all the hosts (default) or enter different credentials for each host.

- a. If you selected multiple hosts and the **Use the same credentials for all selected hosts** option, enter your credentials to log on to access the selected host(s) and click **OK**.
- b. If you selected multiple hosts and the **Enter different credentials for each selected host** option, it displays a grid which allows you to enter different credentials for each host listed. Place your cursor in a cell in the grid to activate it and enter the data.

A progress bar displays in the Task Progress pane on the All Hosts page. The final status of the task displays, including any failures or advisories encountered. To see the AD Readiness check results, open the host's property page and select the **Readiness Check Results** tab.

Join hosts to Active Directory

In order to manage access to a host using Authentication Services for Active Directory, you must join the host to an Active Directory domain. Joining a host to a domain creates a computer account for that host. Once you have deployed and installed the Authentication Services Agent software on a host, use the **Join to Active Directory** command on the All Hosts view's **Join** menu to join the host to an Active Directory domain.


To join hosts to Active Directory

1. Select one or more hosts from the list on the All Hosts view, open the **Join or Configure** menu tool bar button and select **Join to Active Directory**.

NOTE: The **Join to Active Directory** tool bar menu is enabled when you select hosts that have the Authentication Services Agent installed and are not joined Active Directory.

The tool bar button will not be active if:

- You have not selected any hosts.
- You have selected multiple hosts with different states (joined, not joined).

2. On the Join Host to Active Directory dialog, enter the following information to define how and where you want to join the host to Active Directory:
 - a. Select the Active Directory domain to use for the join operation or enter the FQDN of the Active Directory domain.
Use the same domain you entered when you performed the Check for AD Readiness.
 - b. Optionally enter a name for the computer account for the host.
Leave this field blank to generate a name based on the host's DNS name.
 - c. Click the  button to locate and select a container in which to create the host computer account.
 - d. Enter the optional join commands to use.
See *Optional Join Commands* in the management console online Help for a list of commands available.
 - e. Enter the user name and password to log onto Active Directory.
The user account you enter must have elevated privileges in Active Directory with rights to create a computer account for the host.
3. On the Log on to Host dialog, enter the user credentials to access the selected host(s) and click **OK**.

NOTE: This task requires elevated credentials. The management console pre-populates this information.

The Task Progress pane on the All Hosts view displays a progress bar and the final status of the tasks, including any failures or advisories encountered.

Check QAS agent status

You can either check the health status of Authentication Services agents manually, or you can configure the management console to automatically check the QAS Agent Status and report any warnings or failures to the console.

NOTE: Running the *Check QAS Agent Status* commands requires:

- you are logged on as an Active Directory account in the *Manage Hosts* role
- the hosts have Authentication Services 4.0.3.78 (or later) Agent software installed

See *Check QAS Agent Status Commands Not Available* in the management console online Help for more information.

Check QAS agent status manually

To check QAS agent status

1. Select one or more hosts on the All Hosts view, open the **Check** menu from the Prepare panel of the tool bar and choose **Check QAS agent status**.
2. In the Log on to Host dialog, enter the user credentials to access the selected host(s) and click **OK**.

A progress bar displays in the Task Progress pane and the Host Notifications tab indicates the number of hosts with warnings or failures detected.

NOTE: This task requires elevated credentials.

If you select multiple hosts, you are asked if you want to use the same credentials for all the hosts (default) or enter different credentials for each host.

- If you selected multiple hosts and the **Use the same credentials for all selected hosts** option, enter your credentials to log on to access the selected host(s) and click **OK**.
 - If you selected multiple hosts and the **Enter different credentials for each selected host** option, it displays a grid which allows you to enter different credentials for each host listed. Place your cursor in a cell in the grid to activate it and enter the data.
3. Select the **Host Notifications** tab to view the reported warnings or failures.
(See *View the QAS Agent Status* in the management console online Help for details.)

Check QAS agent status automatically

To have updated information about the status of Authentication Services agents, you can configure the management console to periodically check the QAS Agent Status automatically. If it detects a status change on the host, it reports the following warnings or failures to the Host Notifications tab:

- Critical Failure
- Failure
- Warning

To configure the console to automatically check the QAS agent status

1. Select one or more hosts on the *All Hosts* view, open the **Check** menu from the *Prepare* panel of the tool bar, and choose **Check QAS Agent Status automatically**.
 - 1 | **NOTE:** This option is only available for multiple hosts if all hosts are in the same "Check QAS Agent Status" state; that is, they all have automatic status checking turned on, or they all have automatic status checking turned off.
2. Select the **Check status automatically** option, set the frequency for the health status check, and click **OK**.
 - 1 | **NOTE:** Use standard crontab syntax when entering Advanced schedule settings.
3. On the Log on to Host dialog, enter the user credentials to access the selected host(s) and click **OK**.
 - 1 | **NOTE:** This task requires elevated credentials.

When configured for automatic checking, the **Authentication Services state** column on the All Hosts view displays the 🟢 icon. Then, if the server does not receive a heartbeat in over 4 hours (by default), it displays the 🟡 icon. No icon in the **Authentication Services state** column indicates the host is not configured to check the QAS agent status automatically.

If you select multiple hosts, you are asked if you want to use the same credentials for all the hosts (default) or enter different credentials for each host.

- If you selected multiple hosts and the **Use the same credentials for all selected hosts** option, enter your credentials to log on to access the selected host(s) and click **OK**.
 - If you selected multiple hosts and the **Enter different credentials for each selected host** option, it displays a grid which allows you to enter different credentials for each host listed. Place your cursor in a cell in the grid to activate it and enter the data.
- 1 | **NOTE:** If you receive a GID conflict error, see *UID or GID Conflicts* in online Help.
4. View the QAS Agent Status for each host on the *Host Notification* tab.
(See *View the Authentication Services Status Errors* in online Help for details.)

When you configure a host to check the QAS agent status automatically, the management console,

- a. Creates "questusr" (the service account user), if it does not already exist, and, a corresponding "questgrp" group on the host that the management console uses for automatic QAS agent status checking.
- b. Adds *questusr* as an implicit member of *questgrp*.
- c. Adds the auto-check SSH key to *questusr*'s `authorized_keys`,
`/var/opt/quest/home/questusr/.ssh/authorized_keys`.

- d. Verifies the service account user can login to the host.
- e. Creates a cron job that runs QAS agent status according to the specified interval.

NOTE: If you receive an error message saying you could not log in with the user service account, please refer to *Service Account Login Fails* in online Help to troubleshooting this issue.

The *questusr* account is a non-privileged account that does not require root-level permissions. This account is used by the console to gather information about existing users and groups in a read-only fashion, however, the mangement console does not use the *questusr* account to make changes to any configuration files.

NOTE: If *questusr* is inadvertently deleted from the console, the console will not be updated. To recreate the "questusr" account, re-configure the host for automatic QAS agent status checking.

To disable automatic status checking

1. Select one or more hosts on the All Hosts view and choose **Check QAS Agent Status automatically....**
2. Clear the **Check status automatically** option on the Check QAS Agent Status Automatically dialog and click **OK**.
3. On the Log on to Host dialog, enter the user credentials to access the selected host(s) and click **OK**.

When you disable auto-status checking for a host, the mangement console

1. Leaves the "questusr" and the corresponding "questgrp" accounts on the host.
2. Leaves *questusr* as an implicit member of *questgrp*.
3. Removes the auto-check SSH key from that user's `authorized_keys` file.
4. Removes the cron job on the host.

Installing and joining from the Unix command line

While you can use Management Console for Unix to install and configure Authentication Services as explained in [Installing and configuring Authentication Services on page 23](#), you can also manually install the Authentication Services agent on each Unix, Linux, or Mac OS X host from the command line.

This section walks you through the process of installing the Authentication Services Unix agent directly from the command line. For information about installing, upgrading, and uninstalling the Authentication Services agent on supported platforms in an enterprise environment using platform package management tools, refer to [Enterprise package deployment on page 109](#).

Before installing and configuring the Authentication Services Unix agent, One Identity recommends that you run the `preflight` tool to check a host's suitability to run Authentication Services. After you determine that the Unix host is ready, run the Authentication Services installation script, `install.sh`, to install the Unix/Linux agent.

The Authentication Services pre-installation diagnostic tool

One Identity provides the `preflight` utility to check a host's suitability to run Authentication Services by verifying a number of environmental considerations necessary for joining an Active Directory domain.

This utility obtains answers to the following questions:

- Does Authentication Services support the host on which this utility is being run?
- Are the operating system and any patches at requisite levels?
- Is there at least one visible domain controller (DC)?
- Are global catalogs available on any of the domain controllers?
- Are all services needed by Authentication Services available?
- Is a Authentication Services application configuration set up on the target domain?

The `preflight` command-line utility performs the following verifications:

Install Checks:

- Check for supported operating system and correct operating system patches.
- Check for sufficient disk space to install Authentication Services.

Join Checks:

- Check that the hostname of the system is not 'localhost'.
- Check if the name service is configured to use DNS.
- Check `resolv.conf` for proper formatting of name service entries and that the host can be resolved.
- Check for a name server that has the appropriate DNS SRV records for Active Directory.
- Detect a writable domain controller with UDP port 389 open.
- Detect Active Directory site, if available.
- Check if TCP port 464 is open for Kerberos `kpasswd`.
- Check if UDP port 88 and TCP port 88 are open for Kerberos traffic.
- Check if TCP port 389 is open for LDAP.
- Check for a global catalog server and if TCP port 3268 is open for communication with global catalog servers.
- Check for a valid time skew against Active Directory.
- Check for the Authentication Services application configuration in Active Directory.

Post-Join Checks:

- Check if TCP port 445 is open for Microsoft CIFS traffic.

You can find the `preflight.sh` script at the root of the ISO. This script runs the correct `preflight` version for your system.

The most important options and arguments to `preflight` are:

- **`domain-name`**

The domain you want to join with Authentication Services.

- **`-u username`**

An identity with administrator rights for the Active Directory domain you want to join.

NOTE: The `preflight` utility does not make any changes to your system.

Running preflight

To run preflight

1. Mount the Authentication Services distribution media.
2. Enter the following command at the root of the Authentication Services ISO:

```
# ./preflight.sh -u Administrator@example.com
```

where *Administrator* is your user name and *example.com* is the name of your domain.

By default `preflight` outputs the results of the verifications for the three types of checks (Install Checks, Join Checks and Post-Join Checks) to the console. Run the `preflight` utility with the `--verbose` option to obtain detailed information about the various checks in those categories.

The last line of the output tells you whether you are ready to continue deploying Authentication Services.

If you did not get a "Preflight Checks ... complete with status Success" message, correct any failures indicated before continuing with the Authentication Services installation. Be aware of any "Advisories" that it returns, as they may impact your ability to install or join.

- ❶ **NOTE:** If you get a message that says, "Unable to locate Authentication Services Application Configuration", you can ignore that error for now and proceed with the Authentication Services installation. The Authentication Services Active Directory Configuration Wizard starts automatically to help you configure Active Directory for Authentication Services the first time you start the Control Center. Or, you can create the Authentication Services application configuration from the command line, as explained in [Creating the application configuration from the Unix command line on page 58](#).
- ❶ **NOTE:** For information about other `preflight` options, either run `preflight --help` or refer to the *preflight man page* located in the `docs` directory of the installation media. (See [Resolving preflight failures on page 101](#) for additional help in resolving issues.)

The Authentication Services install script

Follow the steps in this topic if you are installing a Authentication Services 4.1 for the first time; that is, if you are not upgrading from VAS 3.5.

The Authentication Services installation script, `install.sh`, installs Authentication Services, joins the domain, and allows you to install licenses. You can run the install script in interactive mode by using the `-i` option. This provides you with a menu of valid operations to perform, including *Running preflight*.

You can also automate the installation process by running `install.sh` in "unattended" mode using `-q` option. In this mode you may specify a set of commands for the script to perform.

- ① **NOTE:** For more information on the Authentication Services installation script, run `install.sh --help`

Installing the Authentication Services agent

To install the Authentication Services agent with the installation script

1. Log in and open a root shell.
2. Mount the installation DVD for your selected platform and navigate to the mount point.
3. Run `install.sh` by entering the following command:

```
# ./install.sh vasclnt
```

- ① **NOTE:** See [Install the Authentication Services agent package on page 109](#) for a list of the Authentication Services Agent installation commands.

After installing Authentication Services some services such as `cron`, `sshd` and `gdm` may need to be restarted in order to reload NSS configuration. If you are unsure of which services to restart, reboot the system.

Installation script options

If you run `install.sh` with no option, it installs (or upgrades) Authentication Services and Authentication Services Group Policy, installs the license, and joins the domain.

The following is a list of the available options to the Authentication Services install script:

Table 12: install.sh: Options

Option	Function
<code>-d</code>	Turn on debug.
<code>-h</code>	Help; displays usage information including a brief summary of options.
<code>--help</code>	Displays full script help.
<code>-v, --version</code>	Displays version and lists products available on this ISO.
<code>-l path</code>	License; path to One Identity license file to copy (unattended mode). Not valid with <code>-i</code> (interactive mode)

Option	Function
-p	Specify alternate ISO path to search for install packages.
-t	Test host and iso and report on what is installed and available.
<none>	Simple mode
-i	Interactive mode; provides a menu showing choices based on existing Authentication Services software installation and includes a help mode.
-q	Unattended mode; executes script in unattended (automatic) mode; requires other options.
-a	Accept License; signals acceptance of One Identity LLC EULA.

Table 13: Special commands

Command	Description
upgrade	Upgrades all products on the system.
remove	Removes all products from the system.
join	Executes interactive <code>vasjoin.sh</code> script. Not valid with <code>-q</code> (Unattended mode).
preflight	Executes interactive preflight test. Not valid with <code>-q</code> (Unattended mode).
license	Executes interactive install of license files (or use <code>-l</code> option). Not valid in with <code>-q</code> (Unattended mode).

In unattended mode, the following arguments are useful for scripting the components you want to install or uninstall.

Table 14: `install.sh`: Unattended mode arguments

Argument	Function
<code>vascert</code>	Installs or upgrades Authentication Services Certificate Autoenrollment
<code>vasclnt</code>	Installs or upgrades Authentication Services agent
<code>vasdev</code>	Installs or upgrades Authentication Services SDK
<code>vasgp</code>	Installs or upgrades Authentication Services Group Policy agent
<code>vasproxy</code>	Installs or upgrades Authentication Services Proxy daemon
<code>vassc</code>	Installs or upgrades Authentication Services for Smart Cards agent
<code>vasyp</code>	Installs or upgrades Authentication Services YP server
<code>novascert</code>	Uninstalls Authentication Services Certificate Autoenrollment
<code>novasclnt</code>	Uninstalls the Authentication Services agent

Argument	Function
novasdev	Uninstalls the Authentication Services SDK
novasgp	Uninstalls the Authentication Services Group Policy agent
novasproxy	Uninstalls the Authentication Services Proxy daemon
novassc	Uninstalls the Authentication Services for Smart Cards agent
novasyp	Uninstalls the Authentication Services YP server

Licensing Authentication Services

You must have the Authentication Services license installed for full Authentication Services functionality on Unix.

There are four ways to manage licenses

1. **Using the Control Center**

One Identity recommends this as a best practice. ([For more information, see Add licenses using the Control Center on page 67.](#))

2. **Using the Authentication Services Group Policy utilities**

For more information, see *Licensing Policy* in the *Authentication Services Administration Guide*.

3. **Running the install.sh script with the -l option**

This allows you to enter a path. The script then places the license in the proper location. [For more information, see Installation script options on page 54.](#)

4. **Installing Licenses From the Command Line**

[For more information, see Installing licenses from the command line on page 57.](#)

To obtain a license, complete the form located at: [Request License Key](#) or contact your account representative for a new license file.

NOTE: If you are running Management Console for Unix with a licensed version of Authentication Services, any time you make a change to the Authentication Services licensing, go into the management console System Setting's *Licenses* and click the **Check for licenses** button to refresh the product license information in Management Console for Unix.

Verifying Authentication Services license information

To verify that you have a valid Authentication Services license

1. Run the following `vastool` command:

```
vastool license -q
```

You will see output similar to the following if you have a valid license installed:

```
Number of Unix Enabled users in use:    150
---QAS---
Number of Licensed Unix Enabled Users: 1000
Valid licenses:                          1
```

Installing licenses from the command line

With root privileges, you can manually install a valid license by copying the new license file to the `licenses` directory on the Unix host.

To install a Authentication Services license manually

1. Copy the license file to the `/etc/opt/quest/vas/.licenses` directory.
2. Ensure the permissions on the license file are set to `0644`.
3. Restart `vasd` as root by running the command corresponding to your platform:

- **Linux/Solaris:**

```
/etc/init.d/vasd restart
```

- **HPUX:**

```
/sbin/init.d/vasd restart
```

- **AIX:**

```
/etc/rc.d/init.d/vasd restart
```

- **Mac OS X:**

```
launchctl unload /Library/LaunchDaemons/com.quest.vasd.plist
```

```
launchctl load /Library/LaunchDaemons/com.quest.vasd.plist
```

Creating the application configuration from the Unix command line

Before you join a Unix client to an Active Directory domain, One Identity recommends that you create the application configuration in the domain to which you are joining to utilize full Authentication Services 4.1 functionality. While the Authentication Services Active Directory Configuration Wizard starts automatically to help you configure Active Directory for Authentication Services the first time you start the Control Center, you do not need to have a Windows console to create the application configuration. You can run the `vastool configure ad` command from the Unix command line to create it. This is typically a one-time process.

i | **NOTE:** You only need to create one Authentication Services application configuration per forest. For more information, see [Version 3 compatibility mode on page 33](#).

To create the Authentication Services application configuration

1. Run the following command from the Unix command line:

```
# /opt/quest/bin/vastool ad -u <user> configure -d <domain>
```

By default Authentication Services creates the application configuration in the Program Data container; however, if you do not have rights to create an organizational unit in the Program Data container, you can create the Authentication Services application configuration in any location you have rights to by specifying the DN (distinguished name) of the creation location, as follows:

```
vastool -u <user> configure -d <domain> ou cn=myou,dc=example,dc=com
```

2. Enter the user's password when prompted.

Changing the schema configuration mode

When you create the Authentication Services application configuration, you set the global schema configuration mode to R2 by default. However you can optionally configure Authentication Services for "schemaless" operation using the `schema configure` command.

To switch to a schemaless configuration

1. Run the following command:

```
# /opt/quest/bin/vastool -u <user> schema -d <domain> configure schemaless
```

The `schema configure` command only allows you to set the schema mode to either R2 or "schemaless" modes. To set the schema configuration to any other mode, you must do so from the Control Center *Preferences*.

2. Enter the user's password when prompted.

Joining the domain

For full Authentication Services functionality on Unix, you must join the Unix system on which you installed the Authentication Services agent to the Active Directory domain. You can join an Active Directory domain either by running `vastool join` from the command line or the interactive join script, `vasjoin.sh`.

Before you join the Unix host to the Active Directory domain, you may want to determine if you are already joined.

To determine if you are joined to an Active Directory domain

1. Run the following command.

```
# /opt/quest/bin/vastool info domain
```

If you are joined to a valid domain this command returns the domain name. If you are not joined to a domain, you will see the following error:

```
ERROR: No domain could be found.  
ERROR: VAS_ERR_CONFIG: at ctx.c:414 in _ctx_init_default_realm  
default_realm not configured in vas.conf. Computer may not be joined to domain
```

Joining the domain using VASTOOL

You can join your Unix host to Active Directory with the `vastool join` command directly from the command line.

Before you join the Authentication Services agent to the Active Directory domain, collect the following information:

- The DNS name of the Active Directory domain of which you want the Authentication Services agent to be a member.
- The user name and password of a user that has sufficient administrative privileges to create computer objects in Active Directory.

To join Active Directory using `vastool join`

1. Run the following command as the root user at a shell prompt:

```
# /opt/quest/bin/vastool -u <user> join <domain-name>
```

2. Enter the user's password when prompted.

The `vastool join` results are shown on the shell's standard output.

NOTE: `vastool join` supports many options that allow you to customize the way the computer is joined to the domain. You can specify the name of the computer object. You can join to a specific organizational unit or use a pre-created computer object. For a list of all `vastool join` options, refer to the *vastool man page*.

Joining the domain using VASJOIN script

Rather than using the `vastool join` command from the command line, you can join your Unix host to Active Directory using the interactive join script, `vasjoin.sh`. The script walks you through the domain join process, calling the `vastool join` command.

The `vasjoin.sh` script is in `/opt/quest/libexec/vas/scripts/` directory. You can use most of the standard `vastool join` command options when running it. However, you can run the join script with no options; it only requires that you supply the domain name and the name of a user with sufficient Active Directory privileges to perform the join.

Table 15: Common `vasjoin` script options

OPTION	FUNCTION
-h	Help; displays options including how to pass <code>vastool join</code> options
-q	Unattended or <i>quiet</i> mode; displays less verbose: no explanations, asks no questions
-i	Interactive mode: prompts for common options
<none>	Simple mode; installs vasclnt and vasgp with options to add license and join domain.

To join Active Directory using the `vasjoin` script

1. Run the script as the root user at a shell prompt, as follows:

```
/opt/quest/libexec/vas/scripts/vasjoin.sh
```

The script ensures that your local host's time is synchronized with that of the controller in the domain you want to join (in order to satisfy Kerberos), then performs the join for you by running `vastool join` as follows:

```
vastool -u <username> join <domain-name>
```

2. Follow the prompts to complete the join process.

NOTE: Run the script in interactive mode as follows:

```
/opt/quest/libexec/vas/scripts/vasjoin.sh -i
```

In interactive mode, it prompts you for specific information and allows you to either save the resulting `vastool join` command in a script or execute the command immediately.

The script presents defaults as part of the prompting and if you accept them all, the result is identical to running the script in simple mode.

The information gathered by the full, interactive mode of `vasjoin.sh` includes the following.

- Specific domain controllers to use
- domain to join
- user, usually administrator, to use in joining
- keytab file
- confirm fixing of Kerberos clock skew, if any
- overwrite your host's existing Active Directory ComputerName object
- change the name of the AD ComputerName object
- AD container in which to put the ComputerName object
- site name
- UPM mode (yes or no)
- user search path on which to look for Active Directory users
- alternate group search path
- workstation mode (yes or no)
- alternate domains in which to search if you want cross-domain logins
- self-enrollment of existing `/etc/passwd` users (yes or no)
- shows path to `lastjoin` (`/etc/opt/quest/vas/lastjoin`)

The `lastjoin` file contains something similar to:

```
/opt/quest/bin/vastool -u administrator join -f acme.com
```

Dynamic DNS update tool

When Authentication Services joins a new computer to a domain, it becomes known to the LDAP and Kerberos protocols, but not to DNS. This is because the IP address of the host is not directly under the control of this part of Active Directory.

Although Active Directory comes with an integrated DHCP and DNS servers, some sites run their own DHCP servers. This means that the leased IP addresses must be communicated to Active Directory's DNS server through another (often manual) means.

The One Identity Dynamic DNS Update Tool, `dnsupdate`, performs this communication. It can automatically and securely inform Active Directory's DNS server of IP address changes of the host due to DHCP lease acquisition and renewal.

Because `dnsupdate` uses Kerberos to authenticate itself to the DNS server, only the computer joined with that name can update its record.

When you run the Authentication Services installation script, `install.sh`, in interactive mode (the `-i` option), it gives you an option to install the One Identity Dynamic DNS Update Tool. Dynamic DNS automatically integrates into the host's native DHCP client infrastructure to securely update DNS servers when its IP address changes. (For more information about running the `install.sh` script, see [Installation script options on page 54.](#))

- ❗ **NOTE:** If Pointer Record (PTR) updates are being rejected, it may be because the DHCP server is doing the update already. Refer to the documentation for the DHCP server being used in your environment. The Microsoft DHCP server does updates on behalf of the client and this is controlled by the Fully Qualified Domain Name (FQDN) option. Please refer to the Microsoft Active Directory DNS/DHCP documentation.

Getting started with Authentication Services

Once you have successfully installed Authentication Services you will want to learn how to do some basic system administration tasks using the Control Center and Management Console for Unix.

Getting acquainted with the Control Center

Authentication Services consists of plugins, extensions, security modules and utilities spread across nearly every operating system imaginable. The Control Center pulls those parts together and provides a single place for you to find the information and resources you need.

Control Center installs on Windows and is a great starting place for new users to get comfortable with some of Authentication Services' capabilities.

You can launch the Control Center from the *Start* menu or by double-clicking the desktop icon, or by double-clicking the Control Center application file from %SystemDrive% : \Program Files (x86)\Quest Software\Authentication Services.

Table 16: Control Center: Navigation links

Control Center Section	Description
Home	The "Welcome" page provides information about how to use the Control Center tools and features.
Management Console	You can run the One Identity Management Console for Unix management console within the Control Center or you can run it separately in a supported web browser. The management console is a separate install on Windows, Unix, Linux, or Mac OS X that you can launch from the ISO.

Control Center Section	Description
	Typically you install one management console per environment to avoid redundancy. One Identity does not advise managing a Unix host by more than one management console in order to avoid redundancy and inconsistencies in stored information. If you manage the same Unix host by more than one management console, you should always re-profile that host to minimize inconsistencies that may occur between instances of the management consoles.
Group Policy	The Control Center provides the ability to search on Active Directory Group Policy Objects that have Unix and Mac OS X settings defined. Also provides links to edit these GPO's and run reports that show the detailed settings of the Group Policy Objects.
Tools	The Control Center provides links to additional tools and resources available with Authentication Services – a great starting place for anyone new to the product.
Preferences	The Control Center allows you to centrally manage the default values generated by the various Authentication Services management tools, including the ADUC snap-in, the PowerShell cmdlets, and the Unix command-Line tools.
Log into remote host	The Control Center provides a simple SSH client (built on PuTTY) for remote access to Unix systems – simplifies new installs from having to find and install a separate PuTTY client.

To run Control Center you must be logged in as a domain user. To make changes to global settings you must have rights in Active Directory to create, delete, and modify objects in the Authentication Services configuration area of Active Directory.

Management console

Management Console for Unix allows you to centrally manage Authentication Services agents running on Unix, Linux and Mac OS X systems.

With the management console you can:

- Remotely deploy the Authentication Services agent software.
- Manage local user and group accounts.
- Configure account mappings from local users to Active Directory accounts.
- Report on a variety of security and host access related information.

You can install the management console on supported Unix, Linux, and Mac OS X platforms. Once installed, you can access it from a browser using default port of 9443 or from the Control Center.

Group Policy

Microsoft Group Policy provides excellent policy-based configuration management tools for Windows. Group Policy enables you to manage Unix resources in much the same way. Group Policy allows you to consolidate configuration management tasks by using the Group Policy functionality of Microsoft Windows Server to manage Unix operating systems and Unix application settings.

To open Group Policy, click **Group Policy** on the left navigation panel of the Authentication Services Control Center.

Filter options

To filter the list of GPOs

1. Expand the **Filter Options** section.
2. Enter all or part of a name to filter the list of GPOs.
3. Open the *Domain* drop down menu to choose a domain.
4. Select the **Unix Settings** or **Mac Settings List Only** options to further filter the GPO list.

If you select both options, only the GPOs configured for both Unix and Mac OS X display.

Edit GPO

To edit a group policy object

1. From the Group Policy window, select a GPO in the list and click **Edit GPO** from the *Actions* menu.

The *Group Policy Object Editor* opens for the selected GPO.

NOTE: For more information about the group policies, refer to the *Authentication Services Administration Guide*, located in Control Center **Tools** view in the *Documentation* section, or in the docs directory of the installation media.

Settings report

A settings report displays all of the Authentication Services Group Policy object settings that apply to Unix or Mac OS X systems.

To generate a Unix settings report

1. From the Group Policy window, select a GPO Name and click **Settings Report** from the *Actions* menu.

An HTML report of the currently configured Unix and Mac OS X settings displays.

NOTE: You can select multiple GPOs to run several reports simultaneously.

Show Files

To open the Windows Explorer

1. From the Group Policy window, select a GPO in the list and click **Show Files** from the *Actions* menu.

The Windows Explorer opens and displays the Group Policy Templates for the selected GPO.

Launch GPMC

NOTE: Microsoft does not support Group Policy Management Console (GPMC) on 64-bit platforms of Windows; thus, One Identity does not support managing group policies through the Control Center on Windows 2003 64-bit and Windows 2003 R2 64-bit, XP 64-bit platforms. (See [Group Policy Management Console with Service Pack 1](#) for more information.)

To launch the Group Policy Management Console

1. From the Group Policy window, click **Launch GPMC** from the *Actions* menu.

Tools

The **Tools** link on the Control Center gives you access to:

- **Authentication Services**

Direct links to installed applications and tools related to Authentication Services.

- **Additional One Identity Products**

Direct links to other One Identity product plugins.

NOTE: The **Additional One Identity Products** link is only available if you have installed other One Identity products such as Defender, Authentication Services for Smart Cards, or One Identity Active Roles.

- **Other Tools**

Direct links to tools related to Authentication Services.

NOTE: The **Other Tools** link is only available if you have installed the Group Policy Management Console.

- **Documentation**

Direct links to Authentication Services documentation.

Preferences

Authentication Services stores certain preferences and settings in Active Directory. This information is used by Authentication Services clients and management tools so that behavior remains consistent across all platforms and tools. The *Preferences* window allows you to configure these settings and preferences.

Licensing

The *Licensing* section of the *Preferences* window in the Control Center displays a list of installed license files. You can add and remove license files at any time. The license files are stored in Active Directory and Authentication Services Unix hosts automatically download and apply new license files from Active Directory.

(Refer to [Licensing Authentication Services on page 10](#) for more information about licensing requirements.)

Add licenses using the Control Center

To add licenses using the Control Center

1. Click the **Preferences** navigation button on the left panel of the Control Center.
2. Expand the **Licensing** section.

The list box displays all licenses currently installed in Active Directory.

3. Click **Add a license** from the *Actions* menu.
4. Browse for the license file and click **Open**.

The license appears in the list box.

NOTE: Unix hosts check for new licenses when the host is joined to the domain or every 24 hours by default. This can be changed by modifying the `configuration-refresh-interval` setting in `vas.conf`.

5. To remove a license, select it and click **Remove license**.
6. To restore a removed license, click **Undo Remove**.

Global Unix Options

The Global Unix Options section displays the currently configured options for Unix-enabling users and groups.

Click **Modify Global Unix Options** to change these settings.

NOTE: Authentication Services uses the Global Unix Options when enabling users and groups for Unix log in.

Table 17: Unix User Defaults

Option	Description
Require unique user login names	Select to require a unique user login name attribute within the forest.
Require unique UID on users	Select to require a unique user's Unix ID (UID) number within the forest.
Minimum UID Number	Enter a minimum value for the Unix User ID (UID) number. Typically you set this to a value higher than the highest UID among local Unix users to avoid conflicts with users in Active Directory and local user accounts.
Maximum UID Number	Enter a maximum value for the Unix User ID (UID) number. Typically you would not change this value unless you have a legacy Unix platform that does not support the full 32-bit integer range for UID number.
Primary GID Number	Enter the default value for the Primary GID number when Unix-enabling a user.
Set primary GID to UID	Select to set the primary GID number to the User ID number.
Default Comments (GECOS)	Enter any text in this box.
Login Shell	Enter the default value for the login shell used when Unix-enabling a user.
Home Directory	Enter the default prefix used when generating the home directory attribute when Unix-enabling a user. The default value is <code>/home/</code> ; use a different value if your Unix user home directories are stored in another location on the file system. Authentication Services uses the user's effective Unix name when generating the full home directory path.
Use lowercase user name for home directory	Select to use a lower-case representation of the user's effective Unix name when generating the full home directory path as a user is Unix-enabled.

Table 18: Unix Group Defaults

Option	Description
Require unique Group Names	Select to require a unique Unix group name attribute within the forest.
Require unique GID Number	Select to require a unique Unix Group ID (GID) attribute within the forest.
Minimum GID Number	Enter the minimum value for the Unix Group ID (GID). Typically this is set to a value higher than the highest GID among local Unix groups to avoid conflicts with groups in Active Directory and local group accounts.
Maximum GID Number	Enter the maximum value for the Unix Group ID (GID). Typically you would not change this value unless you have a legacy Unix platform that does not support the full 32-bit integer range for GID.

These options control the algorithms used to generate unique user and group IDs.

Table 19: Unique IDs

Option	Description
Object GUID Hash	An ID generated from a hash of the user or group object GUID attribute. This is a fast way to generate an ID which is usually unique. If the generated value conflicts with an existing value, the ID is re-generated by searching the forest.
Samba Algorithm	An ID generated from the SID of the domain and the RID of the user or group object. This method works well when there are few domains in the forest. If the generated value conflicts with an existing value, the ID is re-generated by searching the forest.
Legacy Search Algorithm	An ID generated by searching for existing ID values in the forest. This method generates an ID that is not currently in use.

Modifications you make to these Global Unix Options take effect after you restart the Microsoft Management Console (MMC).

- BEST PRACTICE:** It is a best practice to either use the generated default IDs or set the ID manually. Mixing the two methods can lead to ID conflicts.


Logging options

The *Logging Options* section allows you to enable logging for all Authentication Services Windows components. This setting only applies to the local computer. Logging can be helpful when trying to troubleshoot a particular problem. Because logging causes

components to run slower and use more disk space, you should set the **Log Level** to *disabled* when you are finished troubleshooting.

Enable debug logging on Windows

To enable debug logging for all Authentication Services Windows components

1. Open Control Center and click the **Preferences** navigation button on the left panel.
2. Expand the **Logging Options** section.
3. Open the *Log level* drop-down menu and set the log level to **Debug**.
Debug generates the most log output. Higher levels generate less output. You can set the **Log level** to *Disabled* to disable logging.
4. Click  to specify a folder location where you want to write the log files.

Authentication Services Windows components log information into the specified log folder the next time they are loaded. Each component logs to a text file named after the DLL or EXE that generates the log message.

Custom Unix attributes

The Unix schema attributes are fully customizable in Authentication Services. The Custom Unix Attributes section allows you to see which LDAP attributes are mapped to Unix attributes. You can modify this mapping to enable Authentication Services to work with any schema configuration. To customize the mapping, you select a schema template or specify your own custom attributes. A schema template is a pre-defined set of common mappings which adhere to common schema extensions for storing Unix data in Active Directory. Authentication Services supports the following schema templates if the required schema is installed:

Table 20: Unix schema attributes

Schema Template	Description
Schemaless	A template that encodes Unix attribute data in an existing multi-valued attribute.
Windows R2	A template that uses attributes from the Windows 2003 R2 schema extension.
Services for Unix 2.0	A template that uses attributes from the SFU 2.0 schema extension.
Services for Unix 3.0	A template that uses attributes from the SFU 3.0 schema extension.

- ❶ **BEST PRACTICE:** Use a schema designed for storing Unix data in Active Directory whenever possible. Schemas designed for storing Unix data in Active Directory include: Windows 2003 R2, SFU 2, and SFU 3. Only use "schemaless" or custom mappings if it is impossible to make schema extensions in your environment.
- ❶ **NOTE:** If you are running Authentication Services without an application configuration in your forest and your domain supports Windows 2003 R2, you can enable Authentication Services to use the Windows 2003 R2 schema. However, please note, some functionality provided by the Authentication Services application configuration will be unavailable. (For more information, see *Configure Windows 2003 R2 Schema* in the management console online Help.)

Active Directory schema extensions

Authentication Services stores Unix identity and login information in Active Directory. One Identity designed Authentication Services to provide support for the following standard Active Directory schema extensions:

Table 21: Active Directory schema extensions

Schema Extension	Description
Windows 2003 R2 Schema	This schema extension is provided by Microsoft and adds support for the PosixAccount auxiliary class, used to store Unix attributes on user and group objects.
Services for Unix 2.0	Microsoft provides this schema extension with the Services for Unix 2.0 set of tools. It adds custom attributes to user and group objects, used to store Unix account information.
Services for Unix 3.0	Microsoft provides this schema extension with the Services for Unix 3.0 set of tools. It adds custom attributes to user and group objects, used to store Unix account information.

It is possible to customize the schema setup to work with any schema configuration with Authentication Services. No schema extensions are necessary with the new "schemaless" storage feature. When you configure Authentication Services for the first time, Authentication Services attempts to auto-detect the best schema configuration for your environment. The schema configuration is a global application setting that applies to all Authentication Services management tools and Unix agents. You can change the detected settings at any time using Control Center.

Configure a custom schema mapping

If you do not have a schema that supports Unix data storage in Active Directory, you can configure Authentication Services to use existing, unused attributes of users and groups to store Unix information in Active Directory.

To configure a custom schema mapping

1. Open the Control Center and click the **Preferences** on the left navigation panel.
2. Expand the **Custom Unix Attributes** and click **Customize**.
3. Type the LDAP display names of the attributes that you want to use for Unix data. All attributes must be string-type attributes except **User ID Number**, **User Primary Group ID** and **Group ID Number** which may be integers. If an attribute does not exist or is of the wrong type, the border will turn red indicating that the LDAP attribute is invalid.

NOTE: When customizing the schema mapping, ensure that the attributes used for **User ID Number** and **Group ID Number** are indexed and replicated to the global catalog.

For more information, see [Active Directory optimization on page 72](#).

4. Click **OK** to validate and save the specified mappings in Active Directory.

Active Directory optimization

Indexing certain attributes used by the Authentication Services Unix agent can have a dramatic effect on the performance and scalability of your Unix and Active Directory integration project. The **Custom Unix Attributes** panel in the **Preferences** section of Control Center displays a warning if the Active Directory configuration is not optimized according to best practices.

One Identity recommends that you index the following attributes in Active Directory.

- User UID Number
- User Unix Name
- Group GID Number
- Group Unix Name

NOTE: LDAP display names vary depending on your Unix attribute mappings.

It is also a best practice to add all Unix identity attributes to the global catalog. This reduces the number of Active Directory lookups that need to be performed by Authentication Services Unix agents.

Click the **Optimize Schema** link to run a script that updates these attributes as necessary.

NOTE: The **Optimize Schema** option is only available if you have not optimized the Unix schema attributes defined for use in Active Directory.

This operation requires administrative rights in Active Directory. If you do not have the necessary rights to optimize your schema, it generates a schema optimization script. You can send the script to an Active Directory administrator who has rights to make the necessary changes.

All schema optimizations are reversible and no schema extensions are applied in the process.

Learning the basics

The topics in this section help you learn how to do some basic system administration tasks using the Control Center and Management Console for Unix.

- 1 **NOTE:** The exercises in this section assume that you have successfully installed Authentication Services and Management Console for Unix and have added a host to the console and joined it to Active Directory. (See [Prepare Unix hosts on page 38.](#))

This section shows you how to create the following test user and group accounts used in various examples:

- A local group name called "**localgroup**"
- A local user object called "**localuser**"
- An Active Directory group object called "**UNIXusers**"
- An Active Directory user object called "**ADuser**"

One Identity recommends that you work through the topics in this section in order as a self-directed "test drive" of some of the key product features. You will learn how easy it is to manage your users and groups from the management console.

Add a local group

You can use the management console to remotely add a local group to the host.

- 1 **NOTE:** This topic instructs you to set up a local group by the name of "localgroup" referred to by other examples in this guide.

To add a local group to the host

1. From the Management Console for Unix *Host* tab's *All Hosts* view, double-click a host name to open its properties.
2. Select the **Groups** tab and click **Add Group**.
3. In the Add New Group dialog, enter **localgroup** as a local group name in the **Group Name** box and click **Add Group**.
4. In the Log on to Host dialog, enter your credentials and click **OK**.

- 1 **NOTE:** This task requires elevated credentials. Credential information is entered by default from the cache.

The new local group account is added to the system and management console.

Add local user account

- 1 **NOTE:** This topic instructs you to set up a local user by the name of "localuser" referred to by other examples in this guide.

To add a local user account

1. From the *All Hosts* view, double-click a host name to open its properties.
2. Select the **Users** tab from the host properties and click **Add User**.
3. In the Add New User dialog,
 - a. Enter **localuser** as a new local user name in the **Name** box.
 - b. Click **Select Group** browse button next to the **GID** box, to find and select the **local group** account you set up in [Add a local group on page 73](#).
You can also the navigation buttons at the bottom of the list to find and select a group.
 - c. Click the **Select Shell** browse button to find and select a local login shell.
 - d. Enter and re-enter a password of your choice and click **Add User** to add this new local user.
4. On the Log on to Host dialog, enter your credentials to log onto the host and click **OK**.

- 1 **NOTE:** This task requires elevated credentials. The mangement console enters this information by default from the cache.

The new local user account is added to the system and mangement console.

At this point the new local user is valid for local authentication with the password you just set.

Add an Active Directory group account

Authentication Services provides additional tools to help you manage different aspects of migrating Unix hosts into an Active Directory environment. Links to these tools are available from **Tools** in the Control Center.

- 1 **NOTE:** This topic instructs you to set up an Active Directory group by the name of "UNIXusers" referred to by other examples in this guide.

To create a new group in Active Directory

1. In the Control Center, navigate to **Tools** and click the link for **Authentication Services Extensions for Active Directory Users and Computers**.

The *Active Directory Users and Computers* Console opens.

NOTE:

- Windows Vista/Windows 7: You must have the Remote Server Administration Tools installed and enabled.
- Windows2003/Windows XP: You must have the Windows 2003 Server Administration Tools installed.

2. Expand the **domain** folder and select the **Users** folder.
3. Click the **New Group** icon button.
The New Object - Group dialog opens.
4. Enter **UNIXusers** in the **Group name** box and click **OK**.

Add an Active Directory user account

- NOTE:** The following procedure instructs you to use ADUC (Active Directory Users and Computers) to set up an Active Directory user by the name of "ADuser" referred to by other examples in this guide.

To create an Active Directory user account

1. In the Active Directory Users and Computers console, select the **Users** folder and click the **New User** icon button.
2. On the New Object - User dialog, enter information to define a new user named **ADuser** and click **Next**.
The New Object - User wizard guides you through the user setup process.
3. When you enter a password, clear the **User must change password at next logon** option, before you click **Next**.
4. Click **Finish**.
5. Close Active Directory Users and Computers and return to the management console.

Change the default Unix attributes

You can modify the Unix attributes that are generated by default when users are Unix-enabled. To change the Login Shell you must have rights to create and delete child objects in the Authentication Services application configuration in Active Directory.

To change the default Unix attributes

1. Click the **Preferences** navigation button on the left panel of the Control Center.
2. Expand **Global Unix Options**.
The window displays the current settings for Unix-enabling users, groups and the method used for creating unique IDs.
3. Click **Modify Global Unix Options** on the right side of the window.
The Modify Global Options dialog opens.
4. Change the **Login Shell** to **/bin/bash** and click **OK**.
The defaults are saved to Active Directory.

i **NOTE:** Now, when you Unix-enable a user from Active Directory Users and Computers, PowerShell, or the Unix command line, the login shell defaults to /bin/bash. You can customize the other Unix defaults similarly.


Active Directory account administration

The topics that follow show you how to perform Active Directory account administration from Management Console for Unix for hosts that are joined to Active Directory.

Enable local user for AD authentication

This feature, also known as user mapping, allows you to associate an Active Directory user account with a local Unix user. Allowing a local user to log into a Unix host using Active Directory credentials enables that user to take advantage of the benefits of Active Directory security and access control.

To enable a local user for Active Directory authentication



1. From the management console *Host* tab's *All Hosts* view, double-click a host to open its properties.
2. Select the **Users** tab and double-click the **localuser** account to open its properties.
i **NOTE:** To set up this local user account, see [Add local user account on page 74](#).
3. On the *AD Logon* tab, select the **Require an AD Password to logon to Host** option, and click **Select**.
4. On the Select AD User dialog, click the  **Search** button to populate the list of Active Directory users, select the **ADuser** account, and click **OK**.
i **NOTE:** To set up this Active Directory user, see [Add an Active Directory user account on page 75](#).
5. On the localuser's properties, click **OK**.


6. On the Log on to Host dialog, verify your credentials to log onto the host and click **OK**.

You have now "mapped" a local user to an Active Directory user and the management console indicates that the local user account requires an Active Directory password to log onto the Host in the *AD User* column.

You can also map multiple Unix users to use a single Active Directory account using the *Require AD Logon* pane on the *All Local Users* tab.

To assign (or "map") a Unix user to an Active Directory user

1. From the *All Local Users* tab, select one or more local Unix users.
2. In the *Require AD Logon* pane, click the  **Search** button to populate the list of Active Directory users.
(Click the  **Directory** button to search in a specific folder.)
3. Select an Active Directory user and click the **Require AD Logon to Host** button at the bottom of the *Require AD Logon* pane.
4. On the Log on to Host dialog, verify your credentials to log onto the host and click **OK**.

 **NOTE:** This task requires elevated credentials.

The Active Directory user assigned to the selected local Unix user(s) displays in the **AD User** column of the *All Local Users* tab.

Test the mapped user login

Once you have "mapped" a local user to an Active Directory user, you can log into the local Unix host using your local user name and the Active Directory password of the Active Directory user to whom you are "mapped".

To test the mapped user login

1. From the Control Center, under "Login to remote host", enter:
 - the Unix host name in the **Host name** box
 - the local user name, **localuser**, in the **User name** boxand click **Login** to log onto the Unix host with your local user account.
2. If the PuTTY Security Alert dialog opens, click **Yes** to accept the new key.
3. Enter the password for *ADuser*, the Active Directory user account you mapped to *localuser*, when you selected the **Require an AD Password to logon to Host** option on the user's properties.
4. At the command line prompt, enter `id` to view the Unix account information.

5. Enter `/opt/quest/bin/vastool klist` to see the credentials of the Active Directory user account.
6. Enter `exit` to close the command shell.

You just learned how to manage local users and groups from Management Console for Unix by mapping a local user account to an Active Directory user account. You tested this by logging into the Unix host with your local user name and the password for the Active Directory user account to whom you are "mapped".

Unix-enable an Active Directory group

To Unix-enable an Active Directory group


1. On the management console's *Active Directory* tab, open the **Find** box drop-down menu and choose **Groups**.
2. Enter a group name, such as **UNIX**, in the **Search by name** box and press **Enter**.
3. Double-click the group name, such as **UNIXusers**, to open its properties.

i | **NOTE:** To set up this Active Directory user account, see [Add an Active Directory group account on page 74](#).

4. On the *Unix Account* tab, select the **Unix-enabled** option and click **OK**.

Unix-enable an Active Directory user

To Unix-enable an Active Directory user

1. On the management console's *Active Directory* tab, open the **Find** box drop-down menu and choose **Users**.
2. Click  to the **Search by name** box to search for all Active Directory users. Or, enter a portion of your *ADuser* log on name in the **Search by name** box and press **Enter**.
3. Double-click **ADuser**, the Active Directory user name, to open its properties.
4. On the *Unix Account* tab, select the **Unix-enabled** option.

It populates the properties with default Unix attribute values.

5. Make other modifications to these settings, if necessary, and click **OK** to Unix-enable the user.

i | **NOTE:** There are additional settings that you can set using PowerShell which allows you to validate entries for the GECOS, Home Directory, and Login Shell attributes. Refer to [Use Authentication Services PowerShell on page 92](#) to learn more about that.

Once enabled for Unix, you can log on to the host with that Active Directory user's log on name and password.

Test the Active Directory user login

Now that you have Unix-enabled an Active Directory user, you can log into a local Unix host using your Active Directory user name and password.

To test the Active Directory login

1. From the Control Center, under "Login to remote host", enter:
 - the Unix host name in the **Host name** box
 - the Active Directory user name, such as **ADuser**, in the **User name** boxand click **Login** to log onto the Unix host with your Active Directory user account.
2. Enter the password for the Active Directory user account.
3. At the command line prompt, enter `id` to view the Unix account information.
4. After a successful log in, verify that the user obtained a Kerberos ticket by entering:

```
/opt/quest/bin/vastool klist
```

The `vastool klist` command lists the Kerberos tickets stored in a user's credentials cache. This proves the local user is using the Active Directory user credentials.
5. Enter `exit` to close the command shell.

You just learned how to manage Active Directory users and groups from Management Console for Unix by Unix-enabling an Active Directory group and user account. You tested this out by logging into the Unix host with your Active Directory user name and password. Optionally, you can expand on this tutorial by creating and Unix enabling additional Active Directory users and groups and by testing different Active Directory settings such as account disabled and password expired.


Run reports

You can run various reports that capture key information about the Unix hosts you manage from the management console and the Active Directory domains joined to these hosts from the *Reports* view on the *Reporting* tab.

NOTE: The Active Directory reports are only available when you are logged on as an Active Directory account in the *Manage Hosts* role.

To run reports

1. Ensure the hosts for which you want to create reports have been recently profiled.
Reports only generate data gathered from the clients during a *Profile* procedure. Profiling imports information about the host, including local users and groups.
- NOTE:** You can configure the management console to profile hosts automatically. (For more information, see [Profile automatically on page 41.](#))

2. From the management console, click the **Reporting** tab.
3. From the Reports view, expand the report group names to view the available reports, if necessary.
 - **Host Reports**
Unix host information gathered during the profiling process
 - **User Reports**
Local and Active Directory user information
 - **Group Reports**
Local and Active Directory group information
 - **Access & Privileges Reports**
User access information
 - **License Usage Reports**
Product licensing information.
4. Use one of the following methods to select a report:
 - Double-click a report name in the list (such as the **Unix Host Profiles** report).
 - Right-click a report name and select **Run report**.
 - Click the report icon  next to a report.

The selected report name opens a new tab on the Reports view which describes the report and provides some report parameters you can select or clear to add or exclude details on the report.

5. Optionally clear parameters to exclude information from the report.
6. To create a report, either
 - Click **Preview** to see a sample of the report in a browser.
 - Open the **Export** drop-down menu and select the format you want to use for the report: **PDF** or **CSV** (if available).

NOTE: If the CSV report does not open, you may need to reset your internet options. (See *CSV or PDF Reports Do Not Open* in online help for details.)

By default, the management console creates reports in the application data directory:

- On Windows XP/2003 Server:
`%SystemDrive%\Documents and Settings\All Users\Application Data\Quest Software\Management Console for Unix\reports`
- On Windows 2008 Server/Vista/7:
`%SystemDrive%\ProgramData\Quest Software\Management Console for Unix\reports`

- On Unix/Mac OS X:

`/var/opt/quest/mcu/reports`

NOTE: You may need to reconfigure your browser preferences to allow you to save the report in a specific folder.

It launches a new browser or application page and displays the report in the selected format.

NOTE: When generating multiple reports simultaneously or generating a single report that contains a large amount of data, One Identity recommends that you increase the JVM memory. (See *Tune JVM Memory* in the online help for details.)

Reports

The management console provides comprehensive reporting which includes reports that can help you plan your deployment, consolidate Unix identity, secure your hosts and troubleshoot your identity infrastructure. The following tables list the reports that are available in Management Console for Unix.

NOTE: Report availability depends on several factors:

- **User Log-on Credentials:** While some reports are available when you are logged in as **supervisor**, there are some reports that are only available when you are logged on as an Active Directory user. (See *Active Directory Configuration* in online Help for details.)
- **Roles and Permissions:** Reports are hidden if they are not applicable to the user's console role. (See *Console Roles and Permissions System Settings* in online Help for details.) For example, you must have an activated policy server to activate the sudo-related reports.

Host reports

Table 22: Host reports

Report	Description
Authentication Services Readiness	<p>Provides a snapshot of the readiness of each host to join Active Directory. This report is best used for planning and monitoring migration projects. The basic report includes the following information:</p> <ul style="list-style-type: none"> • Total number of hosts • Total number, percentage and names of the hosts ready to join • Total number, percentage and names of the hosts ready to join with advisories

Report	Description
	<ul style="list-style-type: none"> • Total number, percentage and names of the hosts not ready to join • Total number of hosts not checked for AD readiness <p>Use the following report parameters to define details to include in the report.</p> <ul style="list-style-type: none"> • Joined to AD • Ready to Join AD • Ready to Join AD with Warnings • Not Ready to Join AD • Not Checked for Readiness <p>i NOTE: This report is available when you are logged on as the supervisor or an Active Directory account in the <i>Manage Hosts</i> role.</p>
Privilege Manager Readiness	<p>Provides a snapshot of the readiness of each host to join a policy group. The basic report includes the following information:</p> <ul style="list-style-type: none"> • Total number of hosts • Total number, percentage and names of the hosts ready to join • Total number, percentage and names of the hosts not ready to join • Total number of hosts not checked for readiness <p>Use the following report parameters to define details to include in the report.</p> <ul style="list-style-type: none"> • Joined to a policy group • Ready to join a policy group • Ready to join a policy group with warnings • Not ready to join a policy group • Not checked for readiness <p>i NOTE: This report is available when you are logged on as the supervisor or an Active Directory account in the <i>Manage Sudo Policy</i> role or the <i>Audit Sudo Policy</i> role.</p>
Unix Computers in AD	<p>Lists all Unix computers in Active Directory in the requested scope.</p> <p>By default, this report is created using the default domain as the base container. Browse to search Active Directory to locate and select a different base container to begin the search.</p>

Report	Description
	<p>i NOTE: This report is available when you are logged on as an Active Directory account in the <i>Manage Hosts</i> role.</p>
Unix Host Profiles	<p>Summarizes information gathered during the profiling process of each managed host. This report includes the following information:</p> <ul style="list-style-type: none"> • Total number of hosts included in the report • Host Name, IP Address, OS, Hardware • Sudo version number <p>Use the following report parameters to define details to include for each host.</p> <ul style="list-style-type: none"> • Authentication Services Properties • Privilege Manager Properties • Local Users • Local Groups • Host SSH Keys • Installed One Identity Software <p>i NOTE: This report is available when you are logged on as the supervisor or an Active Directory account in the <i>Manage Hosts</i> role.</p>

User reports

Table 23: User reports

Report	Description
AD User Conflicts	<p>Returns all users with Unix User ID numbers (UID numbers) assigned to other Unix-enabled user accounts.</p> <p>By default, it creates this report using the default domain as the base container. Browse to search Active Directory to locate and select a different base container to begin the search.</p> <p>i NOTE: This report is available when you are logged on as an Active Directory account in the <i>Manage Hosts</i> role.</p>
Local Unix User Conflicts	<p>Identifies local user accounts that would conflict with a specified user name and UID on other hosts. You can use this report for planning user consolidation across your hosts. This report includes the following information:</p> <ul style="list-style-type: none"> • Host Name, DNS Name or IP Address where a conflict would occur

Report	Description
	<ul style="list-style-type: none"> User Name, UID Number, Primary GID Number, Comment (GECOS), Home Directory and Login Shell for each host where conflicts exist <p>Use the following report parameters to define the user name and UID number that would cause a conflict with existing local user accounts:</p> <ul style="list-style-type: none"> User Name is UID Number is <p>NOTE: This report is available when you are logged on as the supervisor or an Active Directory account in the <i>Manage Hosts</i> role.</p>
Local Unix Users	<p>Lists all users on all hosts or lists the hosts where a specific user account exists in <code>/etc/passwd</code>. This report includes the following information:</p> <ul style="list-style-type: none"> Host Name, DNS Name or IP Address where the user exists User Name, UID Number, Primary GID Number, Comment (GECOS), Home Directory, and Login Shell for each host where the user exists <p>If you do not define a specific user, it includes all local users on each profiled host in the report.</p> <p>To locate a specific user, use the following report parameters:</p> <ul style="list-style-type: none"> User Name contains UID Number is Primary GID Number is Comment (GECOS) contains Home Directory contains Login Shell contains <p>NOTE: When you specify multiple report parameters, it uses the AND expression; therefore, ALL of the selected parameters must be met in order to locate the user account.</p> <p>NOTE: This report is available when you are logged on as the supervisor or an Active Directory account in the <i>Manage Hosts</i> role.</p>
Local Unix Users with AD Logon	<p>Identifies the local user accounts that are required to use Active Directory credentials to log onto the Unix hosts. This report includes the following information for hosts that are joined to an Active Directory domain:</p> <ul style="list-style-type: none"> Host Name, DNS Name or IP Address of hosts where users exist that are required to log on using their AD credentials User Name, UID Number, Primary GID Number and Comment (GECOS) of local user account

Report	Description
	<ul style="list-style-type: none"> The SAM account Name of the Active Directory account that the local user account must use to log on <p>i NOTE: This report only includes hosts joined to an Active Directory domain with a Authentication Services 4.x agent.</p> <p>i NOTE: This report is only available when the host has Authentication Services 4.x or later installed and is joined to Active Directory. You must be logged in with an Active Directory account in the <i>Manage Hosts</i> role.</p>

Master /etc/- passwd List Provides a consolidated list of all user accounts from all hosts, excluding any local users marked as system users. This report includes the following information:

- Username
- Empty password
- UID
- GID
- GECOS
- Home directory path
- Account's shell

You can consolidate the list of user accounts by matching values for accounts across multiple hosts. Accounts found with matching values are listed as a single local account. This list is best used for migrating local users to Active Directory.

Indicate how you want to match user accounts by selecting the value parameters that you want to match:

- Username
- UID
- GID
- GECOS
- Home Directory
- Shell

Optionally, you can include the host name for the accounts, as well:

- Include the host name for accounts

Report	Description
	<p>i NOTE: If you select the Include the host name for accounts option, the management console adds a column to the <code>Master_etc_passwdList.csv</code> file to identify the host for each user account. One Identity provides the Host column information to help you resolve the entries in the file. However, before you import the <code>.cvs</code> file into the Unix Account Import Wizard, you must remove the Host column.</p> <p>You can easily migrate local users to Active Directory by exporting the <code>Master /etc/passwd List</code> report, then importing it into the Unix Account Import Wizard, accessible from the Authentication ServicesControl Center's Tools link. The Unix Account Import Wizard is a versatile tool that helps migrate Unix account information to Active Directory. It is especially well suited to small, one-shot import tasks such as importing all the local user accounts from a specific Unix host. The Unix Account Import Wizard can import Unix data as new user and group objects or use the data to Unix-enable existing users and groups.</p> <p>i NOTE: This report is available when you are logged on as the supervisor or an Active Directory account in the <i>Manage Hosts</i> role.</p>
Unix-Enabled AD Users	<p>Lists all Active Directory users that have Unix user attributes.</p> <p>i NOTE:</p> <ul style="list-style-type: none"> • A User object is considered to be 'Unix-enabled' if it has values for the UID Number, Primary GID Number, Home Directory and Login Shell. • If Login Shell is <code>/bin/false</code>, the user is considered to be disabled for Unix or Linux logon. • Account Disabled indicates whether the Active Directory User account is enabled or disabled. <p>By default, it creates this report using the default domain as the base container. Browse to search Active Directory to locate and select a different base container to begin the search.</p> <p>i NOTE: This report is only available if you have configured the management console to recognize Active Directory objects (see <i>Configuring the Console to Recognize Unix Attributes in AD</i> in online help), and you are logged on as an Active Directory account in the <i>Manage Hosts</i> role.</p>

Group reports

Table 24: Group reports

Report	Description
AD Group Conflicts	<p>Lists all Active Directory groups with Unix Group ID (GID) numbers assigned to other Unix-enabled groups.</p> <p>By default, it creates this report using the default domain as the base container. Browse to search Active Directory to locate and select the base container to begin the search.</p> <p>i NOTE: This report is available when you are logged on as an Active Directory account in the <i>Manage Hosts</i> role.</p>
Local Unix Groups	<p>Identifies the hosts where a specific group exists in <code>/etc/group</code>. This report includes the following information:</p> <ul style="list-style-type: none">• Host Name, DNS Name or IP Address where the group exists• Group Name, GID Number, and members for each host where the group exists <p>If you do not specify a group, it includes all local groups on each profiled host in the report.</p> <p>To locate a specific group, use the following report parameters:</p> <ul style="list-style-type: none">• Group Name contains• GID Number is• Member contains• Include all group members in report <p>i NOTE: The Member contains field accepts multiple entries separated by a comma. Spaces are taken literally in the search. For example, entering:</p> <ul style="list-style-type: none">• adm, user searches for members whose name contains 'adm' or 'user'• adm,user searches for members whose name contains 'adm' or 'user'. <p>i NOTE: When you specify multiple report parameters (for example, Group Name contains, GID Number is, and Member contains), it uses the AND expression; therefore, ALL of the selected parameters must be met in order to locate a group.</p> <p>In addition, it includes all of the group members in the report by default, but you can clear the Include all group members in report option.</p>

Report	Description
	<p>i NOTE: This report is available when you are logged on as the supervisor or an Active Directory account in the <i>Manage Hosts</i> role.</p>
Unix-Enabled AD Groups	<p>Lists all Active Directory groups that have Unix group attributes.</p> <p>i NOTE: A Group object is considered 'Unix-enabled' if it has a value for the GID Number.</p> <p>By default, it creates this report using the default domain as the base container. Browse to search Active Directory to locate and select a different base container to begin the search.</p> <p>i NOTE: This report is only available if you have configured the management console to recognize Active Directory objects (see <i>Configuring the Console to Recognize Unix Attributes in AD</i> in online help), and you are logged on as an Active Directory account in the <i>Manage Hosts</i> role.</p>

Access & Privileges reports

- i** **NOTE:** The Access & Privileges reports do not report on users and groups from a NIS domain.

Table 25: Access & Privileges reports

Report	Description
Access & Privileges by Host	<p>Identifies all users with log-on access to hosts and the commands the users can run on the hosts. This report includes the following information:</p> <ul style="list-style-type: none"> • Total number of users that can log on to the host • The users that can log on to the host • The commands users can run on the host • The runas aliases for which the user can run commands on the host • The commands the runas alias can run on the host <p>Browse to select a host.</p> <p>Optionally, select the Show detailed report option.</p> <p>i NOTE: This report is available when you are logged on as the supervisor or as an Active Directory account in the <i>Manage Sudo Policy</i>, <i>Manage PM Policy</i>, <i>Audit Sudo Policy</i>, or <i>Audit PM Policy</i> roles. You must have an active policy group for Privilege Manager to run this report; you can only include hosts that are joined to a policy group.</p>

Report	Description
Access & Privileges by User	<p data-bbox="384 271 1394 365">Identifies the users with log-on access to hosts, the commands that user can run on each host, and the "runas aliases" information for that user. This report includes the following information:</p> <ul data-bbox="437 389 1382 607" style="list-style-type: none"> <li data-bbox="437 389 1098 418">• Total number of hosts where the user can logon <li data-bbox="437 436 935 465">• The hosts where the user can logon <li data-bbox="437 483 1066 512">• The commands the user can run on each host <li data-bbox="437 530 1382 560">• The runas aliases for which the user can run commands on each host <li data-bbox="437 577 1153 607">• The commands the runas alias can run on each host <p data-bbox="384 633 1342 696">Use the following report parameters to specify the user to include in the report:</p> <ul data-bbox="437 723 746 797" style="list-style-type: none"> <li data-bbox="437 723 746 752">• A local user (default) <li data-bbox="437 770 612 799">• An AD user <p data-bbox="384 824 719 853">Browse to select a user.</p> <p data-bbox="384 873 1082 902">Optionally select the Show detailed report option.</p> <div data-bbox="405 920 1386 1099" style="border-left: 1px solid #00a0e3; padding-left: 10px;"> <p data-bbox="405 920 1386 1099">NOTE: This report is available when you are logged on as the supervisor or as an Active Directory account in the <i>Manage Sudo Policy</i>, <i>Manage PM Policy</i>, <i>Audit Sudo Policy</i>, or <i>Audit PM Policy</i> roles. You must have an active policy group for Privilege Manager to run this report; you can only include hosts that are joined to a policy group.</p> </div>
Commands Executed	<p data-bbox="384 1128 1378 1294">Provides details about the commands executed by users on hosts joined to a policy group, based on their privileges and recorded as events or captured in keystroke logs by Privilege Manager. This report allows you to search for commands that have been recorded as part of events or keystroke logs for a policy group and includes the following information:</p> <ul data-bbox="437 1319 1031 1491" style="list-style-type: none"> <li data-bbox="437 1319 683 1348">• Command name <li data-bbox="437 1366 911 1395">• User who executed the command <li data-bbox="437 1413 1031 1442">• Date and time the command was executed <li data-bbox="437 1460 994 1489">• Host where the command was executed <p data-bbox="384 1516 1273 1545">Use the following report parameters to define details in the report:</p> <ul data-bbox="437 1570 635 1787" style="list-style-type: none"> <li data-bbox="437 1570 635 1599">• Policy Group <li data-bbox="437 1617 603 1646">• Command <li data-bbox="437 1664 528 1693">• Host <li data-bbox="437 1711 603 1740">• Log status <li data-bbox="437 1758 528 1787">• Date

Report	Description
	<p>i NOTE: You can use wildcards in the text string you enter in the Command box, such as * and ?.</p> <p>i NOTE: This report is available when you are logged on as the supervisor or as an Active Directory account in the <i>Manage Sudo Policy</i>, <i>Manage PM Policy</i>, <i>Audit Sudo Policy</i>, or <i>Audit PM Policy</i> roles. You must have an active policy group for Privilege Manager to run this report; you can only include hosts that are joined to a policy group.</p>
Console Access and Permissions	<p>Lists users who have access to the management console based on membership in a console role and the permissions assigned to that role. This report includes the following information:</p> <ul style="list-style-type: none"> • List of roles • List of permissions assigned to each role • List and number of members assigned to each role <p>i NOTE: This report is available when you are logged on as the supervisor or an Active Directory account in the <i>Manage Console Access</i> role. However, when you access this report as supervisor, the management console requires that you authenticate to Active Directory.</p>
Logon Policy for AD User	<p>Identifies the hosts where Active Directory users have been granted log-on permission. This report includes the following information for hosts joined to an Active Directory domain:</p> <ul style="list-style-type: none"> • Total number of hosts where the AD user has access • List of hosts where the AD user has access <p>Specify the Active Directory users to include in the report:</p> <ul style="list-style-type: none"> • All AD users (default) • Select AD user <p>Browse to search Active Directory to locate and select an Active Directory user.</p> <p>i NOTE: The report might show both the Active Directory login name and local user name(s) in the Login Name column for a selected AD user account because an Active Directory user account can have one or more local user accounts mapped to it.</p> <p>i NOTE: Only hosts joined to an Active Directory domain with a Authentication Services 4.x agent are included in this report.</p>

Report	Description
Logon Policy for Unix Host	<p data-bbox="405 271 1347 338">i NOTE: This report is available when you are logged on as an Active Directory account in the <i>Manage Hosts</i> role.</p> <p data-bbox="384 376 1374 472">Identifies the Active Directory users that have been explicitly granted logon permissions for one or more Unix computers. This report includes the following information for hosts joined to an Active Directory domain:</p> <ul data-bbox="437 495 1331 607" style="list-style-type: none"> <li data-bbox="437 495 1331 562">• Host Name, DNS Name or IP Address of the host selected for the report <li data-bbox="437 573 1139 607">• Users that have been granted permission to log on <p data-bbox="384 629 1066 663">Specify the managed hosts to include in the report:</p> <ul data-bbox="437 685 815 763" style="list-style-type: none"> <li data-bbox="437 685 815 719">• All profiled hosts (default) <li data-bbox="437 730 616 763">• Select host <p data-bbox="384 786 1289 853">Browse to locate and select a managed host that is joined to Active Directory.</p> <p data-bbox="405 875 1342 943">i NOTE: This report only includes hosts joined to an Active Directory domain with a Authentication Services 4.x agent.</p> <p data-bbox="405 976 1347 1043">i NOTE: This report is available when you are logged on as an Active Directory account in the <i>Manage Hosts</i> role.</p>
Policy Changes	<p data-bbox="384 1077 1382 1144">Provides details of changes made to a policy for a Privilege Manager policy group. This report includes the following information:</p> <ul data-bbox="437 1167 1366 1379" style="list-style-type: none"> <li data-bbox="437 1167 1126 1200">• Name of the user that made changes to the policy <li data-bbox="437 1211 890 1245">• Version number for the changes <li data-bbox="437 1256 1366 1323">• Time and date the changes were saved and actively used to enforce policy <li data-bbox="437 1335 1066 1368">• Changes made to the policy based on version <p data-bbox="384 1391 671 1424">Select a policy group.</p> <p data-bbox="384 1447 512 1480">Select to:</p> <ul data-bbox="437 1503 1337 1659" style="list-style-type: none"> <li data-bbox="437 1503 868 1536">• Show all changes to the policy <li data-bbox="437 1547 1318 1615">• Show only changes for a specific pmpolicy file (not available for sudo-based policy) <li data-bbox="437 1626 1337 1659">• Show changes to the policy for changes for one or more revisions <p data-bbox="405 1682 1385 1859">i NOTE: This report is available when you are logged on as the supervisor or as an Active Directory account in the <i>Manage Sudo Policy</i>, <i>Manage PM Policy</i>, <i>Audit Sudo Policy</i>, or <i>Audit PM Policy</i> roles. You must have an active policy group for Privilege Manager to run this report; you can only include hosts that are joined to a policy group.</p>

Product licenses usage reports

Table 26: Product licenses usage reports

Report	Description
Product License Usage	<p>Provides a summary of all licensing information. This report includes the following information for hosts managed by the console:</p> <ul style="list-style-type: none">• Product• Purchased licenses• Used licenses

Use Authentication Services PowerShell

Authentication Services includes PowerShell modules which provide a "scriptable" interface to many Authentication Services management tasks. You can access a customized PowerShell console from the Control Center **Tools** navigation link.

You can perform the following tasks using PowerShell cmdlets:

- Unix-enable Active Directory users and groups
- Unix-disable Active Directory users and groups
- Manage Unix attributes on Active Directory users and groups
- Search for and report on Unix-enabled users and groups in Active Directory
- Install product license files
- Manage Authentication Services global configuration settings
- Find Group Policy objects with Unix/Mac OS X settings configured

Using the Authentication Services PowerShell modules, it is possible to script the import of Unix account information into Active Directory.

Unix-enable a user and user group

To Unix-Enable a user and user group

1. From the Control Center, navigate to **Tools | Authentication Services**.
2. Click **Authentication Services PowerShell Console**.

NOTE: The first time you launch the PowerShell Console it asks you if you want to run software from this untrusted publisher. Enter A at the PowerShell prompt to import the digital certificate to your system as a trusted entity. Once you have done this you will never be asked this question again on this machine.

3. At the PowerShell prompt, enter the following:

```
Enable-QasUnixGroup UNIXusers | Set-QasUnixGroup -GidNumber 1234567
```

NOTE: You created the UNIXusers group in a previous exercise. (See [Add an Active Directory group account on page 74.](#))

Unix attributes are generated automatically based on the Default Unix Attributes settings that were configured earlier and look similar to the following:

```
ObjectClass           : group
DistinguishedName     : CN=UNIXusers,CN=Users,DC=example,DC=com
ObjectGuid            : 71aaa88-d164-43e4-a72a-459365e84a25
GroupName             : UNIXusers
UnixEnabled           : True
GidNumber             : 1234567
AdsPath               : LDAP://windows.example.com/CN=UNIXusers,CN=Users,
                      DC=example,DC=com
CommonName            : UNIXusers
```

4. At the PowerShell prompt, to Unix-enable an Active Directory user using the default Unix attribute values, enter:

```
Enable-QasUnixUser ADuser | Set-QasUnixUser -PrimaryGidNumber 1234567
```

The Unix properties of the user display:

```
ObjectClass           : user
DistinguishedName     : CN=ADuser,CN=Users,DC=example,DC=com
ObjectGuid            : 5f83687c-e29d-448f-9795-54d272cf9f25
UserName              : ADuser
UnixEnabled           : True
UidNumber             : 80791532
PrimaryGidNumber      : 1234567
Gecos                 :
HomeDirectory         : /home/ADuser
LoginShell             : /bin/sh
AdsPath               : LDAP://windows.example.com/CN=ADuser,CN=Users,
                      DC=example,DC=com
CommonName            : ADuser
```

5. To disable the ADuser user for Unix login, at the PowerShell prompt enter:

```
Disable-QasUnixUser ADuser
```

NOTE: To completely clear all Unix attribute information, enter

```
Clear-QasUnixUser ADuser
```

Now that you have Unix-disabled the user, that user can no longer log into systems running the Authentication Services agent.

6. From the Control Center, under "Login to remote host", enter:
 - the Unix host name in the **Host name** box
 - the Active Directory user name, **ADuser**, in the **User name** box
 and click **Login** to log onto the Unix host with your Active Directory user account. A PuTTY window displays.

NOTE: PuTTY attempts to log in using Kerberos, but will fail over to password authentication if Kerberos is not enabled or properly configured for the remote SSH service.

7. Enter the password for the Active Directory user account. You will receive a message that says, "Access denied".

PowerShell cmdlets

Authentication Services supports the flexible scripting capabilities of PowerShell to automate administrative, installation, and configuration tasks. A wide range of new PowerShell cmdlets are included in Authentication Services.

Table 27: PowerShell cmdlets

cmdlet Name	Description
Add-QasLicense	Installs an Authentication Services license file in Active Directory. Licenses installed this way are downloaded by all Unix clients.
Clear-QasUnixGroup	Clears the Unix identity information from group object in Active Directory. The group is no longer Unix-enabled and will be removed from the cache on the Authentication Services Unix clients.
Clear-QasUnixUser	Clears the Unix identity information from a user object in Active Directory. The user is no longer Unix-enabled will be removed from the cache on the Authentication Services Unix clients.
Disable-QasUnixGroup	"Unix-disables" a group and will be removed from the cache on the Authentication Services Unix clients. Similar to Clear-QasUnixGroup except the Unix group name is retained.
Disable-QasUnixUser	Removes an Active Directory user's ability to log in on Unix hosts. (The user will still be cached on the Authentication Services Unix clients.)
Enable-QasUnixGroup	Enables an Active Directory group for Unix by giving a Unix GID number. The GID number is automatically

cmdlet Name	Description
	generated.
Enable-QasUnixUser	Enables an Active Directory user for Unix. The required account attributes UID number, primary GID number, GECOS, login shell and home directory are generated automatically.
Get-QasConfiguration	Returns an object representing the Authentication Services application configuration data stored in Active Directory.
Get-QasGpo	Returns a set of objects representing GPOs with Unix and/or Mac OS X settings configured. This cmdlet is in the <i>Quest.AuthenticationServices.GroupPolicy</i> module.
Get-QasLicense	Returns objects representing the Authentication Services product licenses stored in Active Directory.
Get-QasOption	Returns a set of configurable global options stored in Active Directory that affect the behavior of Authentication Services.
Get-QasSchema	Returns the currently configured schema definition from the Authentication Services application configuration.
Get-QasSchemaDefinition	Returns a set of schema templates that are supported by the current Active Directory forest.
Get-QasUnixGroup	Returns an object that represents an Active Directory group as a Unix group. The returned object can be piped into other cmdlets such as <i>Clear-QasUnixGroup</i> or <i>Enable-QasUnixGroup</i> .
Get-QasUnixUser	Returns an object that represents an Active Directory user as a Unix user. The returned object can be piped into other cmdlets such as <i>Clear-QasUnixUser</i> or <i>Enable-QasUnixUser</i> .
Get-QasVersion	Returns the version of Authentication Services currently installed on the local host.
Move-QasConfiguration	Moves the Authentication Services application configuration information from one container to another in Active Directory.
New-QasAdConnection	Creates an object that represents a connection to Active Directory using specified credentials. You can pass a connection object to most Authentication Services cmdlets to execute commands using different credentials.

cmdlet Name	Description
New-QasArsConnection	Creates an object that represents a connection to an Active Roles Server using the specified credentials. You can pass a connection object to most Authentication Services cmdlets to execute commands using different credentials.
New-QasConfiguration	Creates a default Authentication Services application configuration in Active Directory and returns an object representing the newly created configuration.
Remove-QasConfiguration	Accepts a Authentication Services application configuration object as input and removes it from Active Directory. This cmdlet produces no output.
Remove-QasLicense	Accepts an Authentication Services product license object as input and removes the license from Active Directory. This cmdlet produces no output.
Set-QasOption	Accepts an Authentication Services options set as input and saves it to Active Directory.
Set-QasSchema	Accepts an Authentication Services schema template as input and saves it to Active Directory as the schema template that will be used by all Authentication Services Unix clients.
Set-QasUnixGroup	Accepts a Unix group object as input and saves it to Active Directory. You can also set specific attributes using command line options.
Set-QasUnixUser	Accepts a Unix user object as input and saves it to Active Directory. You can also set specific attributes using command line options.

Authentication Services PowerShell cmdlets are contained in PowerShell modules named *Quest.AuthenticationServices* and *Quest.AuthenticationServices.GroupPolicy*. Use the `Import-Module` command to import the Authentication Services commands into an existing PowerShell session.

Change Auditor for Authentication Services

Change Auditor for Authentication Services allows you to track changes and send alerts on:

- Changes to Active Directory objects and attributes
- Changes to Unix and Mac OS X settings in Group Policy Objects
- Changes to Product settings and configuration

Install Change Auditor for Authentication Services

To install Change Auditor for Authentication Services

1. Insert the Authentication Services distribution media.
The Autorun *Home* page displays.
 - 1 **NOTE:** If the Autorun *Home* page does not display, navigate to the root of the distribution media and double-click **autorun.exe**.
2. Click the **Setup** tab and select **Change Auditor for Authentication Services**.
The Change Auditor for Authentication Services for Active Directory web page opens.
3. Click the **Download** on the left navigation panel.
4. Follow the online instructions to gain access to the *Trial Download* page.
5. From the *Trial Download: Change Auditor for Active Directory* page, click the **Installation Guide** link.
6. Read the *Change Auditor Installation Guide* to obtain detailed steps for installing Authentication Services Defender.

One Identity Defender

One Identity Defender, another One Identity product, provides strong authentication functionality that makes it possible for an Active Directory user to use a hardware or software token to authenticate to Unix, Linux, or Mac OS X platforms.

Install Defender

In order to use strong authentication you must download and install Defender.

- 1 **NOTE:** Defender installation requires a license file. A fully-functional 25-user license for it is included with Authentication Services.

To install Defender

1. Insert the Authentication Services distribution media.
The Autorun *Home* page displays.
 - 1 **NOTE:** If the Autorun *Home* page does not display, navigate to the root of the distribution media and double-click **autorun.exe**.
2. From the *Home* page, click the **Setup** tab.
3. From the *Setup* tab, click **One Identity Defender**.
The One Identity Defender web page opens.

4. Click the **Download** on the left navigation panel.
5. Follow the online instructions to gain access to the *Trial Download* page.
6. From the *Trial Download: Defender* page, click the **Defender Documentation Archive** link.
7. Read the *Defender Installation Guide* to obtain detailed steps for installing Authentication Services Defender.
8. Once you have installed One Identity Defender, see the *One Identity Defender Integration Guide* located in the Control Center **Tools** page, or in the docs directory of the Authentication Services Installation media, for detailed configuration instructions about integrating Authentication Services Defender with Authentication Services.

Troubleshooting

To help you troubleshoot, One Identity recommends the following resolutions to some of the common problems you might encounter as you deploy and use Authentication Services.

Getting help from technical support

If you are unable to determine the solution to a problem, contact Technical Support for help.

i | **NOTE:** For more information, see [About us on page 118](#).

Before you contact Support, please collect the following information:

1. Take a system information snapshot. To do this, run the following command as root:

```
/opt/quest/libexec/vas/scripts/vas_snapshot.sh
```

This produces an output file in /tmp.

2. Make note of the Unix attributes for the user that cannot log in (if applicable). To do this, capture the output from the following commands:

```
vastool -u host/ attrs <username>  
id <username>
```

i | **NOTE:** Depending on your platform, you may need to run `id -a` instead of `id`.

3. Copy the text from any error messages that you see.
4. Save the results of running a "double su". To do this, log in as root and run `su <username>` note any error messages. Then run `su <username>` again and note any error messages.

Once you have collected the information listed above, contact Support at <https://support.oneidentity.com/authentication-services/>.

Disaster recovery

Since Authentication Services relies on Active Directory, follow Microsoft's best practices for keeping the database highly available. The Management Console for Unix and other administration tools, are not critical to the operation of Authentication Services and can quickly be reinstalled from scratch if needed.

Long startup delays on Windows

You may experience long delays (over a minute) when starting the Authentication Services Windows installer or certain Windows management tools such as Control Center. All Authentication Services Windows binaries are Authenticode-signed so that you can be sure that the binaries are authentic and have not been tampered with. This problem occurs when the .NET runtime attempts to verify the Authenticode signature by checking against certificate revocation lists (CRLs) at cr1.microsoft.com. If this site cannot be reached, the .NET framework check will time out (up to 60 seconds). This timeout occurs every time a signed assembly is loaded which can lead to very long load times. You can fix this problem by allowing access to cr1.microsoft.com. See Microsoft KB article [Microsoft KB article 936707](#) for background information.

If the computer is not connected to the internet, you can disable CRL checks for the entire system in Internet Explorer. Go to **Options**, select the **Advanced** tab, under *Settings* clear the **Check for publisher's certification revocation** option.

It is also possible to specify a `generatePublisherEvidence` element in an `<app>.exe.config` that will disable CRL checks for the specific application that you are running. Keep in mind that if you are using Authentication Services components in PowerShell or MMC, you would need to add this configuration for the `powershell.exe.config` and/or `mmc.exe.config`. Refer to [<generatePublisherEvidence> Element](#) for details.

Pointer Record updates are rejected

If Pointer Record (PTR) updates are being rejected, it may be because the DHCP server is doing the update already. Refer to the documentation for the DHCP server used in your environment. The Microsoft DHCP server does updates on behalf of the host and this is controlled by the FQDN option. Please refer to the Microsoft Active Directory DNS/DHCP documentation.

Resolving DNS problems

It is imperative that DNS is correctly configured. Authentication Services relies on DNS in order to locate domain controllers. Follow these steps to verify that domain controllers can be located using DNS:

1. Use `dig` to test whether your DNS configuration can locate a domain controller. Enter the following at the Unix command prompt, replacing `<DNS Domain Name>` with your Active Directory DNS domain name:

```
dig -t any _ldap._tcp.dc._msdcs.<DNS Domain Name>
```

If DNS is configured correctly, you will see a list of domain controllers for your domain. If not, work with your DNS administrator to resolve the issue.

2. Use `dig` to test whether you can locate a domain controller in your site. Enter the following at the Unix command prompt, replacing `<Site Name>` with the name of your Active Directory site and `<DNS Domain Name>` with your Active Directory DNS domain name.

```
dig -t _ldap._tcp.<Site Name>._sites.dc._msdcs.<DNS Domain Name>
```

If DNS is configured correctly, you will see a list of domain controllers for your site. If not, work with your DNS administrator to resolve the issue.

It is possible to work around DNS problems using the `vastool join` command to specify the domain controller host name on the command line. Authentication Services can work without DNS configured as long as the forward lookup in the `/etc/hosts` file exists. The forward lookup resolves the domain controller host name to an IP address.

You can test this on Linux by firewalling DNS (port 53) with `iptables`. Make sure that you have an entry for your domain controller in `/etc/hosts` then as root, enter the following commands replacing `<administrator>` with the name of an Active Directory administrator `<DNS Domain Name>` with your Active Directory DNS domain name and `<DC Host Name>` with the host name of your domain controller:

```
iptables -A INPUT -p udp --dport 53 -j DROP
iptables -A OUTPUT -p udp --dport 53 -j DROP
/opt/quest/bin/vastool -u <administrator> join <DNS Domain Name> <DC Host Name>
```

Resolving preflight failures

If one of the preflight checks fail, preflight prints a suggested resolution. The following table provides additional problem resolution information. The checks are listed by the associated command-line flags.

Table 28: Install checks

Preflight Option	Check	Resolution
--os-patch	Checks for supported operating system and correct operating system patches.	Install the Authentication Services agent on a supported operating system that has the required operating system patches. Click www.oneidentity.com/products/authentication-services/ to view a list of supported Unix and Linux platforms that run Authentication Services.
--disk-space	Checks for sufficient disk space to install Authentication Services.	Free up more disk space. Authentication Services requires disk space in /opt, /etc, and /var to install.

Table 29: Join checks

Preflight Option	Check	Resolution
--tld	Checks that the DNS Top Level Domain (TLD) is not '.local'	Ensure that mDNS is disabled in /etc/nsswitch.conf or use a domain other than .local.
--hostname	Checks that the hostname of the system is not 'localhost'	One Identity recommends that you have a unique hostname in order to maintain uniqueness of computer names in Active Directory. Another option is to ignore this check and use -n computer_name when joining. (See the <i>vastool man page</i> for more information.)
--name-service	Checks if the name service is configured to use DNS.	Ensure your host is configured to use DNS properly. Consult your platform documentation to determine the proper method to enable DNS for hostname resolution. See Resolving DNS problems on page 101 for solutions.
--host-resolve	Ensures that the host can resolve names using DNS.	Check your /etc/resolv.conf file to ensure that name server entries are correct and reachable. Make sure that UDP port 53 (DNS) is open. This check attempts to resolve the domain name and can fail if your DNS configuration is invalid. This check expects to find properly formatted IPv4 addresses. Invalid or unreachable name server entries will cause delays even though the check will pass if at least one valid name server is found. If you notice delays when running this check, make sure that your name server configuration does not reference invalid name servers. See Resolving DNS problems on page 101 for

Preflight Option	Check	Resolution
		solutions.
--srv-records	Checks for a nameserver that has the appropriate DNS SRV records for Active Directory	SRV records advertise various Active Directory services. Your configured name server must provide SRV records in order for Authentication Services to take advantage of automatic detection and fail over. Ensure that UDP port 53 (DNS) is open.
--dc	Detects a writable domain controller with UDP port 389 open.	<p>If a domain controller is passed on the preflight command line, <code>preflight</code> checks that UDP port 389 is open and that the domain controller is writable. In this case, you may be able to specify a different domain controller.</p> <p>If you do not pass in the name of a domain controller, this check attempts to locate a writable domain controller using DNS SRV records. Ensure that your DNS SRV records are up to date in the configured DNS server. Authentication Services can work with read-only domain controllers, but the computer object must have already been created with the proper settings in Active Directory.</p>
--site	Detects Active Directory site, if available.	This check warns you if Authentication Services was unable to locate an Active Directory site based on your computer's network address. A site configuration is not necessary but Authentication Services performs better if site information is configured in Active Directory. To resolve this problem, configure a site in Active Directory.
--kerberos-password	Checks if TCP port 464 is open for Kerberos kpasswd.	Ensure that TCP port 464 (<code>kpasswd</code>) is open. This port must be open in order for Authentication Services to set the computer object's password.
--kerberos-traffic	Checks if UDP port 88 and TCP port 88 are open for Kerberos traffic.	These ports are the main Kerberos communication channels; they must be open for Authentication Services to authenticate to Active Directory. By default Authentication Services uses TCP, but may be configured to prefer UDP.
--ldap	Checks if TCP port 389 is open for LDAP.	This port must be open for Authentication Services to communicate with domain controllers using LDAP. This communication is GSS SASL encrypted and signed.

Preflight Option	Check	Resolution
--global-catalog	Checks whether the Global Catalog is accessible on TCP port 3268.	Authentication Services can function in a limited way without a global catalog server, however, Authentication Services will be unable to resolve Active Directory users and groups from domains in the forest other than the one to which the host is joined. In addition, some searches may be slower. Make sure that TCP port 3268 (global catalog) is open and that you have configured at least one domain controller as a global catalog and that the global catalog server is up and reachable.
--timesync	Checks the machine's time is not skewed too far from Active Directory.	If the time difference between the Unix host and the domain controller is too large, Kerberos traffic will not succeed. You can usually resolve this failure by running <code>vastool timesync</code> to synchronize time with the Active Directory domain. Port 123 UDP must be open in order to synchronize time with the domain controller. This check automatically synchronizes the time if you specify the <code>-S</code> option and run the application with root permissions.
--app-configuration	Checks for the Authentication Services application configuration in Active Directory.	This check fails if you have not configured the Active Directory forest for Authentication Services. Use Control Center (Windows) to create the necessary application configuration. This check can also fail due to an invalid username/password or if there is a time synchronization problem between the Unix host and the domain controller.
--rodc	Checks against the given domain controller even if it is read-only, instead of selecting another domain controller.	The <code>--rodc</code> option runs preflight against the given domain controller instead of picking a writable DC. The <code>--rodc</code> check affects the <code>--kerberos-*</code> and <code>--ldap</code> checks. If the <code>--rodc</code> check fails, resolve preflight port check failures.

NOTE: If you get a message that says, "Unable to locate Authentication Services Application Configuration", you can ignore that error and proceed with the Authentication Services installation. The Authentication Services Active Directory Configuration Wizard starts automatically to help you configure Active Directory for Authentication Services the first time you start the Control Center.

Table 30: Post-join checks

Preflight Option	Check	Resolution
--ms-cifs	Checks if TCP port 445 is open for Microsoft Directory Services CIFS traffic.	In order to use Group Policy on Unix, this port must be open to allow Authentication Services to use the CIFS protocol to download Group Policy objects from domain controllers.

System optimization

Kerberos works best with a random number generator package installed on the operating system. If one is not installed, it will use a potential slow fallback entropy generating system.

HP-UX

HP provides a `/dev/random` driver for hp-UX 11i (11.11), named 'KRNG11I'. It is available, for free, from the KRNG11I depot. You can check if this is already installed by running:

```
$ swlist KRNG11I
```

For older versions (hp-UX 11.00), an open-source implementation of `/dev/random` is available from "[random](#)" *DLKM (dynamically loadable kernel module) for HP-UX* .

Solaris

Entropy is generally obtained from `/dev/random` which is an interface to a kernel random source. On Solaris 8, the `/dev/random` driver is provided in the following patches from [ORACLE](#):

- solaris8/sparc: OS patch 112438
- solaris8/x86: OS patch 112439

Time synchronization problems

Kerberos is a time-sensitive protocol. Your Unix hosts must be synchronized within five minutes of your Active Directory domain controllers. Run the following command as root to have Authentication Services synchronize the local time with Active Directory:

```
vastool timesync
```

Unable to install or upgrade

The most common installation or upgrade failure is that the Unix host cannot read the Authentication Services application configuration in Active Directory. Ensure that you have followed the instructions in [Configure Active Directory for Authentication Services on page 29](#) and that the configuration has been created successfully.

During an upgrade you may see an error that Authentication Services cannot upgrade because the application configuration cannot be located. If you previously joined to a specific domain controller Authentication Services disabled DNS SRV record lookups. This means that Authentication Services cannot resolve other domains in the forest and may be unable to locate the application configuration. In this case you must ensure that the domain controller you specified is a global catalog. Otherwise, you must create the Authentication Services application configuration in the domain that you join or you must properly configure DNS to return SRV records and join normally, rather than specifying a domain controller when you join.

For more information, see [About Active Directory configuration on page 31](#).

Unable to join the domain

If you are unable to join the domain, run the `preflight` utility to validate your environment. (For more information, see [The Authentication Services pre-installation diagnostic tool on page 51](#).)

Then, verify the following:

- Check that the Active Directory account specified during join has rights to join the computer to the domain.
- Check that the Unix host is able to properly resolve the domain name through DNS.

If you are joining to a specific domain controller you must ensure that Authentication Services can locate and read the configuration information in Active Directory. You should do one of the following:

- Make sure the domain controller you specify is a global catalog.
- Create the Authentication Services application configuration in the domain to which you are joining.

[For more information, see About Active Directory configuration on page 31.](#)

- Properly configure DNS to return `srv`-records and avoid joining to a specific domain controller.

Unable to log in

If you are unable to log in as an Active Directory user after installing, check the following:

1. Log in as root on the Unix host.
2. Check the status of the Authentication Services subsystems. To do this, run the following command:

```
vastool status
```

Correct any errors reported by the status command, then try logging in again.

3. Ensure the user exists locally and is allowed to log in. To check this, run the following command:

```
vastool user checklogin <username>
```

The output displays whether the user is a known Active Directory user. If not, you may need to map the user to an Active Directory account or Unix-enable the Active Directory account. If the user is known, an access control rule may prevent them from logging in. The output of the command displays which access control rules are in effect for the user.

You may need to restart window managers such as `gdm` in order for the window manager to reload NSS modules. Until the window manager reloads the NSS configuration, you will be unable to log in with an Active Directory user. Other services such as `cron` may also be affected by NSS changes. If you are unsure which services need to be reloaded, reboot the system.

NOTE:

If you are configuring on VMware ESX Server vSphere (ESX 4.0) the reason you can not log in may be related to access control issues. Please refer to *Configuring Access Control on ESX 4* in the *Authentication Services Administration Guide*.

vasypd has unsatisfied dependencies

If you receive the following error message while installing the Authentication Services `vasypd` Unix component, the `rpcbind` service may not be enabled.

```
svcadm: Instance "svc:/quest/vas/vasypd:default" has unsatisfied dependencies.  
Error 4 starting vasypd
```

To enable the `rpcbind` service

1. Check the dependencies of `vasypd`:

```
# svcs -d quest/vas/vasypd  
STATE          STIME          FMRI
```

```
disabled    Sep_14    svc:/network/rpc/bind:default
online      Sep_14    svc:/milestone/single-user:default
online      Sep_14    svc:/system/filesystem/local:default
```

2. If rpcbind is disabled, run this command to enable it:

```
# /usr/sbin/svcadm enable -s /network/rpc/bind
```

3. Run the following command to start vasydpd:

```
# /etc/init.d/vasypd start
```

Enterprise package deployment

This section details how to install, upgrade, and uninstall the Authentication Services agent on supported platforms in an enterprise environment using platform package management tools.

Install the Authentication Services agent package

To install the Authentication Services agent package

1. Log in and open a root shell.
2. Mount the installation DVD and run the appropriate command.
(See **Notes** below for additional configuration information.)

Table 31: Authentication Services: Agent installation command

Platform	Command
Linux x86 - RPM	<code># rpm -ihv /<mount>/client/linux-x86/vasclnt- <version>-<build>.i386.rpm</code>
Linux x64 - RPM	<code># rpm -ihv /<mount>/client/linux-x86_64/vasclnt- <version>-<build>.x86_64.rpm</code>
Linux x86 - DEB	<code># dpkg -i /<mount>/client/linux-x86/vasclnt- <version>-<build>.i386.deb</code>
Linux x64 - DEB	<code># dpkg -i /<mount>/client/linux-x86_64/vasclnt- <version>-<build>_amd64.deb</code>
Linux s390	<code># rpm -ihv /<mount>/client/linux-s390/vasclnt- <version>-<build>.s390.rpm</code>
Linux s390x	<code># rpm -ihv /<mount>/client/linux-s390x/vasclnt-</code>

Platform	Command
	<code><version>-<build>.s390x.rpm</code>
VMware ESX 3.x	<code># rpm -ihv /<mount>/client/linux-x86/vasclnt-<version>-<build>.i386.rpm</code>
VMware ESX 4.1	<code># rpm -ihv /<mount>/client/linux-x86_64/vasclnt-<version>-<build>.x86_64.rpm</code>
SLES 8 PPC	<code># rpm -ihv /<mount>/client/linux-glibc22-ppc64/vasclnt-glibc22-<version>-<build>.ppc64.rpm</code>
SLES 9 PPC	<code># rpm -ihv /<mount>/client/linux-glibc23-ppc64/vasclnt-glibc23-<version>-<build>.ppc64.rpm</code>
Solaris 8-10 x86	<code># pkgadd -d /<mount>/client/solaris8-x86/vasclnt_SunOS_5.8_i386-<version>-<build>.pkg vasclnt</code>
Solaris 10 x64	<code># pkgadd -d /<mount>/client/solaris10-x64/vasclnt_SunOS_5.10_i386-<version>-<build>.pkg vasclnt</code>
Solaris 8-10 SPARC	<code># pkgadd -d /<mount>/client/solaris8-sparc/vasclnt_SunOS_5.8_sparc-<version>-<build>.pkg vasclnt</code>
HP-UX PA-RISC 11i v1 (B.11.11)	<code># swinstall -s /<mount>/client/hpux-pa/vasclnt_9000-<version>-<build>.depot vasclnt</code>
HP-UX PA-RISC 11i v2 (B.11.23), 11i v3 (B.11.31)	<code># swinstall -s /<mount>/client/hpux-pa-11v1/vasclnt_hpux-11.11-<version>-<build>.depot vasclnt</code>
HP-UX IA64 11i v1.6 (B.11.22), 11i v2 (B.11.23), 11i v3 (B.11.31)	<code># swinstall -s /<mount>/client/hpux-ia64/vasclnt_ia64-<version>-<build>.depot vasclnt</code>
AIX 4.3.3	<code># installp -acXd /<mount>/client/aix-43/vasclnt.AIX_4.3.<version>-<build>.bff all</code>
AIX 5.1 – 5.2	<code># installp -acXd /<mount>/client/aix-51/vasclnt.AIX_5.1.<version>-<build>.bff all</code>
AIX 5.3 – 6.1	<code># installp -acXd /<mount>/client/aix-53/vasclnt.AIX_5.3.<version>-<build>.bff all</code>
Mac OS X	<code>/usr/sbin/installer -pkg '/<mount>/VAS.mpkg/Contents/Packages/vasclnt.pkg' -target /</code>

Additional Configuration Information:

- To enable Authentication Services authentication for all services you must restart all services that require Authentication Services authentication or restart the system.
- **Linux - RPM:** The x86_64 Authentication Services rpm contains 64-bit and 32-bit libraries, and has an RPM dependency on both the 32-bit libpam library and the 64-bit libpam library. If the 64-bit Linux operating system on which you are installing Authentication Services does not have any 32-bit supporting libraries installed, use the `-- nodeps` RPM flag to force the installation and avoid error messages about missing dependencies.
- **VMware:** You must enter the following additional command, to configure the VMware Authentication Services:
`vastool configure pam vmware-authd`
- **Solaris:** For information on Solaris 10 Zones support and installation, see [Solaris 10 zones/containers support on page 116](#).

In certain situations `pkgadd` requests additional information. Respond appropriately for your system configuration. Initialization scripts that are part of the `vasc1nt` package run during installation to help configure the system.

To install the Authentication Services `vasypd` Unix component on Solaris 10, you must have the `rpcbind` service enabled on the host. (See [vasypd has unsatisfied dependencies on page 107](#) for more information.)

- **HP-UX:** Authentication Services requires that the Unix host system clock be synchronized with the Active Directory server's system clock. By default, HP-UX uses `xntpd` for time services. To properly synchronize the system clocks either configure `xntpd` to sync with a Domain Controller, or disable `xntpd` to allow Authentication Services to synchronize the system time. Consult the `xntpd` documentation for information on disabling `xntpd` and configuring `xntpd`.

You must reboot the HP-UX machine to ensure that all of the new files are installed. HP-UX does not allow you to overwrite files that are in use—this is done as part of the boot sequence.

- **Mac OS X:** To install from the command line, you must first mount the Authentication Services DMG image file. On Mac OS X enter:

```
hdiutil attach <media>/client/macos-106/VAS-<version>.dmg
```

Authentication Services agent upgrade commands

To upgrade the Authentication Services agent package

1. Log in and open a root shell.
2. Mount the installation DVD and run the appropriate command.
(See **Notes** for additional configuration information.)

Table 32: Authentication Services: Agent upgrade commands

Platform	Command
Linux x86 - RPM	# rpm -Uhv /<mount>/client/linux-x86/vasclnt- <version>-<build>.i386.rpm
Linux x64 - RPM	# rpm -Uhv /<mount>/client/linux-x86_64/vasclnt- <version>-<build>.x86_64.rpm
Linux x86 - DEB	# dpkg -i /<mount>/client/linux-x86/vasclnt- <version>-<build>.i386.deb
Linux x64 - DEB	# dpkg -i /<mount>/client/linux-x86_64/vasclnt- <version>-<build>_amd64.deb
Linux s390	# rpm -Uhv /<mount>/client/linux-s390/vasclnt- <version>-<build>.s390.rpm
Linux s390x	# rpm -Uhv /<mount>/client/linux-s390x/vasclnt- <version>-<build>.s390x.rpm
VMware ESX 3.x	# rpm -Uhv /<mount>/client/linux-x86/vasclnt- <version>-<build>.i386.rpm
VMware ESX 4.1	# rpm -Uhv /<mount>/client/linux-x86_64/vasclnt- <version>-<build>.x86_64.rpm
SLES 8 PPC	# rpm -Uhv /<mount>/client/linux-glibc22- ppc64/vasclnt-glibc22-<version>-<build>.ppc64.rpm
SLES 9 PPC	# rpm -Uhv /<mount>/client/linux-glibc23- ppc64/vasclnt-glibc23-<version>-<build>.ppc64.rpm
Solaris 8-10 x86	# pkgadd -d /<mount>/client/solaris8-x86/vasclnt_ SunOS_5.8_i386-<version>-<build>.pkg vasclnt
Solaris 10 x64	# pkgadd -d /<mount>/client/solaris10-x64/vasclnt_ SunOS_5.10_i386-<version>-<build>.pkg vasclnt
Solaris 8-10 SPARC	# pkgadd -d /<mount>/client/solaris8-sparc/vasclnt_ SunOS_5.8_sparc-<version>-<build>.pkg vasclnt
HP-UX PA-RISC 11i v1 (B.11.11)	# swinstall -s /<mount>/client/hpux-pa/vasclnt_9000- <version>-<build>.depot vasclnt
HP-UX PA-RISC 11i v2 (B.11.23), 11i v3 (B.11.31)	# swinstall -s /<mount>/client/hpux-pa-11v1/vasclnt_ hpux-11.11-<version>-<build>.depot vasclnt
HP-UX IA64 11i v1.6 (B.11.22), 11i v2 (B.11.23), 11i v3 (B.11.31)	# swinstall -s /<mount>/client/hpux-ia64/vasclnt_ ia64-<version>-<build>.depot vasclnt

Platform	Command
AIX 4.3.3	# installp -acXd /<mount>/client/aix-43/vasclnt.AIX_4.3.<version>-<build>.bff all
AIX 5.1 – 5.2	# installp -acXd /<mount>/client/aix-51/vasclnt.AIX_5.1.<version>-<build>.bff all
AIX 5.3 – 6.1	# installp -acXd /<mount>/client/aix-53/vasclnt.AIX_5.3.<version>-<build>.bff all
Mac OS X	/usr/sbin/installer -pkg '/<mount>/VAS.mpkg/Contents/Packages/vasclnt.pkg' -target /

Additional Configuration Information:

- i **NOTE:** During the upgrade, vasd reloads and updates its user and group cache. To restart the Authentication Services caching service, see [Restarting Authentication Services services on page 114](#).
- i **NOTE:** If you are using the licensed version of the Authentication Services agent earlier than 3.0, see [Licensing Authentication Services on page 56](#) for licensing instructions.

- 1 **NOTE: VMware:** VMware provides a Host Update Utility to upgrade an ESX 3.5 agent to 4.0, but if Authentication Services is left installed and configured during the procedure, the machine will be inaccessible after the upgrade. This is because the previous 3.5 installation is pushed aside and mounted under the `/esx3-installation` directory, but all the key configuration files, like `/etc/nsswitch.conf` and the `pam.d` directory, are preserved.

If Authentication Services is still configured in those files it leaves the machine in a bad state. Because of this, One Identity recommends that you uninstall Authentication Services before attempting to upgrade to ESX 4.0. In the *vSphere Upgrade Guide*, VMware warns that "no third-party management agents or third-party software applications are migrated," but it does not explicitly say they should be uninstalled prior to upgrade.

Should you accidentally leave Authentication Services installed or configured during the upgrade, use the following steps to fix the machine:

1. Boot into single user mode
2. Copy `/etc/pam.d/vmware-authd.esx4` over `/etc/pam.d/vmware-authd` (backup `vmware-authd` first if desired)
3. Copy `/etc/pam.d/system-auth-generic.esx4` over `/etc/pam.d/system-auth-generic`
4. Remove "vas4" from the `passwd`, `group`, and any other configured lines in `nsswitch.conf`
5. Reboot the machine--the machine should now be accessible
6. Install the `linux-x86_64Authentication Services` packages

- 1 **NOTE: Solaris:** The `-a vasclient-defaults` option specifies an alternative default file for `pkgadd` administrative options that allows `pkgadd` to overwrite an existing package with a new package.

`pkgadd` does not support the concept of upgrading a package, so this allows you to upgrade without having to rejoin your machine to the Active Directory domain, or uninstalling the old version first.

- 1 **NOTE: HP-UX:** Reboot the HP-UX machine to ensure that all of the new files are installed. HP-UX does not allow you to overwrite files that are in use—this is done as part of the boot sequence.

Restarting Authentication Services services

1. The method for restarting services varies by platform:
 - a. To restart Authentication Services on Linux or Solaris, enter:
`/etc/init.d/vasd restart`

b. To restart Authentication Services on HP-UX, enter:

```
/sbin/init.d/vasd restart
```

c. To restart Authentication Services on AIX, enter:

```
stopsrc -s vasd  
startsrc -s vasd
```

NOTE: Due to library changes between the Authentication Services 3.x and 4.1, One Identity recommends that you restart all long-lived processes that use Authentication Services data to force a reload of the newer libraries. For example, you must restart cron.

Uninstall the Authentication Services agent packages

To uninstall the Authentication Services agent packages

1. Log in and open a root shell.
2. Run the following commands to remove the packages.
(See **Notes** for additional configuration information.)

Table 33: Authentication Services: Agent uninstall commands

Package	Command
RPM	# rpm -e vaslnt
DEB	# dpkg -r vaslnt
Solaris	# pkgrm vaslnt
HP-UX	# swremove vaslnt
AIX	# installp -u vaslnt
Mac OS X	/<mount>/Uninstall.app/Contents/MacOS/Uninstall' --console --force vaslnt

Additional Configuration Information:

- **Linux:** The `rpm -e vaslnt` and the `dpkg -r vaslnt` commands run scripts that halt the daemon, unconfigure Authentication Services, flush and delete the Authentication Services cache before finally removing the files.

- **HP-UX:** The `swremove vasclnt` command does not clean up the empty directories that the `vasclnt` package used. In order to clean these up, manually remove the `/opt/quest` directory after you uninstall.

Solaris 10 zones/containers support

Sun introduced Zones (or containers) in Solaris 10. Zones is a partitioning technology used to virtualize operating system services and provide an isolated and secure environment for running applications. There are two types of non-global zone root filesystem models:

- sparse root
- whole root

The sparse root zone model optimizes the sharing of objects while the whole root zone model provides the maximum configurability. Additional information on Solaris 10 and Zones can be found at www.sun.com.

Authentication Services and Solaris 10 Zones installation guidelines

To install Authentication Services in a Solaris 10 Zones configuration

- In Solaris 10 Zones, only the global zone is permitted to do time synchronization. Therefore, if you want to run Authentication Services in "any" Solaris Zone configuration, you must `timesync` the Global Zone with Active Directory. Time synchronization is a requirement of the Kerberos protocol and since Authentication Services is built on Kerberos, Authentication Services also has this requirement.
- The same version of Authentication Services should be installed in any combination of global, whole root, and sparse root zone configurations.
- To disable time synchronization for Authentication Services on the sparse zone, run the below command:

```
vastool configure vas vasd timesync-interval 0
```

- The following symlinks must exist in the global zone in order for the sparse zones to work correctly:

- `/usr/lib/security/pam_vas3.so` | `/opt/quest/usr/lib/security/pam_vas3.so`
- `/usr/lib/security/sparcv9/pam_vas3.so` |
`/opt/quest/usr/lib/security/sparcv9/pam_vas3.so`

If `/usr` is shared, you need the following symlinks in the global zone pointing to counterpart files in `/opt/quest/lib`:

- /usr/lib/nss_vas4.so.1 | /opt/quest/lib/nss/nss_vas4.so.1

- /usr/lib/security/pam_vas3.so | /opt/quest/usr/lib/security/pam_vas3.so

In such a scenario, you do not need Authentication Services joined to a domain in the global zone in order for sparse zones to work, but the symlinks must exist.

Each zone must have its own unique copy of /etc and /var because Authentication Services stores zone-specific information in those locations. Sharing /etc and /var with the global zone is not a supported configuration.

Contacting us

For sales or other inquiries, visit <https://www.oneidentity.com/company/contact-us.aspx> or call +1-800-306-9329.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to-videos
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product

A

- Access & Privileges by Host report 88
- Access & Privileges by User report 88
- Access & Privileges Reports 88
- Active Directory
 - changing configuration settings 12
- Active Directory configuration
 - determines schema mappings 31
 - moving the configuration data 31
 - purpose defined 31
 - updating 31
 - validates license information 31
- Active Directory schema
 - how uses 71
- Active Directory user account
 - creating 75
- ActiveRoles Server option
 - not available if ActiveRoles Server agent is not installed 29
- AD Group Conflicts report 87
- AD User Conflicts report 83
- AD user identity formats 37
- AD users and groups
 - managing 76
- Add Hosts
 - procedure 39
- Add Hosts dialog
 - add hosts to management console 39
 - profile hosts 40
- All Hosts dialog
 - Join to Active Directory 46

- All Hosts view
 - install software 44
- application configuration
 - creating from command line 58
 - running Authentication Services without 33
- Application Configuration
 - overriding requirement 32
- associate an AD user account with a local Unix user 76
- Authentication Services
 - configure management console 35-36
- Authentication Services Readiness report 81
- automatic profiling
 - disable 41
 - enable 41
- automatic status checking
 - disable 48
 - enable 48

B

- Best Practice:
 - add Unix identity attributes to global catalog 72
 - do not install or run Windows components on AD domain controllers 11
 - index attributes in Active Directory 72
 - install only one management console per environment 63

- license management 56
- use generated UIDs and GIDs 68
- use schema designed for storing Unix data in AD 70

C

- caching of Unix host credentials 40
- change Active Directory configuration settings 31
- Check for AD Readiness 46
- check QAS Agent Status 48
- check QAS status automatically 48
- Commands Executed report 88
- components
 - .msi files 26
 - installing windows components with msixexec.exe 26
- configure
 - user service account 41, 48
- configure for Active Directory 35
- configure for Authentication Services 36
- Console Access and Permissions report 88
- Control Center
 - described 63
 - must be logged in as domain user 63
- credentials
 - accepted user name formats 37
- customize the schema mapping 71

D

- debug logging
 - enabling 70
- disable automatic profiling 41
- Dynamic DNS Update Tool 61

E

- elevated credentials required
 - automatic profiling 41
 - automatic QAS status 48
 - install Authentication Services software 44
 - join host to AD 46
- enable debug logging 70
- enable local user for AD authentication 76

F

- Filter Options 65

G

- global settings modifications 63
- Global Unix Options 68
- group
 - add to console 73
- Group Reports 87

H

- health status of QAS agents
 - checking 47
- host
 - check status 48
 - join to Active Directory 46
- Host Notifications 48
- Host Reports 81
- hosts
 - add to management console 39
 - install software 44
 - profile 40-41

I

- Import Public Key
 - using 40
- Install Software
 - procedure 44
- install.sh
 - about 53
 - interactive mode 61
- installation script
 - using 54
- Installation Script Options 54
- installing
 - Linux agent 109
 - Unix agent 51
- installing components
 - MSI properties 26

J

- join domain in Version 3 Compatibility Mode 33
- Join Host procedure 46
- joining domain
 - determining if joined 59
- joining the AD domain 59-60

K

- known_hosts file
 - importing 39

L

- LDAP attributes
 - mapped to Unix attributes 70

license

- Any VAS 3.x or higher license is valid for 4.x. 10
- installing 10
- updating 36
- updating in the console 10, 56

License

- adding 67

licenses 56

- installing 57

Limitation:

- Microsoft does not support (GPMC) on 64-bit platforms of Windows 11

Linux agent

- installing 109

local account administration 73-74

Local Unix Groups report 87

Local Unix User Conflicts report 83

Local Unix Users report 83

Local Unix Users with AD Logon report 83

Logging

- enabling 69
- setting options 69

login credentials

- accepted formats 37

Login with AD password 77, 79

Logon Policy for AD User report 88

Logon Policy for Unix Host report 88

M

manage local users and groups 76

management console

- add hosts 39

management console requirements 20

mapping users 76
Master /etc/passwd List report 83
migrating Unix account info to AD 81

O

Optimize Schema
 requires AD administrator rights 72

P

patch level requirements 13
performance and scalability 72
Permissions
 required 12
permissions required for full
 functionality 15
Policy Changes report 88
PosixAccount auxiliary class schema
 extension 71
post-install setup 35
PowerShell cmdlets 94
PowerShell modules 92
Preferences
 configuring settings 67
preflight Diagnostic Tool
 About 51
preflight utility
 running 53
Privilege Manager Readiness report 81
Profile Host
 procedure 40
profile hosts automatically 41
PTR updates are rejected 100

Q

QAS Agent Status commands are not
 enabled 47

questusr
 about 41, 48

R

reload configuration settings 114
report
 Access & Privileges by Host 88
 Access & Privileges by User 88
 AD Group Conflicts 87
 AD User Conflicts 83
 Authentication Services Readiness 81
 Commands Executed 88
 Console Access and Permissions 88
 Local Unix Groups 87
 Local Unix User Conflicts 83
 Local Unix Users 83
 Local Unix Users with AD Logon 83
 Logon Policy for AD User 88
 Logon Policy for Unix Host 88
 Master /etc/passwd List 83
 Policy Changes 88
 Privilege Manager Readiness 81
 Product Licenses Usage 92
 Unix-Enabled AD Groups 87
 Unix-Enabled AD Users 83
 Unix Computers in AD 81
 Unix Host Profiles 81
reports
 descriptions 81
 report parameters 81

- run 79
- required AD rights 63
- required rights 31
- Requirements
 - Windows Management Tools 11
- Requirements:
 - encryption types 19
 - network ports 22
 - Permissions 15
 - Windows Permissions 12
- restart services 114
- run reports 79

S

- saving credentials on server 40
- saving host credentials on server 46
- schema
 - configuration 70
 - Custom Unix attributes 70
 - extensions 70
 - LDAP attributes 70
 - templates 70
 - Unix attributes 70
- schema configuration
 - defined 71
- schema extension
 - PosixAccount auxiliary class 71
- schema mappings
 - customizing
 - index and replicate GUI and UID attributes to global catalog 71
- schemaless configuration 58
- set global value 68
- Set supervisor Password dialog 37

- Setup Management Console for Unix dialog 35
- standard Active Directory schema extensions 71
- supervisor account
 - described 37
- System Optimization 105

T

- troubleshooting 99
- Troubleshooting
 - using logs 69
- Troubleshooting:
 - cannot configure console for AD during initial install 35
 - changes made to NSS libraries 114
 - determine if joined to AD 59
 - Diagnostic Tool 51
 - feature not available 46
 - Getting Help from Support 99
 - join to AD is not available 46
 - Long Startup Delays on Windows 100
 - Profile Automatically option is not available 41
 - PTR updates are rejected 61
 - rejected PTR updates 100
 - Resolving DNS Problems 101
 - Resolving Preflight Failures 101
 - Time Synchronization Problems 105
 - Unable to Install or Upgrade 106
 - Unable to Join the Domain 106
 - Unable to Log In 107
 - vastool kinit delay 105
 - vasypd has unsatisfied dependencies 107
- Troubleshooting:QAS status checking not

working 47

U

Unix-enable an Active Directory group 78

Unix-enable an Active Directory user 78

Unix-Enabled AD Groups report 87

Unix-Enabled AD Users report 83

Unix Account Import Wizard

accessing 81

Unix agent

about installing 51

packages 109

Unix Agent Requirements 13

Unix Computers in AD report 81

Unix Group ID (GID) 68

Unix Host Profiles report 81

Unix identity management tasks

performing from Control Center 34

Unix User ID (UID) 68

upgrading VAS 3.5 to QAS 4.x 53

user login name

changes for 4.x 33

User Reports 83

user service account 41, 48

configure 41, 48

users

add to console 74

V

vas_status.sh

customizing 47

vasd

restart 114

vasjoin Script

using 60

vasjoin.sh

using 59

vastool join

using 59

Version 3 Compatibility Mode 33

W

where to set 68